

DB2 Universal Database for OS/390 and z/OS



Command Reference

Version 7

DB2 Universal Database for OS/390 and z/OS



Command Reference

Version 7

Note

Before using this information and the product it supports, be sure to read the general information under “Notices” on page 357.

Second Edition, Softcopy Only (August 2001)

This edition applies to Version 7 of IBM DATABASE 2 Universal Database Server for OS/390 and z/OS (DB2 for OS/390 and z/OS), 5675-DB2, and to any subsequent releases until otherwise indicated in new editions. Make sure you are using the correct edition for the level of the product.

This softcopy version is based on the printed edition of the book and includes the changes indicated in the printed version by vertical bars. Additional changes made to this softcopy version of the book since the hardcopy book was published are indicated by the hash (#) symbol in the left-hand margin. Editorial changes that have no technical significance are not noted.

This and other books in the DB2 for OS/390 and z/OS library are periodically updated with technical changes. These updates are made available to licensees of the product on CD-ROM and on the Web (currently at www.ibm.com/software/data/db2/os390/library.html). Check these resources to ensure that you are using the most current information.

© Copyright International Business Machines Corporation 1983, 2001. All rights reserved.

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

About this book	xv
Who should read this book	xv
Conventions and terminology used in this book	xv
Naming conventions	xv
Product terminology and citations	xviii
How to read the syntax diagrams	xix
Prerequisite and related information	xx
How to send your comments.	xxi
 Summary of changes to this book	 xxiii
 Chapter 1. Privileges, authorization IDs, and the bind process	 1
Privileges and authorization IDs	1
The bind process	1
 Chapter 2. Commands	 3
DB2 command parsing	3
Parts of a DB2 command	3
Characters with special meanings	4
Examples of Keyword Entry	5
Scope of commands	5
Output from DB2 commands	6
Issuing commands from IFI.	6
DSN subcommand parsing	7
Abbreviations	7
Description of commands	7
The DSN command and its subcommands	7
DB2 commands	8
IMS commands.	10
CICS attachment facility commands	10
MVS IRLM commands	11
TSO CLISTS	11
-ALTER BUFFERPOOL (DB2)	12
Environment	12
Authorization.	12
Syntax	12
Option descriptions	12
Usage notes	16
Examples	18
-ALTER GROUPBUFFERPOOL (DB2)	19
Environment	19
Authorization.	19
Syntax	19
Option descriptions	19
Usage notes	21
Examples	22
-ALTER UTILITY (DB2)	23
Environment	23
Authorization.	23
Syntax	23
Option descriptions	23
Usage note	25
Example	25

-ARCHIVE LOG (DB2)	26
Environment	26
Authorization.	26
Syntax	27
Option descriptions	27
Usage notes	29
Examples	30
BIND PACKAGE (DSN).	32
Environment	32
Authorization.	32
Syntax	35
Option descriptions	36
Examples	36
BIND PLAN (DSN)	38
Environment	38
Authorization.	38
Syntax	40
Option descriptions	41
Examples	41
Options of BIND and REBIND for PLAN, PACKAGE, and TRIGGER PACKAGE	44
-CANCEL THREAD (DB2).	77
Environment	77
Authorization.	77
Syntax	77
Option descriptions	77
Usage notes	78
Examples	81
/CHANGE (IMS)	82
Environment	82
Authorization.	82
Syntax	82
Option descriptions	82
Usage note	82
Examples	83
DCLGEN (DECLARATIONS GENERATOR) (DSN).	84
Environment	84
Authorization.	84
Syntax	84
Option descriptions	85
Usage notes	88
Examples	90
/DISPLAY (IMS)	92
Environment	92
Authorization.	92
Syntax	92
Option descriptions	92
Output	93
Example	94
-DISPLAY ARCHIVE (DB2)	95
Environment	95
Authorization.	95
Syntax	95
Usage note	95
Example	95
-DISPLAY BUFFERPOOL (DB2)	97
Environment	97

|
|
|
|
|
|
|

Authorization	97
Syntax	97
Option descriptions	97
Output	99
Examples	103
-DISPLAY DATABASE (DB2)	106
Environment	106
Authorization	106
Syntax	107
Option descriptions	108
Usage notes	112
Output	113
Examples	115
-DISPLAY DDF (DB2)	119
Environment	119
Authorization	119
Syntax	119
Option descriptions	119
Output	119
Examples	120
-DISPLAY FUNCTION SPECIFIC (DB2)	121
Environment	121
Authorization	121
Syntax	121
Option descriptions	121
Usage notes	122
Output	122
Examples	123
-DISPLAY GROUP (DB2)	125
Environment	125
Authorization	125
Syntax	125
Option descriptions	125
Usage notes	125
Output	126
Examples	127
-DISPLAY GROUPBUFFERPOOL (DB2)	129
Environment	129
Authorization	129
Syntax	130
Option descriptions	130
Output	131
Examples	136
-DISPLAY LOCATION (DB2)	143
Environment	143
Authorization	143
Syntax	143
Option descriptions	143
Output	144
Examples	144
-DISPLAY LOG (DB2)	146
Environment	146
Authorization	146
Syntax	146
Usage notes	146
Examples	146

-DISPLAY PROCEDURE (DB2)	148
Environment	148
Authorization	148
Syntax	148
Option descriptions	148
Output	149
Examples	150
-DISPLAY RLIMIT (DB2)	152
Environment	152
Authorization	152
Syntax	152
Example	152
-DISPLAY THREAD (DB2)	153
Environment	153
Authorization	153
Syntax	154
Option descriptions	154
Usage notes	157
Output	158
Examples	160
-DISPLAY TRACE (DB2)	165
Environment	165
Authorization	165
Syntax	166
Option descriptions	166
Examples	169
-DISPLAY UTILITY (DB2)	171
Environment	171
Authorization	171
Syntax	171
Option descriptions	171
Usage notes	172
Output	172
Examples	173
DSN (TSO)	175
Environment	175
Authorization	175
Syntax	175
Option descriptions	175
Usage notes	176
Examples	177
DSNC (CICS attachment facility)	178
Environment	178
Authorization	178
Syntax	178
Option descriptions	178
Usage note	178
Example	178
DSNC DISCONNECT (CICS attachment facility)	179
Environment	179
Authorization	179
Syntax	179
Option description	179
Usage notes	179
Example	179
DSNC DISPLAY (CICS attachment facility)	180

Environment	180
Authorization	180
Syntax	180
Option descriptions	180
Usage notes	181
Output	181
Examples	182
DSNC MODIFY (CICS attachment facility)	184
Environment	184
Authorization	184
Syntax	184
Option descriptions	184
Usage notes	185
Example	185
DSNC STOP (CICS attachment facility)	186
Environment	186
Authorization	186
Syntax	186
Option descriptions	186
Usage notes	186
Example	186
DSNC STRT (CICS attachment facility)	187
Environment	187
Authorization	187
Syntax	187
Option descriptions	187
Usage note	187
Examples	187
DSNH (TSO CLIST)	189
Environment	189
Authorization	189
Syntax	190
Summary of DSNH CLIST parameters	190
General parameter descriptions	193
DSNH/DSN subcommand summary	207
DSNH CLIST/BIND PLAN subcommand comparison	207
DSNH CLIST/BIND PACKAGE subcommand comparison	210
Usage notes	213
Examples	214
END (DSN)	217
Environment	217
Authorization	217
Syntax	217
Usage note	217
Example	217
FREE PACKAGE (DSN)	218
Environment	218
Authorization	218
Syntax	218
Option descriptions	219
Usage notes	219
Examples	220
FREE PLAN (DSN)	221
Environment	221
Authorization	221
Syntax	221

Option descriptions	221
Usage notes	222
Example	222
MODIFY irlImproc,ABEND (MVS IRLM)	223
Environment	223
Authorization	223
Syntax	223
Option descriptions	223
Usage notes	223
Example	223
MODIFY irlImproc,DIAG (MVS IRLM)	225
Environment	225
Authorization	225
Syntax	225
Option descriptions	225
Usage note	226
Example	226
MODIFY irlImproc,PURGE (MVS IRLM)	227
Environment	227
Authorization	227
Syntax	227
Option descriptions	227
Usage notes	227
Example	227
MODIFY irlImproc,SET (MVS IRLM)	228
Environment	228
Authorization	228
Syntax	228
Option descriptions	228
Usage notes	229
Examples	230
MODIFY irlImproc,STATUS (MVS IRLM)	232
Environment	232
Authorization	232
Syntax	232
Option descriptions	232
Usage notes	233
Examples	233
-MODIFY TRACE (DB2)	238
Environment	238
Authorization	238
Syntax	238
Option descriptions	238
Example	239
REBIND PACKAGE (DSN)	240
Environment	240
Authorization	240
Syntax	242
Option descriptions	243
Usage note	243
Example	243
REBIND PLAN (DSN)	244
Environment	244
Authorization	244
Syntax	246
Option descriptions	247

Usage note	247
Example	247
REBIND TRIGGER PACKAGE (DSN)	248
Environment	248
Authorization	248
Syntax	249
Option descriptions	249
Usage notes	250
Output	250
Example	250
-RECOVER BSDS (DB2).	251
Environment	251
Authorization	251
Syntax	251
Usage note	251
Example	251
-RECOVER INDOUBT (DB2)	252
Environment	252
Authorization	252
Syntax	252
Option descriptions	252
Usage note	254
Examples	254
-RECOVER POSTPONED (DB2).	255
Environment	255
Authorization	255
Syntax	255
Option descriptions	255
Usage note	255
Output	255
Example	256
-RESET GENERICLU (DB2)	257
Environment	257
Authorization	257
Syntax	257
Option descriptions	257
Usage notes	257
Examples	258
-RESET INDOUBT (DB2)	259
Environment	259
Authorization	259
Syntax	260
Option descriptions	260
Output	261
Usage notes	261
RUN (DSN).	262
Environment	262
Authorization	262
Syntax	262
Option descriptions	262
Usage note	264
Examples	264
-SET ARCHIVE (DB2).	265
Environment	265
Authorization	265
Syntax	265

|
|
|
|
|
|
|

Option descriptions	265
Usage notes	266
Output	266
Examples	266
-SET SYSPARM (DB2)	268
Environment	268
Authorization	268
Syntax	268
Option descriptions	268
Usage notes	268
Examples	268
-SET LOG (DB2).	270
Environment	270
Authorization	270
Syntax	270
Option descriptions	270
Usage notes	271
Examples	271
SPUFI (DSN)	273
Environment	273
Authorization	273
Syntax	273
Usage notes	273
/SSR (IMS)	274
Environment	274
Authorization	274
Syntax	274
Option description	274
Usage note	274
/START (IMS)	275
Environment	275
Authorization	275
Syntax	275
Option descriptions	275
Usage note	275
-START DATABASE (DB2)	276
Environment	276
Authorization	276
Syntax	277
Option descriptions	277
Usage notes	280
Examples	282
-START DB2 (DB2).	283
Environment	283
Authorization	283
Syntax	283
Option descriptions	283
Usage notes	284
Examples	285
-START DDF (DB2).	286
Environment	286
Authorization	286
Syntax	286
Usage note	286
Example	286
-START FUNCTION SPECIFIC (DB2)	287

Environment	287
Authorization	287
Syntax	287
Option descriptions	288
Usage notes	288
Examples	289
START irlmproc (MVS IRLM)	290
Environment	290
Authorization	290
Syntax	290
Option descriptions	290
Example	293
-START PROCEDURE (DB2)	294
Environment	294
Authorization	294
Syntax	295
Option descriptions	295
Usage notes	295
Examples	296
-START RLIMIT (DB2)	297
Environment	297
Authorization	297
Syntax	297
Option description	297
Example	298
-START TRACE (DB2)	299
Environment	299
Authorization	299
Syntax	300
Option descriptions	300
The destination block	301
The constraint block	302
Usage notes	307
Examples	308
/STOP (IMS)	309
Environment	309
Authorization	309
Syntax	309
Option descriptions	309
Usage note	309
-STOP DATABASE (DB2)	310
Environment	310
Authorization	310
Syntax	311
Option descriptions	311
Usage notes	313
Examples	315
-STOP DB2 (DB2)	316
Environment	316
Authorization	316
Syntax	316
Option descriptions	316
Usage notes	317
Example	317
-STOP DDF (DB2)	318
Environment	318

Authorization	318
Syntax	318
Option descriptions	318
Usage notes	319
Examples	320
-STOP FUNCTION SPECIFIC	321
Environment	321
Authorization	321
Syntax	321
Option descriptions	322
Usage notes	322
Examples	323
STOP irImproc (MVS IRLM).	324
Environment	324
Authorization	324
Syntax	324
Option description	324
Usage note	324
Example	324
-STOP PROCEDURE (DB2)	326
Environment	326
Authorization	326
Syntax	327
Option descriptions	327
Usage notes	328
Examples	328
-STOP RLIMIT (DB2)	329
Environment	329
Authorization	329
Syntax	329
Example	329
-STOP TRACE (DB2)	330
Environment	330
Authorization	330
Syntax	331
Option descriptions	331
Usage notes	334
Examples	334
-TERM UTILITY (DB2)	335
Environment	335
Authorization	335
Syntax	335
Option descriptions	335
Usage notes	336
Examples	337
/TRACE (IMS).	338
Environment	338
Authorization	338
Syntax	338
Option descriptions	338
Examples	338
TRACE CT (MVS IRLM)	340
Environment	340
Authorization	340
Syntax	340
Option descriptions	340

	Usage notes	341
I	Appendix A. Directory of subsystem parameters	343
I	Editing the subsystem parameters and DSNHDECP values	343
I	Directory of subsystem parameters and DSNHDECP values.	343
	Appendix B. How to use the DB2 library	349
	Appendix C. How to obtain DB2 information	351
	DB2 on the Web	351
	DB2 publications	351
	BookManager format	351
	PDF format.	351
#	CD-ROMs and DVD	351
	DB2 education	352
	How to order the DB2 library	352
	Subscription through the Publication Notification System (PNS)	352
	Appendix D. Summary of changes to DB2 for OS/390 and z/OS Version 7	353
	Enhancements for managing data	353
	Enhancements for reliability, scalability, and availability.	353
	Easier development and integration of e-business applications	354
	Improved connectivity	355
	Features of DB2 for OS/390 and z/OS.	356
	Migration considerations	356
	Notices	357
	Programming interface information	358
	Trademarks.	359
	Glossary	361
	Bibliography	379
	Index	385

About this book

This is a reference book that lists numerous commands that system administrators, database administrators, and application programmers use. The commands are in alphabetical order for quick retrieval.

Important

In this version of DB2® for OS/390® and z/OS, some utility functions are available as optional products. You must separately order and purchase a license to such utilities, and discussion of those utility functions in this publication is not intended to otherwise imply that you have a license to them.

Who should read this book

This book presents reference information for people involved in system administration, database administration, and operation. It presents detailed information on commands, including syntax, option descriptions, and examples for each command.

Conventions and terminology used in this book

Naming conventions that are unique to DB2 commands are discussed in “Naming conventions”. Terminology is discussed in “Product terminology and citations” on page xviii.

Naming conventions

When a parameter refers to an object created by SQL statements (for example, tables, table spaces, and indexes), SQL syntactical naming conventions are followed.

This section describes naming conventions unique to commands. Characters are classified as *letters*, *digits*, or *special characters*.

- A *letter* is any one of the uppercase characters A through Z (plus the three characters reserved as alphabetic extenders for national languages, #, @, and \$ in the United States).
- A *digit* is any one of the characters 0 through 9.
- A *special character* is any character other than a letter or a digit.

See Chapter 2 of *DB2 SQL Reference* for an additional explanation of long identifiers, short identifiers, and location identifiers.

authorization-id

A short identifier of 1 to 8 letters, digits, or the underscore that identifies a set of privileges. An authorization ID must begin with a letter.

collection-id

An SQL long identifier of 1 to 18 letters, digits, or the underscore that identifies a collection of packages; therefore, a collection ID is a qualifier for a package ID. A collection ID must begin with a letter.

A collection ID should not begin with DSN; this can sometimes conflict with DB2-provided collection IDs. If a collection ID beginning with DSN is specified, DB2 issues a warning message.

connection-name

An identifier of 1 to 8 characters that identifies an address space connection to DB2. A connection identifier is one of the following:

- For DSN processes running in TSO foreground, the connection name “TSO” is used.
- For DSN processes running in TSO batch, the connection name BATCH is used.
- For the call attachment facility (CAF), the connection name DB2CALL is used.
- For the Recoverable Resource Manager Services attachment facility (RRSAF), the connection name RRSAF is used.
- For IMS and CICS processes, the connection name is the system identification name.

See Part 4 (Volume 1) of *DB2 Administration Guide* for more information about connection names.

correlation-id

An identifier of 1 to 12 characters that identifies a process within an address space connection. A correlation ID must begin with a letter.

A correlation ID can be one of the following:

- For DSN processes running in TSO foreground, the correlation ID is the TSO logon identifier.
- For DSN processes running in TSO batch, the correlation ID is the job name.
- For CAF processes, the correlation ID is the TSO logon identifier.
- For RRSAF processes, the correlation ID is the value specified during signon.
- For IMS processes, the correlation ID is *pst#.psbname*.
- For CICS processes, the correlation ID is *identifier.thread_number.transaction_identifier*.

See Part 4 (Volume 1) of *DB2 Administration Guide* for more information about correlation IDs.

data-set-name

An identifier of 1 to 44 characters that identifies a data set.

dbrm-member-name

An identifier of 1 to 8 letters or digits that identifies a member of a partitioned data set. (MVS requires this naming convention.)

A DBRM member name should not begin with DSN; this can sometimes conflict with DB2-provided DBRM member names. If a DBRM member name beginning with DSN is specified, DB2 issues a warning message.

dbrm-pds-name

An identifier of 1 to 44 characters that identifies a partitioned data set.

ddname

An identifier of 1 to 8 characters that designates the name of a DD statement.

hexadecimal-constant

A sequence of digits or any of the letters from A to F (uppercase or lowercase).

hexadecimal-string

An X followed by a sequence of characters that begins and ends with an apostrophe. The characters between the string delimiters must be a hexadecimal number.

ip address (or Internet address)

A 4 byte value that uniquely identifies a TCP/IP host within the TCP/IP network. IP addresses are usually displayed in a format called *dotted decimal*, where each byte of the IP address is displayed in decimal format with a period delimiting each number.

location-name

A location identifier of 1 to 16 letters (but excluding the alphabetic extenders), digits or the underscore that identifies an instance of a data base management system. A location name must begin with a letter.

luname

An SQL short identifier of 1 to 8 characters that identifies a logical unit name. An luname must begin with a letter.

luwid

A fully qualified LU network name and an LUW instance number.

The LU network name consists of an optional 8 character network ID, a period, and an 8 character network LU name. If you indicate no network ID, no period is required. The LUW instance number consists of 12 hex characters that uniquely identify the unit of work.

member-name

An identifier of 1 to 8 characters that identifies either a member of a partitioned data set (MVS requires this naming convention) or a member of a data sharing group.

A name for a member of a partitioned data set should not begin with DSN; this can sometimes conflict with DB2-provided member names. If a name beginning with DSN is specified, DB2 issues a warning message.

package-id

An SQL short identifier of 1 to 8 letters, digits, or underscores that identifies a package. For packages created under DB2, a package ID is the name of the program whose precompilation produced the package's DBRM. A package ID must begin with a letter. (MVS requires this naming convention.)

A package ID should not begin with DSN; this can sometimes conflict with DB2-provided package IDs. If a package ID beginning with DSN is specified, DB2 issues a warning message.

package-name

A name given to the object created during the bind process of a single package. A package name consists of a location name, a collection ID, and a package ID separated by periods. An additional attribute, a version ID, allows for multiple versions of a package to have the same name.

plan-name

An SQL short identifier of 1 to 8 letters, digits or underscores that identifies an application plan. A plan name must begin with a letter.

A plan name should not begin with DSN; this can sometimes conflict with DB2-provided plan names. If a plan name beginning with DSN is specified, DB2 issues a warning message.

qualifier-name

An SQL short identifier of 1 to 8 letters, digits, or the underscore that identifies the implicit qualifier for unqualified table names, views, indexes, and aliases.

string

A sequence of characters that begins and ends with an apostrophe.

subsystem-name

An identifier that specifies the DB2 subsystem as it is known to MVS.

table-name

A qualified or unqualified name that designates a table. A table name can contain one or two parts, depending upon its qualification. The first part is the authorization ID that designates the owner of the table; the second part is an SQL long identifier. A period must separate each of the parts.

table-space-name

A short identifier that designates a table space of an identified database. If a database is not identified, a table space name specifies a table space of database DSNDB04.

utility-id

An identifier of 1 to 16 characters that uniquely identifies a utility process within DB2. A utility ID must begin with a letter, and the identifier can contain periods.

version-id

An SQL identifier of 1 to 64 lowercase alphabetic letters, uppercase alphabetic letters, digits, underscores, at signs (@), number signs (#), dollar signs (\$), dashes and periods that is assigned to a package when the package is created. The version ID that is assigned is taken from the version ID associated with the program being bound. Version IDs are specified for programs as a parameter of the DB2 precompile.

Product terminology and citations

In this book, DB2 Universal Database™ Server for OS/390 and z/OS is referred to as "DB2 for OS/390 and z/OS." In cases where the context makes the meaning clear, DB2 for OS/390 and z/OS is referred to as "DB2." When this book refers to other books in this library, a short title is used. (For example, "See *DB2 SQL Reference*" is a citation to *IBM® DATABASE 2™ Universal Database Server for OS/390 and z/OS SQL Reference*.)

When referring to a DB2 product other than DB2 for OS/390 and z/OS, this book uses the product's full name to avoid ambiguity.

The following terms are used as indicated:

DB2 Represents either the DB2 licensed program or a particular DB2 subsystem.

C and C language

Represent the C programming language.

CICS® Represents CICS/ESA® and CICS Transaction Server for OS/390.

IMS™ Represents IMS or IMS/ESA®.

MVS Represents the MVS element of OS/390.

OS/390

Represents the OS/390 or z/OS operating system.

RACF®

Represents the functions that are provided by the RACF component of the SecureWay® Security Server for OS/390 or by the RACF component of the OS/390 Security Server.

How to read the syntax diagrams

The following rules apply to the syntax diagrams used in this book:

- Read the syntax diagrams from left to right, from top to bottom, following the path of the line.

The ► symbol indicates the beginning of a statement.

The → symbol indicates that the statement syntax is continued on the next line.


The ► symbol indicates that a statement is continued from the previous line.

The → symbol indicates the end of a statement.

- Required items appear on the horizontal line (the main path).




- Optional items appear below the main path.




If an optional item appears above the main path, that item has no effect on the execution of the statement and is used only for readability.




- If you can choose from two or more items, they appear vertically, in a stack. If you *must* choose one of the items, one item of the stack appears on the main path.




If choosing one of the items is optional, the entire stack appears below the main path.




If one of the items is the default, it appears above the main path and the remaining choices are shown below.



- An arrow returning to the left, above the main line, indicates an item that can be repeated.



If the repeat arrow contains a comma, you must separate repeated items with a comma.



A repeat arrow above a stack indicates that you can repeat the items in the stack.

- Keywords appear in uppercase (for example, FROM). They must be spelled exactly as shown. Variables appear in all lowercase letters (for example, *column-name*). They represent user-supplied names or values.
- If punctuation marks, parentheses, arithmetic operators, or other such symbols are shown, you must enter them as part of the syntax.

Prerequisite and related information

This book is intended to serve as a reference for people who understand system administration, database administration, or application programming in the DB2 environment. You should have some knowledge of:

- CICS, IMS, or TSO
- MVS Job Control Language (JCL)
- Structured Query Language (SQL)

How to send your comments

Your feedback helps IBM to provide quality information. Please send any comments that you have about this book or other DB2 for OS/390 and z/OS documentation.

You can use any of the following methods to provide comments:

- Send your comments by e-mail to db2pubs@vnet.ibm.com and include the name of the product, the version number of the product, and the number of the book. If you are commenting on specific text, please list the location of the text (for example, a chapter and section title, page number, or a help topic title).
- Send your comments from the Web. Visit the Web site at:

<http://www.ibm.com/software/db2os390>

The Web site has a feedback page that you can use to send comments.

- Complete the readers' comment form at the back of the book and return it by mail, by fax (800-426-7773 for the United States and Canada), or by giving it to an IBM representative.

Summary of changes to this book

The principal changes to this book are as follows:

- Chapter 2. Commands introduces the following new commands:
 - “-SET SYSPARM (DB2)” on page 268
 - “-DISPLAY DDF (DB2)” on page 119
 - “MODIFY irlmproc,PURGE (MVS IRLM)” on page 227.
- New options are available for the following commands:
 - “-CANCEL THREAD (DB2)” on page 77
 - NOBACKOUT
 - “-DISPLAY THREAD (DB2)” on page 153
 - RRSURID
 - “DSN (TSO)” on page 175
 - GROUP
 - “MODIFY irlmproc,DIAG (MVS IRLM)” on page 225
 - PLOCK
 - ALL
 - NONE
 - “-RECOVER POSTPONED (DB2)” on page 255
 - CANCEL
 - “-SET LOG (DB2)” on page 270
 - SUSPEND
 - RESUME
 - CHKTIME
 - “-START DB2 (DB2)” on page 283
 - LIGHT

For information about the changes to the Version 7 product, see “Appendix D. Summary of changes to DB2 for OS/390 and z/OS Version 7” on page 353.

Chapter 1. Privileges, authorization IDs, and the bind process

This chapter contains information about the privileges and authorization IDs that are required to issue various commands and a summary of the bind process.

Privileges and authorization IDs

The issuer of a command can be an individual user. It can also be a program running in batch mode or an IMS or CICS transaction. We use the term *process* to represent any or all of those.

A process is represented to DB2 by a set of identifiers (IDs). What the process can do with DB2 is determined by *privileges* and *authorities* that can be held by its identifiers. We use “*the privilege set of a process*” to mean the entire set of privileges and authorities that can be used by the process in a specific situation.

There are three types of identifiers: primary authorization IDs, secondary authorization IDs, and SQL IDs.

- Generally it is the primary authorization ID that identifies a specific process. For example, in the process initiated through the TSO attachment facility, the primary authorization ID is identical to the TSO logon ID. A trace record identifies the process by that ID.
- Secondary authorization IDs, which are optional, can hold additional privileges available to the process. A secondary authorization ID is often a Resource Access Control Facility group ID. For example, a process can belong to a RACF® group that holds the LOAD privilege on a particular database. Any member of the group can run the LOAD utility to load table spaces in the database.
DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.
- An SQL authorization ID (SQL ID) holds the privileges exercised when issuing certain dynamic SQL statements. This ID plays little part in the commands described in this book.

Within DB2, a process can be represented by a primary authorization ID and possibly one or more secondary IDs. For detailed instructions on how to associate a process with one or more IDs, and how to grant privileges to those IDs, see Part 3 (Volume 1) of *DB2 Administration Guide*.

A privilege or authority is granted to, or revoked from, an identifier by executing an SQL GRANT or REVOKE statement. For the complete syntax of those statements, see Chapter 5 of *DB2 SQL Reference*.

The bind process

The bind process establishes a relationship between an application program and its relational data. This step is necessary before you can execute your program. Currently, DB2 allows you two basic ways of binding a program: to a package, or directly to an application plan. If your application uses DRDA access to distribute data, then you must use packages.

During the precompilation process, the DB2 precompiler produces both modified source code and a database request module (DBRM) for each application program.

The modified source code must be compiled and link-edited before the application program can be run. DBRMs must be bound to a plan or package.

When determining the maximum size of a plan, you must consider several physical limitations, including the time required to bind the plan, the size of the EDM pool, and fragmentation. There are no restrictions to the number of DBRMs that can be included in a plan. However, packages provide a more flexible method for handling large numbers of DBRMs within a plan. As a general rule, it is suggested that the EDM pool be at least 10 times the size of the largest DBD or plan, whichever is greater. For further information, see Part 2 of *DB2 Installation Guide*.

The BIND PACKAGE subcommand allows you to bind DBRMs individually. It gives you the ability to test different versions of an application without extensive rebinding. Package binding is also the only method for binding applications at remote sites.

Even when they are bound into packages, all programs must be designated in an application plan. BIND PLAN establishes the relationship between DB2 and all DBRMs or packages in that plan. Plans can specify explicitly named DBRMs, packages, collections of packages, or a combination of these elements. The plan contains information about the designated DBRMs or packages and about the data the application program intends to use. It is stored in the DB2 catalog.

In addition to building packages and plans, the bind process:

- **Validates the SQL statements using the DB2 catalog.** During the bind process, DB2 checks your SQL statements for valid table, view, and column names. Because the bind process occurs as a separate step before program execution, errors are detected and can be corrected before the program is executed.
- **Verifies that the process binding the program is authorized to perform the data accessing operations requested by your program's SQL statements.** When you issue BIND, you can specify an authorization ID as the owner of the plan or package. The owner can be any one of the authorization IDs of the process performing the bind. The bind process determines whether the owner of the plan or package is authorized to access the data the program requests.
- **Selects the access paths needed to access the DB2 data your program wants to process.** In selecting an access path, DB2 considers indexes, table sizes, and other factors. DB2 considers all indexes available to access the data and decides which ones (if any) to use when selecting a path to the data.

BIND PLAN and BIND PACKAGE can be accomplished using DB2I panels, the DSNH CLIST, or the DSN subcommands BIND PLAN and BIND PACKAGE. For a detailed explanation of binding with DSNH CLIST, see Chapter 2. Commands. A complete description of the bind process can be found in Part 5 of *DB2 Application Programming and SQL Guide*. Further information on BIND can be found in "BIND PACKAGE (DSN)" on page 32 and in "BIND PLAN (DSN)" on page 38. Information about specific options for BIND PLAN and BIND PACKAGE can be found in "Options of BIND and REBIND for PLAN, PACKAGE, and TRIGGER PACKAGE" on page 44.


Chapter 2. Commands

This chapter contains syntax diagrams, semantic descriptions, rules, and usage examples of commands, organized alphabetically by command name.

The tables at the beginning of this chapter summarize the commands that follow. Each table lists commands of one type, describes their functions, and refers to the page on which a complete description begins.

DB2 command parsing

DB2 commands follow a pattern like this:



Parts of a DB2 command

The parts of a command are:

- *Recognition character*. It is shown as a hyphen throughout this book, with the following exceptions:

- If the command is issued from an MVS console, the recognition character must be the *command prefix*.

In DB2 Version 7, the command prefix can be up to eight characters. The default is '-DSN1'. However, the majority of examples in this book assume that the command prefix has been defined as a hyphen (-). Examples involving members of a data sharing group demonstrate the use of multi-character command prefixes, such as -DB1G.

Inserting a space between the command prefix and the command is optional. For example, you can use either one of the following formats:

```
-DB1GDIS THREAD(*)
-DB1G DIS THREAD(*)
```

Using a space makes it easier for users to identify the command, especially when the command prefix has multiple characters.

The command prefix can be defined at installation time. For more information, see Part 2 of *DB2 Installation Guide*.

- If the command is issued from an IMS terminal, the recognition character must be the command recognition character (CRC). The command recognition character is defined in the IMS SSM PROCLIB member. For more information, see *IMS Customization Guide*.
 - If the command is issued from a CICS terminal or under the DSN command processor, the recognition character must be a hyphen.
- *Command name*. Command names have abbreviations, which are provided in the command descriptions in this chapter.

- *Operands*. These are combinations of keywords and parameters that can be specified for the command.
 - *Keywords* can be required or optional. They must be entered exactly as shown in the descriptions of the commands.
 - A keyword can have zero or more *parameters*. A parameter list, if present, must be enclosed in parentheses.
 - *Separators*. These can be one or more blanks or commas. An open parenthesis marks the beginning of a parameter list; no separator is needed. Optionally, an equal sign can be used to separate a single parameter from its keyword without using parentheses.

Characters with special meanings

The following characters have special meaning for the syntax of DB2 commands:

- A blank is a separator.
Multiple blanks are equivalent to a single blank, except in strings enclosed between apostrophes.
- ,
- '
An apostrophe is the usual SQL string constant delimiter, and marks the beginning or end of a string constant in SQL. (In COBOL programs only, the QUOTESQL precompiler option allows you to choose the quotation mark as the SQL string delimiter; the apostrophe is then the SQL escape character.)

Letters not in string constants are changed to uppercase. Two successive apostrophes in a string constant are changed to one apostrophe. Blanks, commas, equal signs, and parentheses in string constants are treated as literal characters, and are not recognized as separators.

There is an exception to the rule about changing letters to uppercase. If the CODED CHARACTER SET install option is set to 930 or 5026 during installation, the letters are not folded to uppercase, whether in an SQL string constant or not.
- "
A quotation mark is the SQL escape character, and marks the beginning or end of an SQL delimited identifier. (In COBOL programs only, the QUOTESQL precompiler option allows you to choose the apostrophe as the SQL escape character; the double quotation mark is then the SQL string delimiter.)

Within a string delimited by quotation marks, two successive quotation marks are changed to one. Other rules are the same as for SQL string constants.
- =
An equal sign separates a single parameter from a keyword. Thus, an equal sign is used as a separator for keywords that have only one parameter. An equal sign can be used for keywords with multiple parameters when only one member of the parameter list is specified.
- (
An open parenthesis marks the beginning of a parameter list.
-)
A close parenthesis marks the end of a parameter list.
- :
A colon means an inclusive range. For example, (A:D) means the same as (A,B,C,D); (1:5) means (1,2,3,4,5). The colon can be used this way only in commands where this operation is specifically permitted.
- *
An asterisk means any of the following usages:

***** A single asterisk as a keyword_value indicates all. For example:
-DISPLAY UTILITY ()*

***keyword_value**

An asterisk as the first character of a keyword_value indicates that a match for the value will be satisfied when all characters following the * are the same. For example: (*BCD)

keyword*value

An intermediate asterisk indicates that a match for the value will be satisfied when all characters preceding and all characters following the asterisk are the same. For example: (ABC*EFG)

keyword_value*

An asterisk as the final character of a keyword_value indicates that a match will for the value will be satisfied when all characters preceding the asterisk are the same. For example: (ABC*)

keyword*_value

Asterisks used as the first, intermediate and final characters in a string are also valid. For example: (*BCD*FGH*)

For example, DISPLAY UTILITY (*) displays the status of all utilities;
DISPLAY UTILITY (R2*) displays the status of all utilities whose identifiers begin with R2.

The asterisk pattern-matching character is available to all DB2 commands, but not all DB2 commands support an asterisk. The asterisk can be used this way only in commands in which the operation is specifically permitted.

NO (two-character string) negates the keyword that follows.

A negated keyword means the opposite of the keyword itself, and is often used to override a keyword default. In keywords that have no opposite meaning, the initial characters NO can be merely part of the keyword itself; for example, in NODE.

Examples of Keyword Entry

The following are general examples of valid keywords and parameters:

- MODE (FORCE)
- MODE=FORCE
- MODE (NOFORCE) (keyword negation)
- MODE=NOFORCE (keyword negation)
- DATABASE(name1 name2 . . . name*n*) ACCESS(RO)
- SPACENAM (name1,name2) ACCESS(RO)
- ACCESS (RO),SPACENAM=name
- Combinations of the above

Do not use more than one parameter after an equal sign, or an error condition will occur.

Scope of commands

In a data sharing environment, the *scope* of a command is the breadth of its impact:

Member

Many commands used in a data sharing environment have *member* scope because they affect only the DB2 for which they are issued. For example, a

DISPLAY THREAD command displays only those threads that exist for the member identified by the command prefix.

Group Other commands have *group* scope because they affect an object in such a way that affects all members of the group. For example, a STOP DATABASE command issued from any member of the group stops that database for all members of the group.

The commands that have group scope are:

ALTER GROUPBUFFERPOOL (DB2)	FREE PACKAGE (DSN)
BIND PACKAGE (DSN)	FREE PLAN (DSN)
BIND PLAN (DSN)	MODIFY irlImproc,DIAG,DELAY (MVS IRLM)
DCLGEN (DSN)	REBIND PACKAGE (DSN)
DISPLAY DATABASE (DB2)	REBIND PLAN (DSN)
DISPLAY GROUP (DB2)	REBIND TRIGGER PACKAGE (DSN)
DISPLAY GROUPBUFFERPOOL (DB2)	START DATABASE (DB2)
DISPLAY UTILITY (DB2)	STOP DATABASE (DB2)

These commands have either group or member scope, depending on what option you specify with them:

ARCHIVE LOG (DB2)

MODIFY irlImproc,STATUS (MVS IRLM)

TERM UTILITY (DB2)

All other commands have member scope. The description of each command includes its scope. For more details on data sharing, see *DB2 Data Sharing: Planning and Administration*.

Output from DB2 commands

The amount of output that you receive from a DB2 command is always less than 256 KB. The following factors determine the maximum amount of output you can receive:

- The amount of storage available to your DB2 subsystem or to an individual command.
- The environment from which you issue the DB2 command.
For example, if you issue a DB2 command from an IMS console, you can receive no more than 32 KB of output.
- For DISPLAY DATABASE, the value of the LIMIT parameter.
- For DISPLAY THREAD, the number of lines of output.
DISPLAY THREAD does not display more than 254 lines of output.

Issuing commands from IFI

Consider using IFI to let your programs issue commands to DB2. This method returns information about the success or failure of the command to your program. If the command issues a non-zero return code, the information returned to your program includes diagnostic information about the command processed.

For more information about submitting DB2 commands through IFI, see Appendix E (Volume 2) of DB2 Administration Guide.

DSN subcommand parsing

The parsing of DSN subcommands conforms to standard TSO command parsing conventions. For information about TSO command parsing, see *OS/390 TSO/E Programming Services*.

To continue a subcommand on the next line while using the DSN processor, type either a hyphen (-) or a plus sign (+) at the end of the current line. If you use a plus sign, precede it by at least one blank character to prevent the concatenation of character strings from line to line. Using a plus sign causes TSO/E to delete leading delimiters (blanks, commas, tabs, and comments) on the continuation line, and will reduce the overall size of the command.

Abbreviations

The names of the DSN command and its subcommands cannot be abbreviated. For compatibility with prior releases of DB2, abbreviations for some keywords are allowed. **Recommendation:** To avoid potential problems, avoid abbreviating keywords.

Description of commands

The commands are divided into these categories:

- The DSN command and its subcommands
- DB2 commands
- IMS commands
- CICS attachment facility commands
- MVS IRLM commands
- TSO CLISTS

The DSN command and its subcommands

Environment: DSN is the DB2 command processor and executes as a TSO command processor. All of its subcommands, except SPUFI, run under DSN in either the foreground or background, and all, except END, also run under DB2 Interactive (DB2I). SPUFI runs only in the foreground under ISPF.

Table 1. DSN command and subcommands

DSN command or Subcommand	Function	Refer to page
BIND	Builds an application package or plan	32, 38
DB2 commands	Execute a DB2 command	Table 2 on page 8
DCLGEN	(DECLARATIONS GENERATOR) Produces declarations for tables or views	84
DSN	Starts a DSN session	175
END	Ends the DSN session	217
FREE	Deletes an application package or plan	218, 221
REBIND	Updates an application package or plan	240, 244

Table 1. DSN command and subcommands (continued)

DSN command or Subcommand	Function	Refer to page
REBIND TRIGGER PACKAGE	Updates an application trigger package	248
RUN	Executes an application program	262
SPUFI	Executes the SQL Processor Using File Input	273
*	A comment	175

DB2 commands

Environment: The command START DB2 can be issued only from an MVS console. All other DB2 commands can be issued from:

- An MVS console or MVS application program
- A DSN session
- A DB2I panel
- An IMS terminal
- A CICS terminal
- An application program, using the DB2 instrumentation facility interface (IFI)

DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.

Extended MCS Consoles: The extended MCS console feature of MVS lets an MVS system have more than 99 consoles. Because DB2 supports extended MCS consoles, messages returned from a DB2 command are routed to the extended MCS console that issued the command. For more information on extended MCS consoles, see Part 4 (Volume 1) of DB2 Administration Guide, and *OS/390 MVS Planning: Operations*.

Table 2. DB2 commands

DB2 command	Function	Refer to page
-ALTER BUFFERPOOL	Alters attributes for the buffer pools	12
-ALTER GROUPBUFFERPOOL	Alters attributes for the group buffer pools	19
-ALTER UTILITY	Alters parameter values of the REORG utility	23
-ARCHIVE LOG	Enables a site to close a current active log and open the next available log data set	26
-CANCEL THREAD	Cancels processing for specific local or distributed threads	77
-DISPLAY ARCHIVE	Displays information about archive log processing	95
-DISPLAY BUFFERPOOL	Displays information about the buffer pools	97
-DISPLAY DATABASE	Displays status information about DB2 databases	106
-DISPLAY FUNCTION SPECIFIC	Displays statistics about external user-defined functions	121
-DISPLAY GROUP	Displays information about the data sharing group to which a DB2 subsystem belongs	125

Table 2. DB2 commands (continued)

DB2 command	Function	Refer to page
-DISPLAY GROUPBUFFERPOOL	Displays status information about DB2 group buffer pools	129
-DISPLAY LOCATION	Displays status information about distributed threads	143
-DISPLAY LOG	Displays log information and status of the offload task	146
-DISPLAY PROCEDURE	Displays status information about stored procedures	148
-DISPLAY RLIMIT	Displays status information about the resource limit facility (governor)	152
-DISPLAY THREAD	Displays information about DB2 threads	153
-DISPLAY TRACE	Displays information about DB2 traces	165
-DISPLAY UTILITY	Displays status information about a DB2 utility	171
-MODIFY TRACE	Changes the IFCIDs (trace events) associated with a particular active trace	238
-RECOVER BSDS	Reestablishes dual bootstrap data sets	251
-RECOVER INDOUBT	Recovers threads left indoubt	252
-RECOVER POSTPONED	Completes back-out processing for units of recovery left incomplete during an earlier restart	255
-RESET GENERICLU	Purges information stored by VTAM in the coupling facility	257
-RESET INDOUBT	Purges information displayed in the indoubt thread report generated by the -DISPLAY THREAD command	259
-SET ARCHIVE	Controls the allocation of tape units and the deallocation time of the tape units for archive log processing	265
-SET LOG	Modifies the checkpoint frequency	270
-SET SYSPARM	Changes subsystem parameters online	268
-START DATABASE	Makes the specified database available for use	276
-START DB2	Initializes the DB2 subsystem (can be issued only from an MVS console)	283
-START DDF	Starts the distributed data facility	286
-START FUNCTION SPECIFIC	Activates an external function that is stopped	287
-START PROCEDURE	Activates the definition of stopped or cached stored procedures	294
-START RLIMIT	Starts the resource limit facility (governor)	297
-START TRACE	Initiates DB2 trace activity	299
-STOP DATABASE	Makes specified databases unavailable for applications	310
-STOP DB2	Stops the DB2 subsystem	316
-STOP DDF	Stops the distributed data facility	318

Table 2. DB2 commands (continued)

DB2 command	Function	Refer to page
-STOP FUNCTION SPECIFIC	Stops the acceptance of SQL statements for specified functions	321
-STOP PROCEDURE	Stops the acceptance of SQL CALL statements for stored procedures	326
-STOP RLIMIT	Stops the resource limit facility (governor)	329
-STOP TRACE	Stops trace activity	330
-TERM UTILITY	Terminates execution of a utility	335

Completion Messages: Message DSN9022I indicates the normal end of DB2 command processing; DSN9023I indicates the abnormal end of DB2 command processing.

IMS commands

Environment: Each IMS command can be issued from an IMS terminal.

Table 3. IMS commands

IMS command	Function	Refer to page
/CHANGE	Resets an indoubt recovery unit	82
/DISPLAY	Displays the status of the connection between IMS and the specified subsystem (DB2), or displays the outstanding recovery units associated with the specified subsystem (DB2)	92
/SSR	Allows the IMS operator to enter an external subsystem (DB2) command	274
/START	Makes available the connection between IMS and the specified external subsystem (DB2)	275
/STOP	Prevents application programs from accessing the external subsystem's (DB2's) resources	309
/TRACE	Allows users to direct and control IMS tracing activities	338

CICS attachment facility commands

Environment: Each CICS attachment facility command can be issued from a CICS terminal.

Table 4. CICS attachment facility commands

CICS attachment facility commands	Function	Refer to page
DSNC	Allows you to enter DB2 commands from CICS	178
DSNC DISCONNECT	Disconnects threads	179
DSNC DISPLAY	Displays information on CICS transactions	180

Table 4. CICS attachment facility commands (continued)

CICS attachment facility commands	Function	Refer to page
DSNC MODIFY	Modifies the ERRDEST entry in the resource control table (RCT), or modifies the maximum active thread value associated with a given transaction or group name	184
DSNC STOP	Stops the CICS attachment facility	186
DSNC STRT	Starts the CICS attachment facility	187

MVS IRLM commands

Environment: Each MVS IRLM command can be issued from an MVS console.

Table 5. MVS commands affecting the IRLM

MVS command	Function	Refer to page
MODIFY irlmproc, ABEND	Abends IRLM	223
MODIFY irlmproc, DIAG,DELAY	Initiates diagnostic dumps for IRLM subsystems	225
MODIFY irlmproc, PURGE	Releases IRLM locks	227
MODIFY irlmproc, SET	Dynamically sets the maximum CSA or the number of trace buffers allowed for IRLM	228
MODIFY irlmproc, STATUS	Displays IRLM status	232
START irlmproc	Starts an IRLM component with an installation-supplied procedure	290
STOP irlmproc	Shuts down IRLM normally	324
TRACE CT	Starts, stops, or modifies IRLM tracing	340

TSO CLISTs

Table 6. TSO CLISTs

CLIST	Function	Refer to page
DSNH	Prepares a program for execution, and executes it if it runs under TSO. Runs under TSO in foreground or background.	189
DSNU	Generates JCL to execute DB2 utility jobs. Can be executed directly or by using DB2I. For details on this command procedure, see <i>DB2 Utility Guide and Reference</i> .	

-ALTER BUFFERPOOL (DB2)

-ALTER BUFFERPOOL (DB2)

The DB2 command ALTER BUFFERPOOL alters attributes for active or inactive buffer pools. Altered values are remembered until altered again.

Abbreviation: -ALT BPOOL

Environment

This command can be issued from an MVS console, a DSN session under TSO, a DB2I panel (DB2 COMMANDS), an IMS or CICS® terminal, or a program using the instrumentation facility interface (IFI).

Data sharing scope: Member


Authorization

To execute this command, the privilege set of the process must include one of the following:

- SYSOPR authority
- SYSCTRL authority
- SYSADM authority

DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.

Syntax



Option descriptions

(bpname)

Names the buffer pool to alter.

- 4-KB page buffer pools are named BP0, BP1, ..., BP49.
- 8-KB page buffer pools are named BP8K0, BP8K1, ..., BP8K9.
- 16-KB page buffer pools are named BP16K0, BP16K1, ..., BP16K9.
- 32-KB page buffer pools are named BP32K, BP32K1, ..., BP32K9.

VPSIZE (integer)

Changes the virtual buffer pool size.

-ALTER BUFFERPOOL (DB2)

integer specifies the number of buffers to allocate to the active virtual buffer pool.

integer can range from 0 to 400000 for 4-KB page buffer pools other than BP0. For BP0, the minimum value is 56. For 8-KB page buffer pools, the range is from 0 to 200000. For 16-KB page buffer pools, the range is from 0 to 100000. For 32-KB page buffer pools, the range is from 0 to 50000.

DB2 limits the total VPSIZE for all buffer pools to 1.6 GB. However, the amount of available real and virtual storage can further limit the amount of buffer pool storage DB2 can acquire.

If you specify VPSIZE as 0 for an active buffer pool (other than BP0), DB2 quiesces all current database access and update activities for that buffer pool and then deletes the buffer pool. Subsequent attempts to use table spaces or indexes that are assigned to that buffer pool fail.

VPTYPE

Specifies the type of virtual buffer pool to be allocated. Changes to the VPTYPE value apply after DB2 reallocates the buffer pools.

If the specified virtual pool is currently allocated, VPTYPE and VPSIZE are mutually exclusive. In order to change both the type and size specifications, follow the procedure in 16.

When DB2 is installed, the **default** is **VPTYPE (PRIMARY)**. However, when you issue the ALTER BUFFERPOOL command, you must explicitly specify either PRIMARY or DATASPACE when the VPTYPE option is used.

#

(PRIMARY)

The virtual buffer pool is to be allocated in the DB2 database services address space.

#

(DATASPACE)

The virtual buffer pool is to be allocated in one or more DB2-associated data spaces.

HPSIZE (*integer*)

Changes the hiperpool size. If the buffer pool is active at the time the command is issued, the hiperpool is created, expanded, contracted, or deleted depending on the new HPSIZE value.

integer specifies the number of buffers for a hiperpool. For 4-KB-page hiperpools, the acceptable values range from 0 to 2097152. For 8-KB-page hiperpools, the range is from 0 to 1048576. For 16-KB-page hiperpools, the range is from 0 to 524288. For 32-KB-page hiperpools, the range is from 0 to 262144.

DB2 limits the total HPSIZE for all buffer pools to 8 GB. However, the amount of available expanded or real storage can further limit the amount of buffer pool storage DB2 can acquire. A value of 0 can be specified for all buffer pools.

VPSEQT (*integer*)

Changes the sequential steal threshold for the virtual buffer pool.

integer specifies the sequential steal threshold for the virtual buffer pool. It is expressed as a percentage of the total virtual buffer pool size, and valid values range from 0 to 100. This threshold affects the allocation of buffers in the virtual buffer pool to page read requests that are part of a sequential access pattern. This includes pages being prefetched. If the number of buffers containing sequentially accessed pages exceeds the threshold, a sequential request

-ALTER BUFFERPOOL (DB2)

attempts to reuse one of those buffers rather than a buffer containing a non-sequentially accessed page. The initial default value is 80.

When VPSEQT=0, sequentially accessed pages are not kept in the virtual buffer pool after being released by the accessing agent. Also, prefetch is disabled.

When VPSEQT=100, DB2 does not prefer reusing sequential buffers over using non-sequential buffers.

VPSEQT (integer)

Changes the parallel sequential threshold for the virtual buffer pool. This threshold determines how much of the virtual buffer pool is used for parallel processing operations.

integer specifies the parallel sequential threshold for the virtual buffer pool. It is expressed as a percentage of the sequential steal threshold, and valid values range from 0 to 100. The initial default value is 50.

When VPPSEQT=0, parallel processing operations are disabled.

VPPSEQT (integer)

Changes the assisting parallel sequential threshold for the virtual buffer pool. This threshold determines the portion of the virtual buffer pool that is used for processing queries that originate on other members of the data sharing group. It is valid and effective only when DB2 is on a data sharing mode; it is ignored when DB2 is not on a data sharing mode.

integer specifies the assisting parallel sequential threshold for the virtual buffer pool. It is expressed as a percentage of the parallel sequential threshold (VPPSEQT). Whenever the sequential steal threshold or the parallel sequential threshold is altered, it directly affects the portion of buffer resources dedicated to "assistant" parallel operations. The valid values range from 0 to 100. The initial default value is 0.

When VPXPSEQT=0, this bufferpool cannot be used to assist another DB2 with parallel processing.

HPSEQT (integer)

Changes the hiperpool sequential steal threshold.

integer specifies the sequential steal threshold for the hiperpool. It is expressed as a percentage of the total hiperpool size, and valid values range from 0 to 100. This threshold affects the allocation of hiperpool buffers when casting out sequentially accessed pages from the virtual pool. If the number of buffers in the hiperpool containing sequentially accessed pages exceeds the threshold, the buffer allocation for a sequentially accessed page attempts to reuse one of these buffers rather than a buffer containing a non-sequentially accessed page. The initial default is 80.

When HPSEQT=0, sequentially accessed pages are not cast out to the hiperpool.

When HPSEQT=100, DB2 does not prefer reusing sequential buffers over using non-sequential buffers.

DWQT (integer)

Changes the buffer pool's deferred write threshold.

integer specifies the deferred write threshold for the virtual buffer pool. It is expressed as a percentage of the total virtual buffer pool size, and valid values range from 0 to 90. This threshold determines when deferred writes begin,

-ALTER BUFFERPOOL (DB2)

based on the number of unavailable (non-stealable) buffers. When the count of non-stealable buffers exceeds the threshold, deferred writes begin. The initial default value is 50.

VDWQT (*integer1*,*integer2*)

integer1 specifies the vertical deferred write threshold for the virtual buffer pool. It is expressed as a percentage of the total virtual buffer pool size, and valid values range from 0 to 90.

This threshold determines when deferred writes begin, based on the number of updated pages for a given data set. Deferred writes begin for that data set when the count of updated buffers for a data set exceeds the threshold. This threshold can be overridden for page sets accessed by DB2 utilities and must be less than or equal to the value specified for the DWQT option.

The default value is 10. A value of 0 indicates that the deferred write of 32 pages begins when the updated buffer count for the data set reaches 40.

integer2 specifies the vertical deferred write threshold for the virtual buffer pool. It is expressed as an absolute number of buffers. You can use *integer2* when you want a relatively low threshold value for a large virtual pool, but *integer1* cannot provide a fine enough granularity between *integer1* values of 0 and 1. *integer2* only applies when *integer1* is 0; DB2 ignores a value specified for *integer2* if the value specified for *integer1* is non-zero. *integer2* can range from 0 to 9999. The default value is 0.

If *integer1* is 0 and *integer2* is a non-zero value, DB2 uses the value specified for *integer2* to determine the threshold. If both values are 0, then the *integer1* value of 0 is used as the threshold.

CASTOUT

Changes the CASTOUT attribute of the hiperspaces used to back the hiperpool.

When DB2 is installed, the **default** is **CASTOUT (YES)** for all hiperpools. However, when you issue the ALTER BUFFERPOOL command, you must explicitly specify either YES or NO when the CASTOUT option is used.

(YES)

Allows MVS to discard data cached in the hiperpool when a shortage of expanded storage arises. When data is discarded, hiperspace backing expanded storage pages is released.

(NO)

Directs MVS to assign a high priority to keeping the data cached in the hiperpool. Because this could severely limit the availability of expanded storage to other processes on the system, specify CASTOUT(NO) only for buffer pools associated with databases for which response time is critical.

PGSTEAL

Specifies the page stealing algorithm DB2 uses for the virtual buffer pool.

When DB2 is installed, the **default** is **PGSTEAL (LRU)**. However, when you issue the ALTER BUFFERPOOL command, you must explicitly specify either LRU or FIFO when the PGSTEAL option is used.

#

(LRU)

Specifies the virtual buffer pool buffers should be managed using the least recently used (LRU) algorithm.

#

(FIFO)

Specifies the virtual buffer pool buffers should be managed using the first in first out (FIFO) algorithm.

-ALTER BUFFERPOOL (DB2)

Usage notes

The following sections contain additional information about how to use the ALTER BUFFERPOOL command.

Changing several buffer pool attributes: A failure in modifying one buffer pool attribute has no effect on other modifications requested in the same command.

Insufficient virtual storage: If insufficient virtual storage is detected while expanding a virtual buffer pool or while creating or expanding a hiperpool, DB2 issues an error message, and the process terminates, leaving the virtual buffer pool or hiperpool with a smaller size than was requested. Similarly, DB2 issues an error message if it is unable to create a hiperspace.

Contracting an active virtual buffer pool: If you use ALTER BUFFERPOOL to contract the size of an active virtual buffer pool, DB2 contracts the pool by marking active buffers as "to be deleted," which means they are not reusable to satisfy other page requests. However, the virtual storage might not be freed immediately. A system administrator can determine the status of the buffer pool by issuing the DISPLAY BUFFERPOOL command.

Deleting an active buffer pool: If you use ALTER BUFFERPOOL to delete an active buffer pool (by specifying 0 for VPSIZE), DB2 issues a message to indicate that it is ready to explicitly delete this buffer pool. Once DB2 accepts the delete buffer pool request, the buffer pool is marked as "delete pending". All current access to the buffer pool is quiesced, later access attempts fail with an error message, and all open page sets that refer to the buffer pool are closed.

Altering hiperpool attributes: If you use ALTER BUFFERPOOL to alter the CASTOUT attribute of an already active hiperpool, DB2 marks the hiperpool as temporarily unavailable, so transactions are executed using the buffer pool without its backing hiperpool. The hiperspaces backing the hiperpool are deleted and re-created with the new CASTOUT attribute. All pages that were cached in the hiperpool are purged before the hiperpool is activated again.

When DB2 is restarted, if a hiperpool could not be created, DB2 issues a warning message indicating the reason. Under this condition, DB2 comes up with only the virtual bufferpool created. Use ALTER BUFFERPOOL to set the HPSIZE value to 0 to avoid any further messages.

Altering attributes stored in the BSDS: The virtual bufferpool and hiperpool attributes that are stored in the BSDS cannot be changed off line.

Altering the VPTYPE for a virtual buffer pool: If the virtual pool is currently allocated and you change the VPTYPE attribute, the VPTYPE specification becomes effective only at the next allocation of the virtual buffer pool. To alter the VPTYPE attribute for a buffer pool and have it take effect, use the following procedure:

1. Issue the ALTER BUFFERPOOL command, specifying a new value for VPTYPE. If the virtual pool is currently allocated, the new specification takes effect the next time the buffer pool is allocated. If the buffer pool is currently allocated, proceed to step 2.
2. If the target buffer pool is not BP0:
 - a. Issue the following command to deallocate the buffer pool:
`-ALTER BUFFERPOOL(bpname) VPSIZE(0)`

-ALTER BUFFERPOOL (DB2)

- b. Issue the following command to redefine the buffer pool with the new type and new size:
`-ALTER BUFFERPOOL(bpname) VPSIZE(newsize) VPTYPE(newtype)`
3. If the target buffer pool is BP0:
 - a. Issue the following command to specify the new type:
`-ALTER BUFFERPOOL(0) VPTYPE(newtype)`
 - b. Deallocate BP0 by either issuing the STOP DATABASE command to stop all table spaces and indexes that are using BP0, or stop DB2.
 - c. Depending on the action taken in step 3b, issue START DATABASE commands to start the stopped table spaces and indexes, or restart DB2.
 - d. Optionally, issue the following command to specify the new size.
`-ALTER BUFFERPOOL(BP0) VPSIZE(newsize)`

If you skip this step, the previous size is used.

Converting an active buffer pool to use a data space: When you convert buffer pool 0 (BP0) to use a data space, use either one of the following procedures.

Procedure 1

1. Issue ALTER BUFFERPOOL(0) VPTYPE(DATASPACE)
2. Issue STOP DB2
3. Issue START DB2

Procedure 2 (requires SYSADM authority)

1. Issue ALTER BUFFERPOOL(0) VPTYPE(DATASPACE)
2. Stop all databases that are using BP0 (or stop all databases)
3. Stop DDF
4. Stop the Resource Access Limit Facility
5. Stop all work databases that are using BP0
6. Stop DSNDDB06
7. Stop DSNDDB01
8. Start all datasets starting with step 7 back to step 2

When you convert buffer pools other than BP0, use the following procedure.

1. Issue ALTER BUFFERPOOL(x) VPSIZE(0)
2. Let all datasets in the buffer pool stop
3. Issue ALTER BUFFERPOOL(x) VPTYPE(DATASPACE) VPSIZE(newsize)

Relating VPPSEQT and VPXSEQT: The Table 7 on page 18 explains how the two parallel sequential thresholds, VPPSEQT for parallel sequential and VPXPSEQT for assisting parallel sequential threshold, are related. VPXPSEQT is a percentage of VPPSEQT, which is itself a portion of VPSEQT. Multiply VPXPSEQT by VPPSEQT to obtain the total amount of the virtual buffer pool that can be used to assist another DB2 with parallel processing. In addition, VPPSEQT is affected by changing VPSIZE and VPSEQT; therefore, VPXPSEQT is also affected by VPSIZE and VPSEQT. For more information on the relationships of the various thresholds and possible configurations, see Chapter 6 of *DB2 Data Sharing: Planning and Administration*.

-ALTER BUFFERPOOL (DB2)

Table 7. Relationship between VPPSEQT and VPXPSEQT

If VPPSEQT is ...	and VPXPSEQT is ...	the percentage of the virtual buffer pool available to assist Sysplex query parallelism is...
50	50	25
50	100	50
100	50	50
anything	0	0
0	anything	0

Examples

Example 1: Set the virtual buffer pool and hiperpool for BP0 to 1000 and 10000 buffers, respectively.

```
-ALTER BUFFERPOOL(BP0) VPSIZE(1000) HPSIZE(10000)
```

Example 2: Set the sequential steal threshold of the virtual buffer pool for BP0 to 75 percent of the virtual pool size, while disabling caching of sequentially accessed pages in the hiperpool.

```
-ALTER BUFFERPOOL(BP0) VPSEQT(75) HPSEQT(0)
```

Example 3: Set the hiperpool size for BP4 to 10000 buffers and explicitly specify that cached data in the hiperpool for BP4 can be discarded.

```
-ALTER BUFFERPOOL(BP4) HPSIZE(10000) CASTOUT(YES)
```

Example 4: Delete BP1. Be very careful when using this option because when you specify a 0 size for an active buffer pool, DB2 quiesces all current database access and fails all subsequent page set open requests.

```
-ALTER BUFFERPOOL(BP1) VPSIZE(0)
```

-ALTER GROUPBUFFERPOOL (DB2)

The DB2 command ALTER GROUPBUFFERPOOL alters attributes of group buffer pools.

Abbreviation: -ALT GBPOOL

Environment

This command can be issued from an MVS console, a DSN session under TSO, a DB2I panel (DB2 COMMANDS), an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

Data sharing scope: Group


Authorization

To execute this command, the privilege set of the process must include one of the following authorities:

- SYSOPR authority
- SYSCTRL authority
- SYSADM authority

DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.

Syntax



Option descriptions

(gbpname)

Names the DB2 group buffer pool.

- 4-KB group buffer pools are named GBP0, GBP1, ... , GBP49.
- 8-KB group buffer pools are named GBP8K0, GBP8K1, ... , GBP8K9.
- 16-KB group buffer pools are named GBP16K0, GBP16K1, ... , GBP16K9.
- 32-KB group buffer pools are named GBP32K, GBP32K1, ... , GBP32K9.

(structure-name)

Names the backing coupling facility structure for the group buffer pool. The coupling facility structure name has the following format:

groupname_gbpname

-ALTER GROUPBUFFERPOOL (DB2)

where *groupname* is the DB2 data sharing group name and the underscore (_) separates *groupname* and *gbpname*.

GBPCACHE

Specifies whether *gbpname* is to be used for both caching data and cross-invalidation, or just for cross-invalidation.

(YES)

gbpname is used for caching data and cross-invalidation.

Any “no data caching” attribute that is specified at either the page set or group buffer pool level takes precedence over a caching specification. For more information, see Table 8.

Table 8. Precedence of a no-data-caching specification

Group buffer pool specification	Page set specification	Attribute that takes precedence
GBPCACHE(NO)	GBPCACHE CHANGED GBPCACHE ALL	GBPCACHE(NO)
GBPCACHE(YES)	GBPCACHE NONE	GBPCACHE NONE

(NO)

Indicates that *gbpname* is used only for cross-invalidation. This group buffer pool contains no data entries. The GBPCACHE option of table spaces or index spaces that use this group buffer pool is ignored.

AUTOREC

Specifies whether automatic recovery by DB2 takes place when a structure failure occurs or when the connectivity of all members of the group to the group buffer pool is lost.

(YES)

Indicates that DB2 is to automatically recover page sets and partitions that have a status of group buffer pool RECOVER pending (GRECP) and that have pages on the logical page list.

(NO)

Disables automatic recovery. Enter a START DATABASE command to recover page sets and partitions that have a status of GRECP or that have pages on the logical page list.

RATIO (*ratio*)

Changes the desired ratio in the group buffer pool of the number of directory entries to the number of data pages; that is, how many directory entries there are for each data page.

ratio can be a decimal number from 1.0 to 255, inclusive. Any digits after the first decimal place are ignored; for example, 5.67 is treated as 5.6. In numbers greater than 25, any digits after the decimal point are ignored; for example, 25.98 is treated as 25. The default is 5.

The actual number of directory entries and data pages that are allocated depends on the size of the coupling facility structure, which is specified in the coupling facility policy definitions.

CLASST (*integer*)

Changes the threshold at which class castout is started. It is expressed as a percentage of the size of the number of data entries; *integer* can range from 0 to 90. The default is 10.

-ALTER GROUPBUFFERPOOL (DB2)

As an example, CLASST(5) starts class castout when the number of pages in that class equals 5% of the group buffer pool page capacity.

GBPOOLT (*integer*)

Changes the threshold at which data in the group buffer pool is cast out to disk. It is expressed as a percentage of the number of data entries; *integer* can range from 0 to 90. The default is 50.

As an example, GBPOOLT(55) casts out data if the number of pages in the group buffer pool equals 55% of the group buffer pool page capacity.

GBPCHKPT (*integer*)

Changes the time interval, in minutes, between successive checkpoints of the group buffer pool. *integer* can range from 1 to 999999. Unless a value is explicitly specified for the GBPCHKPT option, the default value is 8 minutes.

The more frequently checkpoints are taken, the less time it takes to recover the group buffer pool if the coupling facility fails.

Usage notes

Defaults: Issuing the command does not change any option that is not explicitly specified; the default is to leave the value unchanged. When the command is first issued for a group buffer pool or a structure, the option defaults are as follows:

Option	Value
GBPCACHE	YES
RATIO	5
CLASST	10 (%)
GBPOOLT	50 (%)
GBPCHKPT	8 (minutes)

When new values take effect: When you issue the ALTER GROUPBUFFERPOOL command, some option specifications become effective only at the next allocation of the group buffer pool. Refer to Table 9 for more information.

Table 9. Changing group buffer pool attributes

Keyword	New value takes effect	Applicable if GBPCACHE(NO)?
GBPCACHE	at next allocation ¹	N/A
AUTOREC	immediately	No
RATIO	at next allocation ²	No ³
CLASST	immediately	No ³
GBPOOLT	immediately	No ³
GBPCHKPT	immediately	No ³

-ALTER GROUPBUFFERPOOL (DB2)

Notes:

1. You can use the MVS command SETXCF START,REBUILD to have the change take effect if the group buffer pool is not duplexed. If the group buffer pool is duplexed and you want to change to GBPCACHE(NO), first go back to simplex mode and rebuild. GBPCACHE(NO) is not allowed for duplexed group buffer pools.
 2. You can use the MVS command SETXCF START,REBUILD to have the change take effect if the group buffer pool is not duplexed. If the group buffer pool is duplexed, first go back to simplex mode and rebuild; then optionally go back to duplex mode. If a group buffer pool is duplexed, both instances of that duplexed group buffer pool use the same RATIO value.
 3. DB2 issues message DSNB761 when you specify this option for a GBPCACHE(NO) group buffer pool. These settings only take effect after the GBPCACHE attribute has been changed to YES.
-

Examples

Example 1: For group buffer pool 0, change the ratio of directory entries to data pages to 1 directory entry for every data page. The RATIO specification becomes effective at the next allocation of the group buffer pool.

```
-DB1G ALTER GROUPBUFFERPOOL (GBP0) RATIO(1)
```

Example 2: For group buffer pool 2, change the class castout threshold to 5% and the group buffer pool castout threshold to 30%. The new values take effect immediately.

```
-DB1G ALTER GROUPBUFFERPOOL (GBP2) CLASST(5) GBPOOLT(30)
```

Example 3: Assume that the DB2 group name is DSNCAT. For group buffer pool 3, change the class castout threshold to 5%. The new value takes effect immediately. Because the group name is DSNCAT, the coupling facility structure name is DSNCAT_GBP3. Also, in the event of a structure failure, the AUTOREC(YES) option enables DB2 to automatically recover the page sets and partitions that are in a GRECP status or that have pages on the logical page list.

```
-DB1G ALTER GROUPBUFFERPOOL (DSNCAT_GBP3) CLASST(5) AUTOREC(YES)
```

Example 4: For group buffer pool 32K, change the GBP checkpoint frequency to 5 minutes. The new value takes effect immediately. Here, with AUTOREC(NO) specified, you are in effect taking control of the recovery process rather than DB2 in the event of a structure failure. You might choose to do this to determine what pagesets or partitions are in a GRECP status or that have pages on the logical page list and before entering the START DATABASE command to enable DB2 to recover the data with the options you specify.

```
-DB1G ALTER GROUPBUFFERPOOL (GBP32K) GBPCHKPT(5) AUTOREC(NO)
```


-ALTER UTILITY (DB2)

The DB2 command ALTER UTILITY changes the values of certain parameters of an execution of the REORG utility that uses SHRLEVEL REFERENCE or CHANGE. Specifically, this command changes the values of DEADLINE, MAXRO, LONGLOG, and DELAY. For more information about those parameters and the REORG utility, see *DB2 Utility Guide and Reference*.

REORG can be altered only from the DB2 on which it is running.

Abbreviation: -ALT UTIL

Environment

This command can be issued from an MVS console, a DSN session, a DB2I panel (DB2 COMMANDS), an IMS or a CICS terminal, or a program using the instrumentation facility interface (IFI).

Data sharing scope: Member

Authorization


To execute this command, the primary or some secondary authorization ID of the process must be the ID that originally submitted the utility job, or the privilege set of the process must include one of the following authorities:

- DBMAINT, DBCTRL, or DBADM authority
- SYSOPR, SYSCTRL, or SYSADM authority

DB2 commands that are issued from an MVS console are not associated with any secondary authorization IDs.

For users with DBMAINT, DBCTRL, or DBADM authority, the command takes effect only when a user has sufficient authority over each object that the utility job accesses.

Syntax



Option descriptions

(utility-id)

Is the utility identifier, or the UID parameter, used when creating the utility job step.

This job must execute REORG with SHRLEVEL CHANGE or SHRLEVEL REFERENCE.

-ALTER UTILITY (DB2)

If *utility-id* was created by the DSNU CLIST by default, it has the form *tso-userid.control-file-name*. For the control file name that is associated with each utility, see *DB2 Utility Guide and Reference*.

If *utility-id* was created by default by the EXEC statement that executed DSNUTLIB, then this token has the form *userid.jobname*.

DEADLINE

Specifies the deadline by which the user wants the switch phase of reorganization to start. If DB2 estimates that the switch phase will not start by the deadline, DB2 terminates reorganization. The default is the most recently specified value of DEADLINE.

The pre-switch processing might continue until after the deadline.

(NONE)

Specifies that there is no deadline for the read-only iteration of log processing.

(timestamp)

Specifies the deadline by which the user wants the switch phase to start processing. This deadline must not have been reached when ALTER UTILITY executes. For more information on the format for specifying a timestamp, see the discussion of data types in *DB2 SQL Reference*.

MAXRO

Specifies the maximum amount of time that is tolerated for the last iteration of log processing during reorganization. During that iteration, applications have read-only access.

The actual execution time of the last iteration can exceed the value specified for MAXRO.

(integer)

Is the number of *seconds*. The default is the most recently specified value of MAXRO.

(DEFER)

Specifies that the log phase is deferred indefinitely.

LONGLOG

Specifies the action that DB2 performs (after sending the LONGLOG message to the console) if the number of log records that are processed during the next iteration is not sufficiently lower than the number of log records that were processed during the previous iterations. The default is the most recently specified value of LONGLOG.

(CONTINUE)

Specifies that DB2 continues performing reorganization.

(TERM)

Specifies that DB2 terminates reorganization after the delay.

(DRAIN)

Specifies that DB2 drains the write claim class after the delay. The number of log records, and thus the *estimated* time, for a future iteration of log processing will be 0.

DELAY *integer*

Specifies a lower bound for the interval between the time when REORG sends the LONGLOG message to the console and the time when REORG performs the action specified by the LONGLOG parameter.

-ALTER UTILITY (DB2)

integer is the number of *seconds*. The value must be nonnegative. The default is the most recently specified value of DELAY.

Usage note

REORG can be altered only from the DB2 subsystem on which it is running.

Example

The following example alters the execution of the REORG utility for the utility job step whose utility identifier is REORGEMP:

```
-ALTER UTILITY (REORGEMP) REORG MAXRO(240) LONGLOG DRAIN
```

In this example:

- MAXRO(240) changes the maximum tolerable time for the last iteration of log processing to 240 seconds (4 minutes).
- LONGLOG DRAIN changes the action that DB2 performs (if reorganization's reading of the log is not catching up to applications' writing of the log quickly enough) to draining of the write claim class.
- DELAY was not specified and therefore, the example does not change the existing delay between sending of the LONGLOG message to the console and performing the action specified by LONGLOG.
- DEADLINE was not specified and the example does not change the existing deadline (if any) of the last iteration of log processing.

-ARCHIVE LOG (DB2)

-ARCHIVE LOG (DB2)

When issued without any options, the DB2 command ARCHIVE LOG performs the following functions:

- Truncates the current active log data sets
- Starts an asynchronous task to offload the data sets
- Archives previous active log data sets not yet archived
- Returns control to the user (immediately)

In a data sharing environment, you can truncate and archive the logs for an individual member or for all members in the group.

When specified with the option MODE(QUIESCE), the ARCHIVE LOG command attempts to quiesce (suspend) all DB2 user update activity on the DB2 active log prior to the offload process. Once a system-wide point of consistency is reached (that is, when all currently active update users have reached a commit point), the active log is immediately truncated, and the offload process is initiated. The resulting point of consistency is captured in the current active log before it is offloaded. In a data sharing environment, you can create a system-wide point of consistency only for the entire group.

For further information regarding the ARCHIVE LOG command, see Part 4 (Volume 1) of *DB2 Administration Guide*.

Abbreviation: -ARC LOG

Environment

This command can be issued from an MVS console, a DSN session under TSO, a DB2I panel (DB2 COMMANDS), an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

The ARCHIVE LOG command can also be issued from the MVS subsystem interface (SSI) to enable automated scheduling systems and other programs to execute the command via supervisor call instruction (SVC) 34.

Data sharing scope: Group or member, depending on whether you specify MODE(QUIESCE), or on which SCOPE option you choose


Authorization

To execute this command, the privilege set of this process must include one of the following:

- ARCHIVE privilege
- Installation SYSOPR authority
- SYSCTRL authority
- SYSADM authority

DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.

Syntax



Option descriptions

SCOPE

Specifies whether the command applies to the entire data sharing group or to a single member only. The SCOPE option is valid only in a data sharing environment; the option is ignored in a non-data-sharing environment. SCOPE cannot be specified if MODE(QUIESCE) is specified; the two keywords are mutually exclusive.

(MEMBER)

Initiates offload processing only for the member from which the command is issued. User update activity is not suspended. If that member, or the entire group, is already archiving, the command fails. This is the default, except when MODE(QUIESCE) is specified.

(GROUP)

Initiates offload processing for every member of the DB2 group. User update activity is not suspended. If any member of the group, or the entire group, is already archiving, the command fails.

MODE(QUIESCE)

Halts all new update activity by the DB2 subsystem for a specified period of time and attempts to bring all existing users to a point of consistency after a commit or rollback. When a point of consistency is reached and captured in the current active log data set, the current active log data set is truncated, and another log data set in the inventory becomes current. offload processing then begins with the oldest active log data set and ends with the active log data set that was truncated.

In a data sharing environment, before archiving logs of any member, the option quiesces all active members of a data sharing group. The option also ensures that each inactive member had successfully quiesced its update activity and resolved any indoubt units of recovery (URs) before the inactive subsystem completed normal termination. If any DB2 is in a failed state, fails during quiesce processing, or is stopped with outstanding URs, the ARCHIVE LOG command fails, and the remaining active members allow update activity to proceed.

If there are no indoubt URs left on all quiesced members, active or inactive, the archive operation can continue for active members in the group. Thus, you can archive logs of a data sharing group normally without forcing all members to be active. The current logs of inactive members are truncated and offloaded after they start up.

-ARCHIVE LOG (DB2)

If a system-wide point of consistency cannot be reached during the quiesce period, which is a length of time you can control, execution of the ARCHIVE LOG command fails and an error message is issued. In a data sharing environment, the maximum time period applies for the whole group, and if any DB2 cannot quiesce within the time allowed, the command fails.

If you do not use the TIME option to specify the quiesce time period, the default is the value specified in the field QUIESCE PERIOD of installation panel DSNTIPA.

If there is no update activity on DB2 data when the command ARCHIVE LOG MODE(QUIESCE) is issued, the active log is truncated and offloaded immediately.

TIME(*nnn*)

Specifies the maximum length of time, in seconds, in which the DB2 subsystem is allowed to attempt a full system quiesce.

The **default** is the period specified in the field QUIESCE PERIOD of installation panel DSNTIPA. See Part 2 of *DB2 Installation Guide* for more information on this field.

nnn can range from 001 to 999 seconds. You must allocate an appropriate time period for the quiesce processing or the following events can occur:

- The quiesce processing can expire before a full quiesce is accomplished.
- An unnecessary DB2 lock contention can be imposed.
- A time-out can occur.

This option is valid only when used in conjunction with the option MODE(QUIESCE).

WAIT

Specifies whether the DB2 subsystem should wait until the quiesce processing has completed before returning control to the invoking console or program, or return control when the quiesce processing begins.

This option is valid only when used in conjunction with the option MODE(QUIESCE).

(YES)

Specifies that the quiesce processing must complete before returning control to the invoking console or program.

If WAIT(YES) is used, quiesce processing is synchronous to the user; that is, additional DB2 commands can be issued, but they are not processed by the DB2 command processor until the ARCHIVE LOG command is complete.

(NO)

Specifies that control must be returned to the invoking program when the quiesce processing begins.

If WAIT(NO) is used, quiesce processing is asynchronous to the user; that is, you can enter additional DB2 commands once the ARCHIVE LOG command returns control to you.

CANCEL OFFLOAD

Cancels any offloading currently in progress and restarts the offload process, beginning with the oldest active log data set that has not been offloaded and proceeding through all active log data sets that need offloading. Any suspended offload operations are restarted.

Usage notes

Remote site recovery: The ARCHIVE LOG command is very useful when performing a DB2 backup in preparation for a remote site recovery. For example, the command allows the DB2 subsystem to quiesce all users after a commit point, and capture the resulting point of consistency in the current active log *before* the archive is taken. Therefore, when the archive log is used with the most current image copy (during an offsite recovery), the number of data inconsistencies will be minimized. See Part 4 (Volume 1) of *DB2 Administration Guide* for additional information on backup and recovery.

Simultaneous executions: The ARCHIVE LOG command cannot be executed if another ARCHIVE LOG command is in progress. Instead, error message DSNJ318I is issued and the command fails. This is true in both data sharing and non-data-sharing environments. For example in a data sharing environment, the command fails if the data sharing member, or group to which it belongs, is already archiving.

Available active log space: ARCHIVE LOG cannot be used when the current active log is the last available active log data set because of the following reasons:

- All available active log space would be used.
- The DB2 subsystem would halt processing until an offload is complete.

Executing -ARCHIVE LOG while STOP DB2 is in progress: ARCHIVE LOG without the option MODE(QUIESCE) is permitted when STOP DB2 MODE(QUIESCE) is in progress. However, if an attempt is made to execute the ARCHIVE LOG command when a STOP DB2 MODE(FORCE) is in progress, error message DSNJ315I is issued and the ARCHIVE LOG command is not processed.

ARCHIVE LOG with the option MODE(QUIESCE) is not allowed when a STOP DB2 MODE(FORCE) or STOP DB2 MODE(QUIESCE) is in progress. If an attempt is made to execute the ARCHIVE LOG command under these circumstances, error message DSNJ315I or DSNJ316I is issued.

If the system was not fully quiesced (as determined by the number of users which could not be quiesced), error message DSNJ317I is issued and ARCHIVE LOG command processing is terminated. The current active log data set is not truncated and switched to the next available active log data set and the archive log is not created.

Canceling log offloads: It is possible for the offload of an active log to be suspended when something goes wrong with the offload process, such as a problem with allocation or tape mounting. Issuing ARCHIVE LOG CANCEL OFFLOAD interrupts the offload process and restarts the offload. The command causes an abnormal termination of the offload task, which can result in a dump. We recommend using ARCHIVE LOG CANCEL OFFLOAD only if the offload task no longer seems to be functioning or if you want to restart a previous offload attempt that failed.

Demand on DB2 resources: Using the option MODE(QUIESCE) during prime time or during a period in which time is critical causes a significant disruption in the availability of DB2 for all users of DB2 resources.

Interaction with -DISPLAY THREAD: By issuing message DSNV400I, the command DISPLAY THREAD indicates that an ARCHIVE LOG MODE(QUIESCE) command is active.

-ARCHIVE LOG (DB2)

Quiescing members of a data sharing group: It is not possible to quiesce a single member of a data sharing group. When MODE(QUIESCE) is specified, SCOPE(GROUP) is assumed.

Executing -ARCHIVE LOG while logging is suspended: While logging is suspended by SET LOG SUSPEND, do not use ARCHIVE LOG unless CANCEL OFFLOAD is specified. If logging is suspended, issue SET LOG RESUME to resume logging before issuing ARCHIVE LOG.

Examples

Example 1: Truncate the current active log data sets and initiate an asynchronous job to offload the truncated data sets. No quiesce processing occurs.

```
-ARCHIVE LOG
```

Example 2: Initiate a quiesce period. If all DB2 update activity is stopped within this period, truncate the current active log data set and switch to the next available active log data set. Let the value in the field QUIESCE PERIOD of installation panel DSNTIPA determine the length of the quiesce period. The MODE(QUIESCE) processing is asynchronous.

If the DB2 subsystem can successfully block all update activity before the quiesce period ends, it proceeds to the next processing step. If the quiesce time period is insufficient to successfully quiesce the DB2 subsystem, the active log data sets are not truncated and the archive does not occur.

```
-ARCHIVE LOG MODE(QUIESCE)
```

Example 3: Initiate a quiesce period. If all DB2 update activity is stopped within this period, truncate the current active log data set and switch to the next available active log data set. The maximum length of the quiesce processing period is seven minutes (420 seconds) and the processing is synchronous for the entire seven minutes.

If the DB2 subsystem can successfully block all update activity before the quiesce period ends, it proceeds to the next processing step. If the quiesce time period is insufficient to successfully quiesce the DB2 subsystem, the active log data sets are not truncated and the archive does not occur.

```
-ARCHIVE LOG MODE(QUIESCE) WAIT(YES) TIME(420)
```

Example 4: In a data sharing environment, initiate a quiesce period for all members of the data sharing group. If all DB2 update activity is stopped within this period, truncate the current active log data set and switch to the next available active log data set. Specify a quiesce time period of 10 minutes (600 seconds) to override the value in the field QUIESCE PERIOD of installation panel DSNTIPA for member DB1G. If the update activity has not quiesced after the 10 minute quiesce period, the command fails and new update activity is allowed to proceed.

```
-DB1G ARCHIVE LOG MODE(QUIESCE) TIME(600)
```

Example 5: In a data sharing environment, truncate the active log data sets for group member DB2G and initiate an asynchronous job to offload the truncated data sets, without any quiesce processing. In this example, SCOPE(MEMBER) is used by default.

```
-DB2G ARCHIVE LOG
```


-ARCHIVE LOG (DB2)

Example 6: In a data sharing environment, truncate the data sets for all members of the data sharing group and initiate an asynchronous job to offload the truncated data sets, without any quiesce processing.

```
-DB2G ARCHIVE LOG SCOPE(GROUP)
```

BIND PACKAGE (DSN)

The DSN subcommand BIND PACKAGE builds an application package. DB2 records the description of the package in the catalog tables and saves the prepared package in the directory. For more information on using BIND PACKAGE, see Part 5 of *DB2 Application Programming and SQL Guide*.

Environment

You can use BIND PACKAGE from DB2I, or from a DSN session under TSO that runs in either the foreground or background.

Data sharing scope: Group

Authorization

The package owner must have authorization to execute *all* statements embedded in the package for BIND PACKAGE to build a package without producing error messages. (The SYSADM authority includes this authorization.) For VALIDATE(BIND), DB2 verifies the authorization at bind time. For VALIDATE(RUN), DB2 verifies the authorization initially at bind time, but if the authorization check fails, DB2 rechecks it at run time.

The authorization required to add a new package or a new version of an existing package depends on the value of field BIND NEW PACKAGE on installation panel DSNTIPP. The default value is BINDADD.

Table 10 on page 33 summarizes the authorization required to run BIND PACKAGE, depending on the bind options you specify, and in the case of the ADD option, the value of field BIND NEW PACKAGE.

Table 10. Summary of privileges needed for BIND PACKAGE options

Bind option	Installation panel field BIND NEW PACKAGE	Authorization required to run BIND PACKAGE
ADD, using the default owner or primary authorization ID	BINDADD	<p>The primary authorization ID (default owner) must have one of the following to add a new package or new version of an existing package to a collection:</p> <ul style="list-style-type: none"> • The BINDADD system privilege and either the CREATE IN privilege or PACKADM authority on the collection or on all collections • SYSADM or SYSCTRL authority
	BIND	<p>The primary authorization ID (default owner) must have one of the following to add a new package or a new version of an existing package to a collection:</p> <ul style="list-style-type: none"> • The BINDADD system privilege and either the CREATE IN privilege or PACKADM authority on the collection or on all collections • SYSADM or SYSCTRL authority • PACKADM authority on the collection or on all collections • The BIND package privilege (can only add a new version of an existing package)
ADD, specifying an OWNER other than the primary authorization ID ⁽¹⁾	BINDADD	<p>If the binder does not have SYSADM or SYSCTRL authority, the authorization ID of the OWNER must have one of the following to add a new package or new version of an existing package to a collection:</p> <ul style="list-style-type: none"> • The BINDADD system privilege and either the CREATE IN privilege or PACKADM authority on the collection or on all collections • SYSADM or SYSCTRL authority
	BIND	<p>If the binder does not have SYSADM or SYSCTRL authority, the authorization ID of the OWNER must have one of the following to add a new package or new version of an existing package to a collection:</p> <ul style="list-style-type: none"> • The BINDADD system privilege and either the CREATE IN privilege or PACKADM authority on the collection or on all collections • SYSADM or SYSCTRL authority • PACKADM authority on the collection or on all collections • The BIND package privilege (can only add a new version of an existing package)

BIND PACKAGE (DSN)

Table 10. Summary of privileges needed for BIND PACKAGE options (continued)


Bind option	Installation panel field BIND NEW PACKAGE	Authorization required to run BIND PACKAGE
REPLACE, using the default owner or primary authorization ID	BINDADD or BIND	Primary authorization ID must have one of the following: <ul style="list-style-type: none">• Ownership of the package• BIND privilege on the package• PACKADM authority on the collection or on all collections• SYSADM or SYSCTRL authority
REPLACE, specifying an OWNER other than the primary authorization ID ⁽¹⁾	BINDADD or BIND	If the binder does not have SYSADM or SYSCTRL authority, the authorization ID of the OWNER must have one of the following: <ul style="list-style-type: none">• BIND privilege on the package• PACKADM authority on the collection or on all collections• SYSADM or SYSCTRL authority
COPY	BINDADD or BIND	The primary or secondary authorization ID of the binder or OWNER must have one of the following on the package being copied: <ul style="list-style-type: none">• Ownership of the package• COPY privilege on the package• BINDAGENT privilege from the owner of the package• PACKADM authority on the collection or on all collections• SYSADM or SYSCTRL authority

Notes:


1. If any of the authorization IDs of the process has the SYSADM authority or SYSCTRL authority, OWNER *authorization-id* can be any value. If any of the authorization IDs has the BINDAGENT privilege granted from the owner, then *authorization-id* can specify the grantor as OWNER. Otherwise, the OWNER *authorization-id* must be one of the primary or secondary authorization IDs of the binder.

For additional information on the required authorization to execute BIND PACKAGE see Part 5 (Volume 2) of *DB2 Administration Guide*.

Syntax



BIND PACKAGE (DSN)



Option descriptions

For descriptions of the options shown in the syntax diagram, see “Options of BIND and REBIND for PLAN, PACKAGE, and TRIGGER PACKAGE” on page 44.

Examples

Example 1: Replace version APRIL_VERSION of package TEST.DSN8BC71 at local location USIBMSTODB22 with another version of the package. The new version (or it could be the same) is in the DBRM DSN8BC71. If the DBRM contains no version ID, the version ID of the package defaults to the empty string. The package runs only from the TSO BATCH environment, and from the CICS environment if the connection ID is CON1. The name PRODUCTN qualifies all unqualified table, view, alias and index names.

```
BIND PACKAGE (USIBMSTODB22.TEST) -  
  MEMBER (DSN8BC71) -  
  ACTION (REPLACE) REPLVER (APRIL_VERSION) -  
  QUALIFIER (PRODUCTN) -  
  ENABLE (BATCH, CICS) CICS (CON1)
```

Example 2: UR isolation acquires almost no locks. It is fast and causes little contention, but it reads uncommitted data. Do not use ISOLATION(UR) unless you are sure that your applications and end users can accept the logically inconsistent data that can occur, such as in the case of this example.

Assume that a supervisor routinely executes SQL statements using SPUFI to check the status of parts as they go through the assembly process and to update a table with the results of her inspection. She does not need to know the exact status of the parts; a small margin of error is acceptable.

BIND PACKAGE (DSN)

The supervisor queries the status of the parts from a production table called ASSEMBLY-STATUS and makes the updates in a non-production table called REPORTS. She uses the SPUFI option AUTOCOMMIT NO and has the habit of leaving data on the screen while she performs other tasks.

If the supervisor executes a version of SPUFI that is bound with ISOLATION(UR), the query for the status of the parts executes without acquiring locks using UR isolation level and the update executes using CS isolation level. Thus, the query does not inadvertently hold locks in the production table interfering with the production jobs, and the supervisor has data good enough for her purposes.

The SPUFI application is bound as follows:

```
BIND PACKAGE(DSNESPUR) -  
  COPY(DSNESPCS.DSNESM68) -  
  ACTION(ADD) -  
  ISOLATION(UR)
```

BIND PLAN (DSN)

The DSN subcommand BIND PLAN builds an application plan. All DB2 programs require an application plan to allocate DB2 resources and support SQL requests made at run time. For more information on using BIND PLAN, see Part 5 of *DB2 Application Programming and SQL Guide*.

Environment

You can use BIND PLAN through DB2I, or from a DSN session under TSO that runs in either the foreground or background.

Data sharing scope: Group

Authorization

The plan owner must have authorization to execute *all* SQL statements embedded in the plan¹ for BIND PLAN to build a plan without producing error messages. (The SYSADM authority includes this authorization.) For VALIDATE(BIND), DB2 verifies the authorization at bind time. For VALIDATE(RUN), DB2 verifies the authorization initially at bind time, but if the authorization check fails, DB2 rechecks it at run time.

Table 11 explains the authorization required to run BIND PLAN, depending on the options specified.

Table 11. Summary of privileges needed for BIND PLAN options

Option	Authorization required to run BIND PLAN
ADD, using the default owner or primary authorization ID	Primary authorization ID (default owner) must have one of the following: <ul style="list-style-type: none">• BINDADD privilege• SYSADM or SYSCTRL authority
ADD, specifying an OWNER other than the primary authorization ID	If the binder does not have SYSADM or SYSCTRL authority, the authorization ID of the new OWNER must have one of the following: <ul style="list-style-type: none">• BINDADD privilege• SYSADM or SYSCTRL authority <p>Specifying the OWNER: If any of the authorization IDs of the process has the SYSADM authority or SYSCTRL authority, OWNER <i>authorization-id</i> can be any value. If any of the authorization IDs has the BINDAGENT privilege granted from the owner, then <i>authorization-id</i> can specify the grantor as OWNER. Otherwise, OWNER <i>authorization-id</i> must be one of the primary or secondary authorization IDs of the binder.</p>
REPLACE, using the default owner or primary authorization ID	Primary authorization ID of the process must have one of the following: <ul style="list-style-type: none">• Ownership of the plan• BIND privilege on the plan• SYSADM or SYSCTRL authority

1. This excludes statements included in DBRMs that are bound to packages included in the package list of the plan.


Table 11. Summary of privileges needed for BIND PLAN options (continued)



Option	Authorization required to run BIND PLAN
REPLACE, specifying an OWNER other than the primary authorization ID	<p>If the binder does not have SYSADM or SYSCTRL authority, the authorization ID of the OWNER must have one of the following:</p> <ul style="list-style-type: none"> • Ownership of the plan • BIND privilege on the plan • SYSADM or SYSCTRL authority <p>Specifying the OWNER: If any of the authorization IDs of the process has the SYSADM authority or SYSCTRL authority, OWNER <i>authorization-id</i> can be any value. If any of the authorization IDs has the BINDAGENT privilege granted from the owner, then <i>authorization-id</i> can specify the grantor as OWNER. Otherwise, OWNER <i>authorization-id</i> must be one of the primary or secondary authorization IDs of the binder.</p>
PKLIST, specifying individual packages	<p>Authorization ID of the process must include one of the following:</p> <ul style="list-style-type: none"> • EXECUTE authority on each package specified in the PKLIST • PACKADM authority on specific collections that contain the packages or on all collections • SYSADM authority
PKLIST, specifying (*), indicating all packages in the collection	<p>Authorization ID of the process must include one of the following:</p> <ul style="list-style-type: none"> • EXECUTE authority on <i>collection-id</i>.* • PACKADM authority on specific collections that contain the packages or on all collections • SYSADM authority

For additional information on the required authorization to execute BIND PLAN see Part 5 (Volume 2) of *DB2 Administration Guide*.

BIND PLAN (DSN)

Syntax





Option descriptions

For descriptions of the options shown in the syntax diagram, see “Options of BIND and REBIND for PLAN, PACKAGE, and TRIGGER PACKAGE” on page 44.

Examples

Example 1: This subcommand creates a new plan called IMSONLY. The SQL statements for the plan are in the DBRM member DSN8BC71. An ISOLATION level of cursor stability (CS) provides maximum concurrency when you run the plan, and protects database values only while the program uses them. DEPTM92 owns the plan, but PRODUCTN qualifies any unqualified table, view, index, and alias names referenced in the DBRM.

A cache size of 0 indicates that users will not run the plan repeatedly. Caching the names of users authorized to run the plan helps only when the same user runs the

BIND PLAN (DSN)

plan repeatedly while it is in the EDM pool. Since this is not the case with this plan, there is no need to reserve space in the EDM pool for a cache that the plan does not use.

The option `ENABLE(IMS)` runs the plan only from an IMS environment (DLI Batch, BMP and MPP). If you attempt to run the plan from another environment, such as TSO Batch, the plan allocation fails.

```
BIND PLAN(IMSONLY) -  
  MEMBER(DSN8BC71) -  
  ACTION(ADD) -  
  ISOLATION(CS) -  
  OWNER(DEPTM92) -  
  QUALIFIER(PRODUCTN) -  
  CACHESIZE -  
  ENABLE(IMS)
```

Example 2: If the DBRM of plan IMSONLY in example 1 contains both embedded and dynamic SQL statements and you want to allow other users to run the plan, you must grant the EXECUTE privilege on plan IMSONLY to those users' authorization IDs. However, because the EXECUTE privilege on a plan is sufficient authority to run embedded SQL statements in a DBRM but is not sufficient authority to run dynamic SQL statements, you must also do one of the following:

- Use the SQL GRANT statement to grant the necessary privileges on the objects (tables, views, aliases, and indexes) referenced in the dynamic SQL statements to the users' authorization IDs, or
- BIND the plan IMSONLY with the option `DYNAMICRULES(BIND)` as follows:

```
BIND PLAN(IMSONLY) -  
  MEMBER(DSN8BC71) -  
  ACTION(ADD) -  
  ISOLATION(CS) -  
  OWNER(DEPTM92) -  
  QUALIFIER(PRODUCTN) -  
  CACHESIZE(0) -  
  ENABLE(IMS) -  
  DYNAMICRULES(BIND)
```

To allow other users having only the EXECUTE privilege on a plan to run both the embedded and dynamic SQL statements, you must bind that plan with the option `DYNAMICRULES(BIND)`. When `DYNAMICRULES(BIND)` is in effect for plan IMSONLY:

- A single authorization ID, the authorization ID for DEPTM92, is used for authorization checking of both the embedded and dynamic SQL statements in the DBRM.
- PRODUCTN is the implicit qualifier of unqualified object names referenced in both the embedded and dynamic SQL statements in the DBRM.

Example 3: This subcommand creates a new plan called CICSONLY. The plan specifies an ISOLATION level of cursor stability (CS). DEPTM12 owns the plan, but TESTSYS qualifies any unqualified table, view, index, and alias names referenced in the DBRM. A cache size of 0 indicates that users will not run the plan repeatedly.

The option `ENABLE(CICS)` `CICS(CON1)` runs the plan only from CICS VTAM® node CON1 which is specified in the APPLID parameter of the CICS SIT table. If you attempt to run the plan from another environment or from another CICS VTAM node, the run attempt fails.

BIND PLAN (DSN)

```
BIND PLAN(CICSONLY) -  
  MEMBER(DSN8BC71) -  
  ACTION(ADD) -  
  ISOLATION(CS) -  
  OWNER(DEPTM12) -  
  QUALIFIER(TESTSYS) -  
  CACHESIZE(0) -  
  ENABLE(CICS) CICS(CON1)
```

Options of BIND and REBIND for PLAN, PACKAGE, and TRIGGER PACKAGE

This section lists the options you can use for binding or rebinding plans and packages. Some of them are common for both bind and rebind and both plans and packages.

Defaults: The *default* for an option is the value used if you omit the entire option.

A default of *plan value* for BIND PACKAGE means that the default is the same as the value determined during the bind or rebind of the plan to which the package is appended at run time.

A default of *existing value* for REBIND PLAN or REBIND PACKAGE means that the default is the value that was determined during the previous bind or rebind of the plan or package you are rebinding.

For all other cases, the option descriptions note the specific defaults, which DB2 assigns at bind time. If a specific default value exists, that value is underlined.

Catalog records: The DB2 catalog records information about plans and packages, chiefly in the tables SYSIBM.SYSPPLAN and SYSIBM.SYSPACKAGE. The descriptions of where the options record information omit the constant qualifier, SYSIBM, of those table names.

ACQUIRE	(<u>USE</u>) (<u>ALLOCATE</u>)	On: BIND and REBIND PLAN
<p>Determines whether to acquire resources for DBRMs specified in the MEMBER list when the application first accesses them or when the plan is allocated. Local or remote packages associated with the plan acquire their resources when the application first accesses them.</p> <p>(USE) Acquires table space locks only when the application program bound to the plan first uses them.</p> <p>(ALLOCATE) Acquires all table space locks when the plan is allocated. The value has no effect on dynamic SQL statements, which always use ACQUIRE(USE). If you use ACQUIRE(ALLOCATE), you must also use RELEASE(DEALLOCATE). ACQUIRE(ALLOCATE) can increase the plan size, because additional items become resident in the plan.</p>		

Defaults:

Process	Default value
BIND PLAN	USE
BIND PACKAGE	N/A
REBIND PLAN	existing value
REBIND PACKAGE	N/A

There is no ACQUIRE option for packages. A package always acquires resources when it first uses them, as if you specified ACQUIRE(USE). See Part 5 (Volume 2) of *DB2 Administration Guide*.

Catalog record: Column ACQUIRE of table SYSPLAN.

For more information about:

- How the option affects locking and concurrency, see Part 5 (Volume 2) of *DB2 Administration Guide* or Part 4 of *DB2 Application Programming and SQL Guide*.
- How the option improves the performance of selective partition locking, see Part 5 (Volume 2) of *DB2 Administration Guide* or Part 4 of *DB2 Application Programming and SQL Guide*.
- Estimating the size of a plan, see Part 2 of *DB2 Administration Guide*.

ACTION	(REPLACE) (REPLACE) RPLVER (BIND PACKAGE only) (REPLACE) RETAIN (BIND PLAN only) (ADD)	On: BIND PLAN and PACKAGE
--------	---	---------------------------

Determines whether the object (plan or package) replaces an existing object with the same name or is new.

(REPLACE)

The object replaces an existing one with the same identifier, and a new entry replaces the old one in the catalog table SYSPLAN or SYSPACKAGE. If no object with the given identifier already exists, the bind process creates the new object and a new entry.

The authorization ID designated explicitly or implicitly by the option OWNER becomes the owner of the new object. If that authorization ID is not the previous owner, all grants of privileges for the object that the previous owner issued change to name the new owner as the grantor.

If the bind fails, the old object and its entry remain.

For BIND PACKAGE: You cannot use REPLACE with a remote package bound with either of the options ENABLE or DISABLE. The attempt causes the bind to fail.

REPLVER(*version-id*) (For BIND PACKAGE only)

Replaces a specific version of the package, identified by *version-id*. If the package with the specified *version-id* does not exist, the bind fails.

The default for *version-id* comes from the DBRM if you use the MEMBER option on BIND, or from the COPYVER option if you use the COPY option.

RETAIN (For BIND PLAN only)

Preserves EXECUTE privileges when you replace the plan. If ownership of the plan changes, the new owner grants the privileges BIND and EXECUTE to the previous owner.

RETAIN is *not* the default. If you do not specify RETAIN, everyone but the plan owner loses the EXECUTE privilege (but not the BIND privilege). If plan ownership changes, the new owner grants the BIND privilege to the previous owner.

(ADD)

Adds a new object, but does not replace an existing one. If the object name

BIND PLAN (DSN)

already exists in the catalog, the bind fails. If the bind fails for any reason, the bind process does not produce a new package or plan and makes no entry in the catalog.

Replacing a version of a package (REPLVER): This section describes the effect of ACTION(REPLACE) REPLVER in four situations. Here, DBRM1 is the member name and A and B represent the names of two versions of the package. Suppose you bind version A with this command:

```
BIND PACKAGE(COLL1) MEMBER(DBRM1) ACTION(REPLACE) REPLVER(B)
```

- If neither DBRM1, version A, nor version B exist in the DB2 catalog, the command fails because version B is not in the catalog. No new package is added.
- If DBRM1 and version B, but not version A, exist in the DB2 catalog, then version A replaces version B. As a result, version A exists in the catalog, and version B no longer exists in the catalog.
- If DBRM1 and version A exist in the catalog, but not version B, the command fails because version B is not in the catalog. Version A continues to exist.
- If DBRM1 and both versions A and B exist in the catalog, the command fails because version A already exists.

Defaults:

Process	Default value
BIND PLAN	REPLACE
BIND PACKAGE	REPLACE
REBIND PLAN	N/A
REBIND PACKAGE	N/A

Catalog record: Tables SYSPLAN or SYSPACKAGE.

CACHESIZE	<i>(value of field PLAN AUTH CACHE)</i> <i>(decimal-value)</i>	On: BIND and REBIND PLAN
------------------	---	---------------------------------

Determines the size (in bytes) of the authorization cache acquired in the EDM pool for the plan. At run time, the authorization cache stores user IDs authorized to run. Consulting the cache can avoid a catalog lookup for checking authorization to run the plan.

decimal-value

The size of the cache can range from 0 to 4096. Nonzero values that are not multiples of 256 round to the next highest multiple of 256. CACHESIZE(0) specifies creating no cache when the plan runs.

Defaults:

Process	Default value
BIND PLAN	Value of field PLAN AUTH CACHE on installation panel DSNTIPP, which has a default of 0

BIND PACKAGE

N/A

REBIND PLAN

Existing value

REBIND PACKAGE

N/A

Catalog record: Column CACHESIZE of table SYSPLAN.

For additional information on determining an optimal cache size, see Part 5 of *DB2 Application Programming and SQL Guide*.

COPY	<i>(collection-id.package-id)</i> <i>(collection-id.package-id)</i> COPYVER	On: BIND PACKAGE
-------------	---	-------------------------

Determines that you are copying an existing package and names that package. Copying the package recalculates the access paths in the copy.

To create a remote copy, this option copies SQL statements from a package at your local server. Therefore, you must hold the COPY privilege or its equivalent at the **local** server.

collection-id

The name of the collection that contains the package to copy, as listed in column COLLID of catalog table SYSPACKAGE.

package-id

The name of the package to copy, as listed in column NAME of catalog table SYSPACKAGE.

COPYVER(*version-id*)

Determines the version of the package to copy. The default for *version-id* is the empty string.

Restrictions:

- *collection-id.package-id* must identify a package on the local server.
- You cannot copy to a package in the same collection. If you make the copy on the local server, *collection-id.* on the COPY option must not name the collection used on the PACKAGE option.

Defaults:

Process

Default value

BIND PLAN

N/A

BIND PACKAGE

None

REBIND PLAN

N/A

REBIND PACKAGE

N/A

COPY has *no default*. If you do not use COPY, you must use MEMBER. You cannot use both options.

BIND PLAN (DSN)

The option values of the package copied (**except** the values of ENABLE, DISABLE, OWNER, and QUALIFIER) become the defaults for binding the new package. You can override a default by choosing a new value for an option on the BIND PACKAGE command.

Copy packages to remote servers: To copy and bind packages from DB2 Version 7 to some other server that does not support all the new BIND options in Version 7, use the new OPTIONS(COMMAND) option on BIND PACKAGE COPY. Any options you do not explicitly specify on the BIND PACKAGE subcommand are set to the server's defaults. Using this option can prevent bind errors when you bind and copy packages to servers other than DB2 Version 7.

Catalog record: Column COPY of table SYSPACKAGE.

CURRENTDATA	(YES) (NO)	On: BIND and REBIND PLAN and PACKAGE, REBIND TRIGGER PACKAGE
-------------	---------------	--

Determines whether to require data currency for read-only and ambiguous cursors when the isolation level of cursor stability is in effect. It also determines whether block fetching can be used for distributed, ambiguous cursors.

For more information about updating the current row of a cursor, block fetching, and data currency, see Part 4 of *DB2 Application Programming and SQL Guide*.

(YES) Specifies that currency is required for read-only and ambiguous cursors.

DB2 acquires page or row locks to ensure data currency. Block fetching for distributed, ambiguous cursors is inhibited.

(NO) Specifies that currency is not required for read-only and ambiguous cursors. Block fetching for distributed, ambiguous cursors is allowed.

If your application attempts to dynamically prepare and execute a DELETE WHERE CURRENT OF statement against an ambiguous cursor, after that cursor is opened, use of CURRENTDATA(NO) is not recommended. You receive a negative SQLCODE if your application attempts a DELETE WHERE CURRENT OF statement for any of the following cursors:

- A cursor that is using block fetching
- A cursor that is using query parallelism
- A cursor that is positioned on a row that is modified by this or another application process

Restriction for remote rebinds: You cannot use CURRENTDATA when rebinding a package at a remote server. To change the value of CURRENTDATA, you can:

- Issue BIND REPLACE, remotely or locally.
- Free the package and issue BIND ADD, remotely or locally.
- Rebind the package locally at the location where the package resides.

Defaults:

Process	Default value
BIND PLAN	YES
BIND PACKAGE	YES

REBIND PLAN

Existing value

REBIND PACKAGE

Existing value

Catalog record: Column DEFERPREP of table SYSPACKAGE and column EXPREDICATE of table SYSPLAN.

CURRENTSERVER	(location-name)	On: BIND and REBIND PLAN
---------------	-----------------	--------------------------

Determines the location to connect to before running the plan. The column CURRENTSERVER in catalog table SYSPLAN records the value of *location-name*. The special register CURRENT SERVER also receives that value at the server when the plan is allocated. When the plan runs, the requester implicitly uses a type 1 CONNECT statement to that location.

You should use CURRENTSERVER to cause a local application to use data from a remote server without changing the application. Avoid using CURRENTSERVER with applications that contain explicit CONNECT statements. The implicit type 1 CONNECT statement that is used by CURRENTSERVER causes any explicit CONNECT statement issued in the application to be type 1, even if the application was precompiled with the default type 2.

location-name

The name of the location to connect to. The catalog table SYSIBM.LOCATIONS must contain this name. If the table does not exist, if the table does not contain the DBMS, or if there are no packages at that location, warning messages occur.

SQL return codes: CURRENTSERVER causes DB2 to execute a type 1 CONNECT statement. DB2 does not display or report to the application program any warnings that this CONNECT returns. To display the warnings, use explicit CONNECT statements rather than the CURRENTSERVER bind option.

Defaults:

Process

Default value

BIND PLAN

Local DBMS (regardless of the name of the local location)

BIND PACKAGE

N/A

REBIND PLAN

Existing value

REBIND PACKAGE

N/A

Catalog record: Column CURRENTSERVER of table SYSPLAN.

DBPROTOCOL	(DRDA) (PRIVATE)	On: BIND and REBIND PLAN and PACKAGE
------------	---------------------	--------------------------------------

Specifies which protocol to use when connecting to a remote site that is identified by a three-part name statement.

BIND PLAN (DSN)

For DRDA, a package must be bound to each remote site that is referenced by a three-part name statement. Specify DRDA® to inform DB2 that the three-part name statements in the plan or package are to be converted to DRDA protocol.

If you specify an option on the BIND PACKAGE command, DB2 uses that remote access method for the package statements, regardless of the BIND PLAN option. For remote bind, the default is the system default at the remote site.

If you specify an option on the BIND PLAN statement, that information is stored in table SYSPLAN.

(DRDA)

DBPROTOCOL DRDA is passed on BIND PACKAGE, BIND PLAN, REBIND PACKAGE, or REBIND PLAN invocation.

(PRIVATE)

DBPROTOCOL PRIVATE is passed on BIND PACKAGE, BIND PLAN, REBIND PACKAGE, or REBIND PLAN invocation.

Defaults:

Process	Default value
BIND PLAN	DRDA
BIND PACKAGE	System default
REBIND PLAN	Value that was specified the last time the plan was bound
REBIND PACKAGE	Value that was specified the last time the package was bound

Catalog record: Column DBPROTOCOL of tables SYSPACKAGE and SYSPLAN.

DEFER(PREPARE) NODEFER(PREPARE)	On: BIND and REBIND PLAN and PACKAGE
<p>Determines whether to defer preparation for dynamic SQL statements that refer to remote objects, or to prepare them immediately. If you defer preparation, the dynamic statement prepares when DB2 first encounters a statement of the type EXECUTE, OPEN, or DESCRIBE that refers to the dynamic statement.</p> <p>For BIND and REBIND PACKAGE, if neither option is specified, and NOREOPT(VARS) applies:</p> <ul style="list-style-type: none">• For local bind the package inherits the plan's option at runtime.• For remote bind the default is NODEFER(PREPARE) at the remote DB2 server. <p>If neither DEFER nor NODEFER is specified and REOPT(VARS) applies, DEFER(PREPARE) is the default value.</p> <p>You cannot use both DEFER(PREPARE) and NODEFER(PREPARE). In addition, you cannot use both NODEFER(PREPARE) and REOPT(VARS).</p> <p>NODEFER(PREPARE) Does not defer preparation.</p> <p>DEFER(PREPARE) Defers preparation.</p>	

DEFER(PREPARE) and distributed processing: To improve performance, consider using DEFER(PREPARE) when binding dynamic or static SQL for DB2 private protocol access and when binding dynamic SQL for DRDA access. Specify the bind option DEFER(PREPARE) instead of NODEFER(PREPARE). DB2 does not prepare the dynamic SQL statement until that statement executes. This reduces network traffic, which improves the performance of the dynamic SQL statement.

To defer the preparation of an SQL statement in an application, bind or rebind the application with the option DEFER(PREPARE). This defers PREPARE messages for SQL statements that refer to a remote object until either:

- The statement executes
- The application requests a description of the results of the statement

If you choose to defer PREPARE statements, after the EXECUTE or DESCRIBE statement, you should code your application to handle any SQL error codes or SQLSTATEs that the PREPARE statement might return. You can defer PREPARE statements only if you specify the bind option DEFER(PREPARE).

Defaults:

Process	Default value
BIND PLAN	NODEFER
BIND PACKAGE	Plan value
REBIND PLAN	Existing value
REBIND PACKAGE	Existing value

Catalog record: Column DEFERPREP of table SYSPLAN and column DEFERPREPARE of table SYSPACKAGE.

DEGREE	(1) (ANY)	On: BIND and REBIND PLAN and PACKAGE
---------------	--------------	---

Determines whether to attempt to run a query using parallel processing to maximize performance.

For plans, the value of DEGREE applies only to the DBRMs bound directly to the plan (named in the MEMBER option on BIND PLAN), and has no effect on PKLIST names. The value has no effect on dynamic SQL statements, which use the value of the special register CURRENT DEGREE. The value of the special register can be changed by executing the SET CURRENT DEGREE statement.

- (1) Prohibits parallel processing.
(ANY) Allows parallel processing.

Limitations: If you bind plans or packages using DEGREE=ANY, the space required in the EDM pool could increase by 50%–70%.

Defaults:

Process	Default value
----------------	----------------------

BIND PLAN (DSN)

BIND PLAN
1
BIND PACKAGE
1
REBIND PLAN
Existing value
REBIND PACKAGE
Existing value

Catalog record: Column DEGREE of tables SYSPACKAGE and SYSPLAN.

DISCONNECT	(EXPLICIT) (AUTOMATIC) (CONDITIONAL)	On: BIND and REBIND PLAN
-------------------	--	---------------------------------

Determines which remote connections to destroy during commit operations. The option applies to any application process that uses the plan and has remote connections of any type. Regardless of the value of this option, a commit operation destroys all connections in the release pending state. You can put a connection in the release pending state using the SQL statement RELEASE.

(EXPLICIT)

Destroy only connections in the release pending state. This value allows you maximum flexibility for controlling remote connections.

(AUTOMATIC)

Destroy all remote connections.

(CONDITIONAL)

Destroy all remote connections unless an open cursor defined as WITH HOLD is associated with the connection.

Defaults:

Process
Default value
BIND PLAN
EXPLICIT
BIND PACKAGE
N/A
REBIND PLAN
Existing value
REBIND PACKAGE
N/A

Catalog record: Column DISCONNECT of table SYSPLAN.

DYNAMICRULES	(RUN) (BIND) (DEFINEBIND) (BIND and REBIND PACKAGE only) (DEFINERUN) (BIND and REBIND PACKAGE only) (INVOKEBIND) (BIND and REBIND PACKAGE only) (INVOKERUN) (BIND and REBIND PACKAGE only)	On: BIND and REBIND PLAN and PACKAGE
---------------------	---	---

Determines what values apply at run time for the following dynamic SQL attributes:

- The authorization ID that is used to check authorization
- The qualifier that is used for unqualified objects
- The source for application programming options that DB2 uses to parse and semantically verify dynamic SQL statements

- Whether dynamic SQL statements can include GRANT, REVOKE, ALTER, CREATE, DROP, and RENAME statements

In addition to the DYNAMICRULES value, the run-time environment of a package controls how dynamic SQL statements behave at run time. The two possible run-time environments are:

- The package runs as part of a stand-alone program
- The package runs as a stored procedure or user-defined function package, or runs under a stored procedure or user-defined function

The combination of the DYNAMICRULES value and the run-time environment determine the values for the dynamic SQL attributes. That set of attribute values is called the dynamic SQL statement *behavior*. The four behaviors are:

- Run behavior
- Bind behavior
- Define behavior
- Invoke behavior

The following DYNAMICRULES option descriptions include a description of the dynamic SQL statement behavior for each run-time environment. This information is summarized in Table 12 on page 55.

- (RUN)** Processes dynamic SQL statements using the standard attribute values for dynamic SQL statements, which are collectively called ***run behavior***.
- DB2 uses the authorization ID of the application process and the SQL authorization ID (the value of the CURRENT SQLID special register) for authorization checking of dynamic SQL statements.
 - DB2 uses the authorization ID of the application process and the SQL authorization ID (the value of the CURRENT SQLID special register) as the implicit qualifier of table, view, index, and alias names.
 - Dynamic SQL statements use the values of application programming options that were specified during installation. The installation option USE FOR DYNAMICRULES has no effect.
 - GRANT, REVOKE, CREATE, ALTER, DROP, and RENAME statements can be executed dynamically.

- (BIND)** Processes dynamic SQL statements using the following attribute values, which are collectively called ***bind behavior***.
- DB2 uses the authorization ID of the plan or package for authorization checking of dynamic SQL statements.
 - Unqualified table, view, index, and alias names in dynamic SQL statements are implicitly qualified with value of the bind option QUALIFIER; if you do not specify QUALIFIER, DB2 uses the authorization ID of the plan or package owner as the implicit qualifier.
 - The attribute values that are described in “Common attribute values for bind, define, and invoke behaviors” on page 55.

The values of the authorization ID and the qualifier for unqualified objects are the same as those that are used for embedded or static SQL statements.

- (DEFINEBIND)** Processes dynamic SQL statements using one of two behaviors, ***define behavior*** or ***bind behavior***.

BIND PLAN (DSN)

When the package is run as or runs under a stored procedure or user-defined function package, DB2 processes dynamic SQL statements using define behavior, which consists of the following attribute values:

- DB2 uses the authorization ID of the user-defined function or stored procedure owner for authorization checking of dynamic SQL statements in the application package.
- The default qualifier for unqualified objects is the user-defined function or stored procedure owner.
- The attribute values that are described in “Common attribute values for bind, define, and invoke behaviors” on page 55.

When the package is run as a stand-alone program, DB2 processes dynamic SQL statements using bind behavior, which is described in 53.

(DEFINERUN)

Processes dynamic SQL statements using one of two behaviors, ***define behavior*** or ***run behavior***.

When the package is run as or runs under a stored procedure or user-defined function package, dynamic SQL statements have define behavior, which is described in 53.

When the package is run as a stand-alone program, DB2 processes dynamic SQL statements using run behavior, which is described in 53.

(INVOKEBIND)

Processes dynamic SQL statements using one of two behaviors, ***invoke behavior*** or ***bind behavior***.

When the package is run as or runs under a stored procedure or user-defined function package, DB2 processes dynamic SQL statements using invoke behavior, which consists of the following attribute values:

- DB2 uses the authorization ID of the user-defined function or stored procedure invoker for authorization checking of dynamic SQL statements in the application package.
If the invoker is the primary authorization ID of the process or the CURRENT SQLID value, secondary authorization IDs are also checked if they are needed for the required authorization. Otherwise, only one ID, the ID of the invoker, is checked for the required authorization.
- The default qualifier for unqualified objects is the user-defined function or stored procedure invoker.
- The attribute values that are described in “Common attribute values for bind, define, and invoke behaviors” on page 55.

When the package is run as a stand-alone program, DB2 processes dynamic SQL statements using bind behavior, which is described in 53.

(INVOKERUN)

Processes dynamic SQL statements using one of two behaviors, ***invoke behavior*** or ***run behavior***.

When the package is run as or runs under a stored procedure or user-defined function package, DB2 processes dynamic SQL statements using invoke behavior, which is described in 54.

When the package is run as a stand-alone program, DB2 processes dynamic SQL statements using run behavior, which is described in 53.

Common attribute values for bind, define, and invoke behavior. The following attribute values apply to dynamic SQL statements in plans or packages that have bind, define, or invoke behavior:

- You can execute the statement SET CURRENT SQLID in a package or plan that is bound with any DYNAMICRULES value. However, DB2 does not use the value of CURRENT SQLID as the authorization ID for dynamic SQL statements.
DB2 always uses the value of CURRENT SQLID as the qualifier for the EXPLAIN output PLAN_TABLE.
- If the value of installation option USE FOR DYNAMICRULES is YES, DB2 uses the application programming default values that were specified during installation to parse and semantically verify dynamic SQL statements. If the value of USE for DYNAMICRULES is NO, DB2 uses the precompiler options to parse and semantically verify dynamic SQL statements. For a list of the application programming defaults that the USE FOR DYNAMICRULES option affects, see Part 5 of *DB2 Application Programming and SQL Guide*.
- GRANT, REVOKE, CREATE, ALTER, DROP, and RENAME statements cannot be executed dynamically.

Remote DB2 servers: For a package that uses DRDA access, DB2 sends the DYNAMICRULES option to the DB2 server at bind time.

For a plan or package that uses DB2 private protocol access, DB2 sends a DYNAMICRULES value of BIND or RUN to the server at run time, using the following rules:

- If the DYNAMICRULES value with which the package is bound is BIND, DEFINEBIND, or INVOKEBIND, DB2 sends a value of BIND to the server.
- If the DYNAMICRULES value with which the package is bound is RUN, DEFINERUN, or INVOKERUN, DB2 sends a value of RUN to the server.

Table 12 summarizes the dynamic SQL statement attribute values for each behavior. For more information about the dynamic SQL attributes that are affected by the DYNAMICRULES option, see Part 5 of *DB2 Application Programming and SQL Guide*.

Table 12. Definitions of dynamic SQL statement behaviors

Dynamic SQL attribute	Value for dynamic SQL attributes			
	Bind behavior	Run behavior	Define behavior	Invoke behavior
Authorization ID	Package OWNER	Current SQLID	User-defined function or stored procedure owner	Authorization ID of invoker
Default qualifier for unqualified objects	Bind OWNER or QUALIFIER value	Current SQLID	User-defined function or stored procedure owner	Authorization ID of invoker
CURRENT SQLID	Initialized to Primary authid. SET SQLID is allowed.	Initialized to Primary authid. SET SQLID is allowed.	Initialized to Primary authid. SET SQLID is allowed.	Initialized to Primary authid. SET SQLID is allowed.
Source for application programming options	As determined by the DSNHDECP parameter DYNRULS	Install panel DSNHDECP application defaults	As determined by the DSNHDECP parameter DYNRULS	As determined by the DSNHDECP parameter DYNRULS
Can execute GRANT, REVOKE, CREATE, ALTER, DROP, RENAME?	No	Yes	No	No

BIND PLAN (DSN)

Defaults:

Process	Default value
BIND PLAN	RUN
BIND PACKAGE	Plan value
REBIND PLAN	Existing value
REBIND PACKAGE	Existing value

The default for a package on a remote server is RUN.

Catalog record: Column DYNAMICRULES of tables SYSPACKAGE and SYSPLAN.

<u>ENABLE</u> <u>DISABLE</u>	(*)	On: BIND and REBIND PLAN and PACKAGE
	(BATCH)	
	(CICS)	
	(CICS) CICS(<i>applid</i> , ...)	
	(DB2CALL)	
	(DLIBATCH)	
	(DLIBATCH) DLIBATCH(<i>connection-name</i> , ...)	
	(IMS)	
	(IMSBMP)	
	(IMSBMP) IMSBMP(<i>imsid</i> , ...)	
	(IMSMPP)	
	(IMSMPP) IMSMPP(<i>imsid</i> , ...)	
	(REMOTE) (BIND and REBIND PACKAGE only)	
	(REMOTE) REMOTE (<i>location-name</i> ,..., < <i>luname</i> >,...)	
	(RRSAF)	

Determines which connections can use the plan or package. You cannot use both DISABLE and ENABLE. For packages, DISABLE and ENABLE are valid only for local bind operations.

ENABLE

Lists the system connection types that can use the plan or package. Connection types not listed cannot use it.

DISABLE

Lists the system connection types that cannot use the plan or package. Connection types not listed can use it.

With some connection types you can list connection IDs to identify specific connections of the type to disable or enable.

If you list connection IDs as disabled, any connections not listed for the same connection type are enabled.

If you list connection IDs as enabled, any connections not listed for the same connection type are disabled.

A connection ID is valid only after the keyword that names its corresponding connection type.

Connection types:

(*) Specifies all valid connection types. Use only with ENABLE.

(BATCH)

Indicates that all TSO connections are either enabled or disabled for the plan or package.

(CICS)

Identifies the CICS connection. All CICS VTAM node names specified in the CICS SIT table are either enabled or disabled for the plan or package.

(CICS) CICS(*applid*, ...)

Identifies the CICS VTAM node name specified in the APPLID parameter of the CICS SIT table. The CICS VTAM node identified by *applid* is either enabled or disabled for the plan or package.

(DB2CALL)

Indicates that the call attachment facility (CAF) connection is either enabled or disabled for the plan or package.

(DLIBATCH)

Identifies the Data Language I (DL/I) Batch Support Facility connection. All connection identifiers from the DDITV02 data set or the job name in the JCL that the DL/I batch support system needs to have are either enabled or disabled for the plan or package.

(DLIBATCH) DLIBATCH(*connection-name*, ...)

Specifies the connection identifier as from the DDITV02 data set or the job name in the JCL that the DL/I batch support system needs to have. The DL/I batch connection identified by *connection-name* is either enabled or disabled for the plan or package.

(IMS)

Specifies that all Information Management System (IMS) connections, DLIBATCH, IMSBMP, and IMSMPP are either enabled or disabled for the plan or package.

(IMSBMP)

Specifies the IMS connection for the Batch Message Program (BMP) region. All IMS BMP connections identified by the value of IMSID on the CTL parameter EXEC are either enabled or disabled for the plan or package.

(IMSBMP) IMSBMP(*imsid*, ...)

Specifies the value of IMSID on the CTL parameter EXEC. The IMS BMP connection identified by *imsid* is either enabled or disabled for the plan or package.

(IMSMPP)

Specifies the IMS connection for the Message Processing Program (MPP) and IMS Fast Path (IFP) regions. All IMS MPP connections identified by the value of the IMSID on the CTL parameter EXEC. are either enabled or disabled for the plan or package.

(IMSMPP) IMSMPP(*imsid*, ...)

Specifies the value of IMSID on the CTL parameter EXEC. The IMS MPP connection identified by *imsid* is either enabled or disabled for the plan or package.

(REMOTE)

Indicates that all remote connections are either enabled or disabled for the plan or package.

(REMOTE) REMOTE (*location-name*,...,< *luname*>,...)

(PACKAGE only)

Specifies that the remote connections identified by the following are either enabled or disabled for the package:

BIND PLAN (DSN)

location-name

Specifies the location name of a requesting DBMS that **is** a DB2 for OS/390 and z/OS subsystem.

< luname>

Specifies the logical unit name, as defined to VTAM at the server location, of a requesting DBMS that **is not** a DB2 for OS/390 and z/OS subsystem.

You must bracket a logical unit name with the less than (<) and the greater than (>) characters to differentiate it from a location name.

(RRSAF)

Indicates that the RRS attachment facility connection is either enabled or disabled for the plan or package.

Performance hint: Whenever the plan or package is allocated, DB2 must check the connection type and connection name with the list of enabled or disabled connections. For best performance, keep the list short.

Plans that disable a system: If a plan disables a system, then no packages appended to that plan can run from that system, regardless of the ENABLE/DISABLE options. However, if the same packages are appended to other plans that enable the system, those packages can run from that system under those plans.

Defaults:

Process

Default value

BIND PLAN

ENABLE(*)

BIND PACKAGE

ENABLE(*)

REBIND PLAN

Existing value

REBIND PACKAGE

Existing value

Catalog record: Table SYSPKSYSTEM for packages and table SYSPLSYSTEM for plans.

ENCODING	(ASCII) (EBCDIC) (UNICODE) (ccsid)	On: BIND and REBIND PLAN and PACKAGE
----------	---	--------------------------------------

Specifies the application encoding for all host variables static statements in the plan or package. EBCDIC is the only valid option for a plan or package that was precompiled on DB2 Version 6 or earlier.

Defaults: The default package application encoding scheme is not inherited from the plan application encoding option. The default for a package that is bound on a remote DB2 for OS/390 is the system default application encoding scheme at the remote server.

Process

Default value

BIND PLAN

The system default application encoding scheme that was specified at installation time.

BIND PACKAGE

The system default application encoding scheme that was specified at installation time.

REBIND PLAN

The value that was specified the last time that the plan or package was bound.

REBIND PACKAGE

The value that was specified the last time that the plan or package was bound.

Product-sensitive Programming Interface

EXPLAIN	(NO) (YES)	On: BIND and REBIND PLAN and PACKAGE, REBIND TRIGGER PACKAGE
---------	---------------	--

Obtains information about how SQL statements in the package, or in the member list of the plan, are to execute, and then inserts that information into the table *owner.PLAN_TABLE*, where *owner* is the authorization ID of the owner of the plan or package. This option does not obtain information for statements that access remote objects.

PLAN_TABLE must be a table; it cannot be a view, alias, or synonym. It should exist before the bind process begins.

The EXPLAIN option also populates two optional tables, if they exist: DSN_STATEMNT_TABLE and DSN_FUNCTION_TABLE.

DSN_STATEMNT_TABLE contains DB2's estimate of the processing cost for an SQL statement. See Part 6 of *DB2 Application Programming and SQL Guide* for more information.

DSN_FUNCTION_TABLE contains information about function resolution. See Part 3 of *DB2 Application Programming and SQL Guide* for more information.

You can get EXPLAIN output for a statement that is embedded in a program that is bound with EXPLAIN(NO) by embedding the SQL statement EXPLAIN in the program. Otherwise, the value of the EXPLAIN option applies to all explainable SQL statements in the program, and to the fullselect portion of any DECLARE CURSOR statements.

In all inserts to *owner.PLAN_TABLE*, the value of QUERYNO is the statement number that the precompiler assigned and placed in the DBRM.

For a description of the tables populated by the EXPLAIN option, see information about the EXPLAIN statement in Chapter 5 of *DB2 SQL Reference*.

For automatic rebind: EXPLAIN(YES) is in effect if you bind the plan or package with EXPLAIN(YES) and if the value of field EXPLAIN PROCESSING on installation panel DSNTIPO is YES. If EXPLAIN(YES) and VALIDATE(BIND) are in effect and PLAN_TABLE is not correct, the automatic rebind fails.

(NO) Provides no EXPLAIN information.

(YES) Inserts information in the tables populated by EXPLAIN. If

BIND PLAN (DSN)

owner.PLAN_TABLE does not exist at bind time, the value of the option VALIDATE determines the success of the bind operation.

- If the value is BIND, the bind fails.
- If the value is RUN, DB2 checks to see if the table exists again at run time. If it still does not exist, the plan or package cannot run. If it does exist, DB2 inserts information in PLAN_TABLE before the plan or package runs.

If neither or both of the optional tables DSN_FUNCTION_TABLE or DSN_STATEMNT_TABLE exist, or if they are defined incorrectly, the bind does not fail.

Invalidation resulting from an unsuccessful rebind: An unsuccessful rebind generating a return code of greater than 4 invalidates the rebind object and rolls back all changes to the object, leaving it as it was before the rebind attempt. However, if the rebind fails because of either the REBIND option EXPLAIN or the SQL statement EXPLAIN (that is, the PLAN_TABLE does not exist or was created incorrectly), DB2 rolls back all changes to the object but does not invalidate the object.

Defaults:

Process	Default value
BIND PLAN	NO
BIND PACKAGE	NO
REBIND PLAN	Existing value
REBIND PACKAGE	Existing value

Catalog record: Column EXPLAIN of table SYSPACKAGE and column EXPLAN of SYSPLAN.

_____ **End of Product-sensitive Programming Interface** _____


FLAG	(I) (W) (E) (C)	On: BIND and REBIND PLAN and PACKAGE, REBIND TRIGGER PACKAGE
------	--------------------------	--

Determines what messages to display.

- (I) All informational, warning, error, and completion messages
- (W) Only warning, error, and completion messages
- (E) Only error and completion messages
- (C) Only completion messages

Rebinding multiple plans or packages: When your REBIND command contains an asterisk (*) and affects many plans or packages, FLAG(E) is recommended to avoid running out of message storage.

Defaults:



IMMEDWRITE	(NO) (PH1) (YES)	On: BIND and REBIND PLAN and PACKAGE
------------	------------------------	--------------------------------------

Tells whether immediate writes will be done for updates made to group buffer pool dependent pagesets or partitions. This option is only applicable for data sharing environments. Table 13 shows the implied hierarchy of this option. The IMMEDIATEWRITE option values are as follows:

(NO) Specifies that normal write activity is done. Updated pages that are group buffer pool dependent are written at or before phase two of commit or at the end of abort for transactions that have rolled back.

(PH1) Specifies that updated pages that are group buffer pool dependent are written at or before phase one of commit. If the transaction subsequently rolls back, the pages will be updated again during the rollback process, and they will be written again at the end of abort.

(YES) Specifies that updated pages that are group buffer pool dependent are immediately written as soon as the buffer update completes. Updated pages are written immediately even if the buffer is updated during forward progress or during rollback of a transaction. Specifying this option may impact performance.

Table 13. The implied hierarchy of the IMMEDIATEWRITE option

IMMEDWRITE bind option	IMMEDWRI subsystem parameter	Value at run time
NO	NO	NO
NO	PH1	PH1
NO	YES	YES
PH1	NO	PH1
PH1	PH1	PH1
PH1	YES	YES
YES	NO	YES
YES	PH1	YES
YES	YES	YES

Performance hints: You can use IMMEDIATEWRITE(PH1) and IMMEDIATEWRITE(YES) for situations where a transaction spawns another transaction that can run on another DB2 member and that depends on uncommitted updates that were made by the originating transaction.

Specify IMMEDIATEWRITE(PH1) to cause group buffer pool dependent pages to be written at or before phase 1 of commit.

BIND PLAN (DSN)

Specify IMMEDIATEWRITE(YES) to cause the originating transaction to immediately write its updated GBP-dependent buffers (instead of waiting until the end of commit or rollback), which will ensure that the dependent transaction always gets the same results regardless of whether it runs on the same member or a different member as the originating transaction. IMMEDIATEWRITE(YES) should be used with caution because of its potential impact to performance. The impact will be more significant for plans and packages that do many buffer updates to GBP-dependent pages, and not as noticeable for plans or packages that perform few buffer updates to GBP-dependent pages. The following options can be considered as alternatives to using IMMEDIATEWRITE(YES):

- Always run the dependent transaction on the same DB2 member as the originating transaction.
- Run the dependent transaction with ISOLATION(RR).
- Wait until the completion of phase two of commit before spawning the dependent transaction.
- CURRENTDATA(YES) or ISOLATION(RS) can be used to solve the problem only if the originating transaction updates columns that are not in the WHERE clause of the dependent transaction.

Defaults:

Process	Default value
BIND PLAN	NO
BIND PACKAGE	NO
REBIND PLAN	Existing value
REBIND PACKAGE	Existing value

The default for a package on a remote DB2 server is IMMEDIATEWRITE(NO).

ISOLATION	(RR)	On: BIND and REBIND PLAN and PACKAGE, REBIND TRIGGER PACKAGE
	(RS)	
	(CS)	
	(UR)	
	(NC)	

Determines how far to isolate an application from the effects of other running applications. For more information on isolation levels, see Improving Concurrency in Part 5 (Volume 2) of DB2 Administration Guide.

(RR) *Repeatable read.* Ensures that:

- Your application does not read a row that another process has changed until that process releases that row.
- Other processes do not change a row that your application reads until your application commits or terminates.

(RS) *Read stability.* Ensures that:

- Your application does not read a row that another process has changed until that process releases that row.
- Other processes do not change a row that satisfies the application's search condition until your application commits or terminates. It does

BIND PLAN (DSN)

allow other application processes to insert a row, or to change a row that did not originally satisfy the search condition.

If the server does not support RS, it uses RR.

- (CS)** *Cursor stability.* Ensures, like repeatable read, that your application does not read a row that another process changes until that process releases that row. Unlike repeatable read, cursor stability does not prevent other applications from changing rows that your application reads before your program commits or terminates.
- (UR)** *Uncommitted read.* Unlike repeatable read and cursor stability, does not ensure anything. With the exception of LOB data, uncommitted read avoids acquiring locks on data and allows:
- Other processes change any row your application reads during the unit of work.
 - Your application read any row that another process has changed, even if the process has not committed the row.

You can use this option only with a read-only operation: SELECT, SELECT INTO, or FETCH using a read-only cursor. If you specify ISOLATION(UR) for any other operation, DB2 uses ISOLATION(CS) for that operation.

- (NC)** *No commit.* Used on packages that are bound to certain servers other than DB2 for OS/390 and z/OS. DB2 for OS/390 and z/OS does not support NC. If the server does not support this isolation level, it uses UR.

For more information about how the ISOLATION option affects locking and concurrency, including how DB2 resolves conflicts by using the most restrictive value when the values specified in the plan and package differ, see Part 4 of *DB2 Application Programming and SQL Guide*.

Defaults:

Process	Default value
BIND PLAN	RR
BIND PACKAGE	Plan value
REBIND PLAN	Existing value
REBIND PACKAGE	Existing value

The default for binding a package to a remote server is **RR**.

For REBIND PACKAGE, you cannot change ISOLATION from a specified value to a default of the plan value by using REBIND PACKAGE. To do that, you must use BIND PACKAGE ACTION(REPLACE).

Catalog record: Column ISOLATION of tables SYSPACKAGE and SYSPLAN.

KEEPDYNAMIC	(NO) (YES)	On: BIND and REBIND PLAN and PACKAGE
-------------	---------------	--------------------------------------

Determines whether DB2 keeps dynamic SQL statements after commit points.

BIND PLAN (DSN)

(NO) Specifies that DB2 does not keep dynamic SQL statements after commit points.

(YES) Specifies that DB2 keeps dynamic SQL statements after commit points.

If you specify KEEP_DYNAMIC(YES), the application does not need to prepare an SQL statement after every commit point. DB2 keeps the dynamic SQL statement until one of the following occurs:

- The application process ends
- A rollback operation occurs.
- The application executes an explicit PREPARE statement with the same statement identifier.

If you specify KEEP_DYNAMIC(YES), and the prepared statement cache is active, DB2 keeps a copy of the prepared statement in the cache. If the prepared statement cache is not active, DB2 keeps only the SQL statement string past a commit point. DB2 then implicitly prepares the SQL statement if the application executes an OPEN, EXECUTE, or DESCRIBE operation for that statement.

If you specify KEEP_DYNAMIC(YES), you must not specify REOPT(VARS). KEEP_DYNAMIC(YES) and REOPT(VARS) are mutually exclusive.

Performance hint: KEEP_DYNAMIC(YES) results in improved performance if your DRDA client application uses a cursor defined WITH HOLD. DB2 automatically closes a held cursor when there are no more rows to retrieve, which eliminates an extra network message.

Defaults:

Process	Default value
BIND PLAN	NO
BIND PACKAGE	NO
REBIND PLAN	Existing value
REBIND PACKAGE	Existing value

The default for a package on a remote DB2 server is KEEP_DYNAMIC(NO).

Catalog record: Column KEEP_DYNAMIC of table SYSPLAN and SYSPACKAGE.

LIBRARY		On: BIND PLAN, BIND PACKAGE
	(dbrm-pds-name) (dbrm-pds-name, ...) (BIND PLAN only)	

Determines what partitioned data sets (libraries) to search for the DBRMs listed in the MEMBER option. The libraries must be cataloged.

The bind process searches for the libraries in the order that you list them. If the libraries do not contain some DBRM listed in the MEMBER option, and if a JCL statement exists for DBRMLIB DD, then the process searches for the member among the libraries that the JCL statement describes.

dbrm-pds-name is the data set name of a library.

For **BIND PACKAGE**, you can specify only one library to search.

For **BIND PLAN**, you can specify one or more libraries to search.

Defaults:

Process	Default value
BIND PLAN	None
BIND PACKAGE	None
REBIND PLAN	N/A
REBIND PACKAGE	N/A

The default is to search only the libraries described by the DD statement for DBRMLIB.

MEMBER	(<i>dbrm-member-name</i>) (<i>dbrm-member-name</i> , ...) (BIND PLAN only)	On: BIND PLAN , BIND PACKAGE
--------	--	--

Determines what database request modules (DBRMs) to include in the plan or package.

dbrm-member-name

Specifies the name of a library member that contains a DBRM. You can name the partitioned data set, of which a DBRM is a member, either in the LIBRARY option or in the JCL statement for DBRMLIB DD.

For **BIND PACKAGE** only, the name becomes the package name. Names beginning with DSN are reserved; you receive a warning message if you use one.

For **BIND PACKAGE**, you can use only one member. If you do not use **MEMBER**, you must use **COPY**. You cannot use both options.

For **BIND PLAN**, you can list many members. DB2 sorts the member list in alphabetical order. If you do not use **MEMBER**, you must use **PKLIST**.

Defaults:

Process	Default value
BIND PLAN	None
BIND PACKAGE	None
REBIND PLAN	N/A
REBIND PACKAGE	N/A

Catalog record: Column NAME of table SYSPACKAGE for **BIND PACKAGE**, or the table SYSDBRM for **BIND PLAN**.

BIND PLAN (DSN)

OPTHINT	('hint-id')	On: BIND and REBIND PLAN and PACKAGE
---------	-------------	--------------------------------------

Controls whether query optimization hints are used for static SQL.

('hint-id')

A character string of up to eight characters in length, which is used by the optimizer when searching the PLAN_TABLE for rows to use as input to the optimizer. The delimiters can only be single quotation marks (').

If 'hint-id' contains all blank characters, DB2 does not use optimization hints for static SQL statements.

DB2 uses optimization hints only when optimization hints are enabled for your system. To enable optimization hints, specify YES in the OPTIMIZATION HINTS field of installation panel DSNTIP4.

For more information about using the OPTHINT option, see Part 5 (Volume 2) of *DB2 Administration Guide*.

Restriction: The PACKAGE does not inherit from the PLAN.

Defaults:

Process

Default value

BIND PLAN

All blanks, use normal optimization

BIND PACKAGE

All blanks, use normal optimization

REBIND PLAN

Existing value

REBIND PACKAGE

Existing value

The default for a package on a remote server is all blanks.

Catalog record: Column OPTHINT of tables SYSPLAN and SYSPACKAGE.

OPTIONS(COMPOSITE) OPTIONS(COMMAND)	On: BIND PACKAGE COPY
--	-----------------------

Specifies which bind options to use for the new package.

COMPOSITE

The options for the new package are what you specify on the BIND PACKAGE COPY subcommand. Options that you do not specify are the option values taken from the SYSPACKAGE catalog table row that describes the source package to be copied.

COMMAND

The options for the new package are what you specify on the BIND PACKAGE COPY subcommand. Options that you do not specify are determined as follows:

- For a local copy, the DB2-defined BIND PACKAGE options defaults are used.

BIND PLAN (DSN)

- For a remote copy, the server-defined BIND PACKAGE options defaults are used at the server. You must use the OPTIONS(COMMAND) when copying to a downlevel server. A down-level server is any server that is not DB2 Version 7.

Defaults:

Process
Default value
BIND PACKAGE COPY
OPTIONS(COMPOSITE)

OWNER	(<i>authorization-id</i>)	On: BIND and REBIND PLAN and PACKAGE
--------------	-----------------------------	---

Determines the authorization ID of the owner of the object (plan or package). The owner must have the privileges required to execute the SQL statements contained in the object.

If ownership changes, all grants for privileges on the object that the previous owner issued change to name the new owner as the grantor. The new owner has the privileges BIND and EXECUTE on the object and grants them to the previous owner.

You can bind or rebind only the objects for which the authorization ID has bind privileges. If you do not specify an authorization ID, the process rebinds only the objects for which the primary ID has bind privileges.

For remote BIND or REBIND PACKAGE only, the value of OWNER is subject to translation when sent to the remote system.

Defaults:

Process
Default value
BIND PLAN
Primary ID
BIND PACKAGE
Primary ID
REBIND PLAN
Existing value
REBIND PACKAGE
Existing value

The default owner is the primary authorization ID of the agent that runs the bind process.

Catalog record: Column OWNER of table SYSPACKAGE, column GRANTOR of table SYSPACKAUTH, and column CREATOR of table SYSPLAN.

PACKAGE	(<i>location-name.collection-id.package-id.(version-id)</i>) (*) (REBIND PACKAGE only)	On: BIND and REBIND PACKAGE
----------------	---	------------------------------------

Determines what package or packages to bind or rebind.

You cannot use the BIND PACKAGE subcommand to:

- Bind a package with the same name as an existing trigger package

BIND PLAN (DSN)

- Copy a trigger package

The following options identify the location, collection, package name, and version of the package. You can identify a location and collection. For BIND, the DBRM supplies the package ID and version ID if you use the option MEMBER, or those IDs come from the option COPY. For REBIND, you must identify a package name, and you can also supply a version ID.

location-name

The location of the DBMS where the package binds or rebinds and where the description of the package resides. The location name must be defined in catalog table SYSIBM.LOCATIONS. If that table does not exist or if the DBMS is not in it, you receive an error message.

The default is the local DBMS.

collection-id or *

Specifies the collection to contain the package to bind, or that already contains the package to rebind. There is no default.

For REBIND, you can use an asterisk (*) to rebind all local packages with the specified *package-id* in all the collections for which you have bind privileges.

package-id or * **(For REBIND only)**

Specifies the name of the package to rebind, as listed in column NAME of catalog table SYSPACKAGE. There is no default.

You can use an asterisk (*) to rebind all local packages in *collection-id* for which you have bind privileges.

version-id or * **(For REBIND only)**

Specifies the version of the package to rebind, as listed in column VERSION of catalog table SYSPACKAGE.

You can use an asterisk (*) to rebind all local versions of the specified *package-id* in *collection-id* for which you have bind privileges.

Using simply () rebinds the version of the package that is identified by the empty string.

If you omit *version-id*, the default depends on the how you specify *package-id*. If you use * for *package-id*, then *version-id* defaults to *. If you explicitly provide a value for *package-id*, then *version-id* defaults to the empty string version.

DBRMs created in releases of DB2 before Version 2 Release 3 use a *version-id* of the empty string by default.

(*) (For REBIND only)

Rebinds all local DB2 packages for which the applicable authorization ID has the BIND privilege. Specifying (*) is the same as specifying the package name as (*.*(*)) or (*.*). The applicable authorization ID is:

- The value of OWNER, if you use that option
- The primary authorization ID of the process running the bind, if you do not use the option OWNER

Catalog record: Columns COLLID, NAME, and VERSION of table SYSPACKAGE.

For more information about:

- How to define a location name in SYSIBM.LOCATIONS, see Part 3 of *DB2 Administration Guide*.

- Which packages are bound depending on how you specify collections, packages, and versions on the REBIND PACKAGE command, see Part 4 of *DB2 Application Programming and SQL Guide*.

PATH	(<i>schema-name</i>) (USER) (<i>schema-name</i> , USER , ...)	On: BIND and REBIND PLAN and PACKAGE
-------------	--	---

Determines the SQL path that DB2 uses to resolve unqualified user-defined distinct types, functions, and stored procedure names (in CALL statements).

For the **PATH** option, consider the following guidelines when you specify a *schema-name*:

- The specified schema names are *not* folded to uppercase by DB2. This behavior is different than that for schema names in SQL statements, which are folded to uppercase before being stored in the catalog. If you do not specify these nondelimited schema names in upper case, DB2 cannot find a match in the catalog for those schema names.
- You can specify delimited identifiers in both mixed and uppercase characters.

The **PATH** keyword is mutually exclusive with the **PATHDEFAULT** keyword. Do not specify both keywords in the same REBIND command.

(*schema-name*)

Identifies a schema.

DB2 does not validate that the specified schema actually exists at precompile or at bind time.

You do not need to explicitly specify the SYSIBM, SYSFUN, and SYSPROC schemas; DB2 implicitly assumes that these schemas are at the beginning of the SQL path. DB2 adds these schemas in the order listed above. If you do not specify the SYSIBM, SYSFUN, and SYSPROC schemas, they are not included in the 254-byte length.

(*schema-name*, ...)

Identifies a list of schemas. The same schema name should not appear more than once in the SQL path.

The number of schemas you can specify is limited by the length of the resulting SQL path, which cannot exceed 254 bytes. To calculate the length of the resulting SQL path:

1. Take the length of each schema.
2. Add 2 for delimiters around each *schema-name* in the list.
3. Add 1 for each comma after each schema. Do *not* add 1 for the last schema.

USER Represents a maximum 8-byte *schema-name*. At bind time, DB2 includes this 8-byte length in the total length of the list of schema names specified for the PATH bind option. The maximum length for a list of schema names, including comma separators, delimiters, and the 8-byte USER value, is 254 bytes. If you exceed this limit, DB2 generates an error message at bind time.

At run time, DB2 substitutes the run-time value of the USER special register, which contains the primary authorization ID of the run-time process, for the *schema-name* in the position of USER in the PATH *schema-name* list.

BIND PLAN (DSN)

If you specify USER in a list of schema names, do not use delimiters around the USER keyword.

For more information about schema names, ordinary identifiers, and delimited identifiers, see Chapter 2 of *DB2 SQL Reference*.

Defaults:

Process

Default value

BIND PLAN

"SYSIBM", "SYSFUN", "SYSPROC", *plan qualifier*²

BIND PACKAGE

"SYSIBM", "SYSFUN", "SYSPROC", *package qualifier*²

REBIND PLAN

Existing value

REBIND PACKAGE

Existing value

PATHDEFAULT

On: REBIND PLAN and
PACKAGE

Resets the **PATH** for a package or plan to "SYSIBM", "SYSFUN", "SYSPROC", *plan-qualifier/package-qualifier*.

The **PATHDEFAULT** keyword is mutually exclusive with the **PATH** keyword. Do not specify both keywords in the same REBIND command.

Defaults:

Process

Default value

REBIND PLAN

None

REBIND PACKAGE

None

PKLIST NOPKLIST

(*location-name.collection-id.package-id, ...*) PKLIST only

On: BIND and REBIND
PLAN

PKLIST determines what packages to include in the package list for the plan. The order in which you list packages with partial identifiers determines the search order at run time and can affect performance.

NOPKLIST is used with REBIND PLAN only. NOPKLIST determines that the plan rebinds without a package list. If a package list already exists, then NOPKLIST deletes it.

location-name or *

Names the location of the DBMS where the package resides, or defers that choice until run time. Use either a particular location name or an asterisk (*), or omit this part of the identifier. The default is the local DBMS.

2. Although this is the default value, it is not stored in the catalog. Instead, the catalog value is blank.

BIND PLAN (DSN)

If you use a particular location name, then that DBMS should be defined in catalog table SYSIBM.LOCATIONS. If that table does not exist or if the DBMS is not in it, you receive warning messages.
If you use an asterisk, at run time the location comes from the special register CURRENT SERVER. DB2 checks privileges to use the SQL statements in the package at that location.

collection-id or *
Names the collection that contains the package or defers that choice until run time. Use either a particular collection ID or an asterisk (*). There is no default.

If you use an asterisk, then DB2 checks the privileges to use the SQL statements embedded in the package run time. At that time also, DB2 determines the collection ID as follows:

- If the value in the special register CURRENT PACKAGESET is not blank, then that value is the collection ID.
- If the value of CURRENT PACKAGESET is blank, then DB2 skips the entry unless it is the last entry in the package list. If it is the last or only entry, an error message occurs.

package-id or *
Names a particular package or specifies, by the asterisk, all packages in the collection. Because you cannot specify a *version-id* for the packages included in the package list, all versions are effectively included.

Defaults:

Process	Default value
BIND PLAN	None
BIND PACKAGE	N/A
REBIND PLAN	Existing value
REBIND PACKAGE	N/A

PKLIST has no default; if you do not use PKLIST, you must use MEMBER.

The default for NOPKLIST is to use the package list specified in the PKLIST option, if any, during the current or previous bind or rebind.

Catalog record: Table SYSPACKLIST.

For more information about:

- How the order of search for packages affects performance, see Part 5 of *DB2 Application Programming and SQL Guide*.
- How to define a location name in SYSIBM.LOCATIONS, see Part 3 of *DB2 Administration Guide*.
- The TSO/E restriction that limits the maximum number of packages specified in the PKLIST, see OS/390 TSO/E Programming Services.

PLAN	(<i>plan-name</i>) (*) (REBIND PLAN only)	On: BIND and REBIND PLAN
-------------	--	---------------------------------

Determines what plan or plans to bind or rebind.

BIND PLAN (DSN)

(plan-name)

Specifies the name of the application plan.

For REBIND only, the value of column NAME in the catalog table SYSPLAN; you can use a list of plan names.

The default is to perform all bind functions, including error diagnostics, without producing an application plan and without inserting rows into PLAN_TABLE for the option EXPLAIN.

(*) (For REBIND only)

Rebinds all plans for which the applicable authorization ID has the BIND privilege. The applicable ID is:

- The value of OWNER, if you use that option
- The authorization ID of the process running the bind, if you do not use the option OWNER

Catalog record: Column NAME of table SYSPLAN.

QUALIFIER	<i>(qualifier-name)</i>	On: BIND and REBIND PLAN and PACKAGE
-----------	-------------------------	--------------------------------------

Determines the implicit qualifier for unqualified names of tables, views, indexes, and aliases contained in the plan or package.

(qualifier-name)

Specifies the value of the implicit qualifier. This value is not subject to translation when sent to a remote system for BIND or REBIND PACKAGE.

Defaults:

Process

Default value

BIND PLAN

Owner ID

BIND PACKAGE

Owner ID

REBIND PLAN

Existing value

REBIND PACKAGE

Existing value

The default is the owner's authorization ID, whether you use the OWNER option or its default.

Catalog record: Column QUALIFIER of tables SYSPACKAGE and SYSPLAN.

RELEASE	(COMMIT) (DEALLOCATE)	On: BIND and REBIND PLAN and PACKAGE, REBIND TRIGGER PACKAGE
---------	--	--

Determines when to release resources that a program uses, either at each commit point or when the program terminates.

(COMMIT)

Releases resources at each commit point.

(DEALLOCATE)

Releases resources only when the program terminates.

The value has no effect on dynamic SQL statements, which always use RELEASE(COMMIT), with one exception: When you use RELEASE(DEALLOCATE) and KEEPYNAMIC(YES), and your subsystem is installed with YES for field CACHE DYNAMIC SQL on installation panel DSNTIP4, the RELEASE(DEALLOCATE) option is honored for dynamic SELECT, INSERT, UPDATE and DELETE statements.

Locks that are acquired for dynamic statements are held until one of the following events occurs:

- The application process ends (deallocation).
- The application issues a PREPARE statement with the same statement identifier. (Locks are released at the next commit point.)
- The statement is removed from the cache because it has not been used. (Locks are released at the next commit point.)
- An object that the statement is dependent on is dropped or altered, or a privilege that the statement needs is revoked. (Locks are released at the next commit point.)

RELEASE(DEALLOCATE) can increase the package or plan size, because additional items become resident in the package or plan.

For more information about how the RELEASE option affects locking and concurrency, see Part 5 (Volume 2) of *DB2 Administration Guide* or Part 5 of *DB2 Application Programming and SQL Guide*.

Defaults:

Process	Default value
BIND PLAN	COMMIT
BIND PACKAGE	Plan value
REBIND PLAN	Existing value
REBIND PACKAGE	Existing value

The default for a package that is bound at a remote server is **COMMIT**.

Catalog record: Column RELEASE of tables SYSPACKAGE and SYSPLAN.

NOREOPT(VARS) REOPT(VARS)	On: BIND and REBIND PLAN and PACKAGE
--	---

Specifies whether to have DB2 determine an access path at run time using values for host variables, parameter markers, and special registers.

NOREOPT(VARS)
Does not determine an access path at run time.

REOPT(VARS)
Re-determines the access path at run time.

Usage notes:

- You cannot use both REOPT(VARS) and NOREOPT(VARS).
- You cannot use both REOPT(VARS) and KEEPYNAMIC(YES).

BIND PLAN (DSN)

- You cannot use both REOPT(VARS) and NODEFER(PREPARE).

Defaults:

Process	Default value
BIND PLAN	NOREOPT
BIND PACKAGE	NOREOPT
REBIND PLAN	Existing value
REBIND PACKAGE	Existing value

The default for a package on a remote DB2 server is NOREOPT(VARS).

Catalog record: Column REOPT of table SYSPLAN and SYSPACKAGE.

SQLERROR	(NOPACKAGE) (CONTINUE)	On: BIND PACKAGE only
-----------------	-----------------------------------	------------------------------

Determines whether to create a package if SQL errors occur.

(NOPACKAGE)

Creates no package if an error occurs.

(CONTINUE)

Creates a package, even if errors occur when binding SQL statements. The statements in error cannot execute. Any attempt to execute them at run time causes errors.

Defaults:

Process	Default value
BIND PLAN	N/A
BIND PACKAGE	NOPACKAGE
REBIND PLAN	N/A
REBIND PACKAGE	N/A

Because you cannot use the option SQLERROR for REBIND PACKAGE, the value for the previous package remains in effect when you rebind that package. If you rebind a package that uses SQLERROR(CONTINUE), those SQL statements found in error at bind time do not rebind.

Catalog record: Column SQLERROR of table SYSPACKAGE.

SQLRULES	(DB2) (STD)	On: BIND and REBIND PLAN
-----------------	------------------------	---------------------------------

Determines whether you can execute a type 2 CONNECT statement to an existing SQL connection, according to DB2 rules. Alternatively, the statement causes an error, according to the ANSI/ISO SQL standard of 1992. This option applies to any

BIND PLAN (DSN)

application process that uses the plan and executes type 2 CONNECT statements. It has no effect on type 1 CONNECT statements or the rules for DB2 private protocol access.

(DB2) No error occurs if CONNECT identifies an existing SQL connection. If X is an existing SQL connection, CONNECT TO X makes X the current connection. If X is already the current connection, CONNECT TO X has no effect on the state of any connections.

(STD) An error occurs if CONNECT identifies an existing SQL connection. Therefore, if X is a dormant SQL connection, you must use the SQL statement SET CONNECTION to make X the current connection.

For local operations, the value of SQLRULES is used for the initial value of the SQL special register CURRENT RULES.

Defaults:

Process	Default value
BIND PLAN	DB2
BIND PACKAGE	N/A
REBIND PLAN	Existing value
REBIND PACKAGE	N/A

Catalog record: Column SQLRULES of table SYSPLAN.

VALIDATE	(RUN) (BIND)	On: BIND and REBIND PLAN and PACKAGE
----------	-----------------	--------------------------------------

Determines whether to recheck, at run time, errors of the type "OBJECT NOT FOUND" and "NOT AUTHORIZED" found during bind or rebind. The option has no effect if all objects and needed privileges exist.

(RUN) Indicated that if not all objects or privileges exist at bind time, the process issues warning messages, but the bind succeeds. DB2 checks existence and authorization again at run time for SQL statements that failed those checks during bind. The checks use the authorization ID of the plan or package owner.

(BIND) Indicates that if not all objects or needed privileges exist at bind time, the process issues error messages, and does not bind or rebind the plan or package, *except that*:
For BIND PACKAGE only, if you use the option SQLERROR(CONTINUE), the bind succeeds but the SQL statements in it that have errors cannot execute.

Defaults:

Process	Default value
BIND PLAN	RUN

BIND PLAN (DSN)

BIND PACKAGE

RUN

REBIND PLAN

Existing value

REBIND PACKAGE

Existing value

Catalog record: Column VALIDATE of tables SYSPACKAGE and SYSPLAN.

-CANCEL THREAD (DB2)

The DB2 command CANCEL THREAD cancels processing for specific local or distributed threads.

Abbreviation: -CAN THD

Environment

This command can be issued from an MVS console, a DSN session under TSO, a DB2I panel (DB2 COMMANDS), an IMS or a CICS terminal, or a program using the instrumentation facility interface (IFI).

Data sharing scope: Member


Authorization

To execute this command, the privilege set of this process must include one of the following:

- SYSOPR authority
- SYSCTRL authority
- SYSADM authority

DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.

Syntax



Option descriptions

THREAD (token)

Identifies a specific thread, either distributed or not, whose processing you want to cancel. DB2 assigns a token to each thread that is unique for that DB2 subsystem, but not necessarily unique across subsystems.

The token is a one- to six-digit decimal number. It can be determined from the DB2 command DISPLAY THREAD or from an IFI READS call for IFCID 0147 or 0148. The token can also appear after the equal sign in DB2 messages that display an LUWID.

DDF THREAD(luwid)

Identifies distributed threads for which you want to cancel processing. *luwid* is a logical unit of work identifier (LUWID), consisting of:

- A fully qualified LU network name, which consists of:
 - A one- to eight-character network ID
 - A period
 - A one- to eight-character network LU name
- An LUW instance number, which consists of 12 hexadecimal characters that uniquely identify the unit of work

-CANCEL THREAD (DB2)

If you enter three fields separated by periods, DB2 assumes that you are entering an LUWID.

You might have two or more distributed threads with the same LUWID. All distributed threads with the same LUWID are canceled.

The LUWID can be determined from the DB2 DISPLAY THREAD command and other DB2 messages.

DUMP

Provides a dump for diagnostic purposes.

NOBACKOUT

Specifies that DB2 will not attempt to back out the data during transaction rollback processing. Cancelling the thread with NOBACKOUT leaves objects in an inconsistent state. Do not issue this command with NOBACKOUT unless you have a plan to resolve the data inconsistency.

Multiple NOBACKOUT requests are allowed. However, if the thread is active and the request is accepted, subsequent requests are ignored. You can choose to issue a subsequent request if a request fails (as indicated by message DSNIO32I). Objects that the thread modifies are recovered (backed out). If back out processing fails, the objects are marked REFRESH PENDING (REFP) and either RECOVER PEINDING (RECP) or REBUILD PENDING (RBDP or PSRBD) in the database exception table. Resolve the REFP status of the object by running the RECOVER utility to recover the object to a prior point in time or by running LOAD REPLACE on the object.

Usage notes

Canceling distributed threads: Canceling a distributed thread can cause the thread to enter the indoubt state. Message DSNL450I is issued if the CANCEL command causes the DDF thread to be converted from active to indoubt. DB2 releases the resources that the thread holds when the indoubt state is resolved by automatic indoubt resolution with the coordinator, or by resolution with the command RECOVER INDOUBT.

If a thread that is specified in the command is part of a global transaction, the command is executed against all threads in the global transaction. See Chapter 5 of the DB2 Administration Guide, for an explanation of global transactions.

The CANCEL command schedules a thread to be terminated in DB2. To terminate, the thread must be processing within DB2. If the thread does not terminate, it could be:

- Processing outside of DB2, possibly in the application. If that is the case, the thread does not terminate until the application makes a request to DB2. Use the MVS Cancel command to terminate the application immediately.
- Hung up in VTAM. Use VTAM commands to cause VTAM to return processing to DB2, which will terminate the thread. See topic below for details.

Canceling local threads: The CANCEL command schedules a thread to terminate. Threads that are not in DB2 terminate immediately.

Using VTAM commands to cancel SNA distributed threads: If the CANCEL command does not terminate a distributed thread, it is possible that it is hung up in VTAM. Use the VTAM VARY NET,TERM command to cancel the thread's VTAM

-CANCEL THREAD (DB2)

sessions. To do this, you need to know the VTAM session IDs (SIDs) that correspond to the thread. Take the following steps:

1. Issue the DB2 command `DISPLAY THREAD(*) LUWID(nnnn) DETAIL`. (The value of *nnnn* is the token or LUWID provided by `CANCEL DDF THREAD`.)

This gives you the VTAM session IDs that must be canceled. Sessions are identified by the column header `SESSID` as shown in the following `DISPLAY THREAD` output:

```
-DIS THD(*) LUWID(123) DETAIL
DSNV401I - DISPLAY THREAD REPORT FOLLOWS:
DSNV402I - ACTIVE THREADS:
NAME      ST A  REQ ID          AUTHID    PLAN      ASID TOKEN
BATCH     TR *   5 BKH2C          SYSADM    BKH2      000D  123
V444-DB2NET.LUND0.9F6D9F459E92=123 ACCESSING DATA AT
V446-SAN JOSE:LUND1
V447--LOCATION          SESSID              A ST    TIME
V448--SAN JOSE         00D3590EA1E89701    S1     9332108460302
V448--SAN JOSE         00D3590EA1E89822    V R1    9332108460431
DISPLAY ACTIVE REPORT COMPLETE
DSN9022I - DSNVDT '-DIS THD' NORMAL COMPLETION
```

The **V** indicates the thread is processing in VTAM.

2. Record positions 3 through 16 of `SESSID` for the threads to be canceled. (In the `DISPLAY THREAD` output above, the values are `D3590EA1E89701` and `D3590EA1E89822`.)
3. Issue the VTAM command `DISPLAY NET` to display the VTAM session IDs. The ones you want to cancel match the `SESSIDs` in positions 3 through 16 and the corresponding session IDs are in bold. The following is an output example of this command:

```
D NET,ID=LUND0,SCOPE=ACT
IST097I DISPLAY ACCEPTED
IST075I NAME = LUND0, TYPE = APPL
IST486I STATUS= ACTIV, DESIRED STATE= ACTIV
IST171I ACTIVE SESSIONS = 0000000005, SESSION REQUESTS = 0000000000
IST206I SESSIONS:
IST634I NAME      STATUS          SID          SEND    RECV    VR    TP    NETID
IST635I LUND1     ACTIV-S      D24B171032B76E65 0051    0043    0    0    NET2
IST635I LUND1     ACTIV-S      D24B171032B32545 0051    0043    0    0    NET2
IST635I LUND1     ACTIV-R      D2D3590EA1E89701 0022    0031    0    0    NET2
IST635I LUND1     ACTIV-R      D2D3590EA1E89802 0022    0031    0    0    NET2
IST635I LUND1     ACTIV-R      D2D3590EA1E89822 0022    0031    0    0    NET2
IST314I END
```

4. Issue the VTAM command `VARY NET,TERM` for each of the VTAM SIDs associated with the DB2 thread. In this case, it might be necessary to cancel only the session ID that `DISPLAY THREAD` shows to be processing in VTAM (`D2D3590EA1E89822`).

For more information about VTAM commands, see *VTAM for MVS/ESA Operation*.

Using TCP/IP Commands to Cancel TCP/IP Distributed Threads: If the `CANCEL` command does not terminate a distributed thread, it is possible that it is hung up in TCP/IP. Use the `TCP/IP DROP` command to cancel the thread's connection ID. To do this, you need to first determine the TCP/IP connection ID that corresponds to the thread. Depending on whether the thread is a DB2 requester or server thread, take the following steps:

- Terminating TCP/IP connection for a requester thread:

-CANCEL THREAD (DB2)

1. Issue the DB2 command `DISPLAY THREAD(*) LUWID(nnnn) DETAIL`. (The value of *nnnn* is the token or LUWID provided by `CANCEL THREAD`.)
Find the IP address and local port for the connection to the partner, as shown in the following `DISPLAY THREAD` output:

```
#display thread(*) detail

DSNV401I # DISPLAY THREAD REPORT FOLLOWS -
DSNV402I # ACTIVE THREADS -
NAME      ST A   REQ ID          AUTHID  PLAN    ASID TOKEN
TEST0001 TR      4 CTHDCORID001 SYSADM  DONSQ1  0027    19
V444-USIBMSY.SYEC715B.B4FA989AF056=19 ACCESSING DATA AT
V446-STL714A:9.112.114.102:446
V447--LOCATION          SESSID          A ST TIME
V448--STL714A          1028:446          S2 0032608521413
DISPLAY ACTIVE REPORT COMPLETE
DSN9022I # DSNVDT '-DIS THD' NORMAL COMPLETION
```

In this case, the partner's IP address and port is 9.112.114.102 446, and the local port is 1028.

2. Determine the associated TCP/IP connection ID:

```
d tcpip,,netstat,conn,ipaddr=9.112.114.102

EZZ2500I NETSTAT CS V2R10 TCPIP 534
USER ID  CONN    LOCAL SOCKET          FOREIGN SOCKET          STATE
V71BDIST 0000049D 9.112.114.103..1028    9.112.114.102..446     ESTBLSH
1 OF 1 RECORDS DISPLAYED
```

3. Terminate the connection:

```
v tcpip,,drop,conn=0000049d

EZZ0060I PROCESSING COMMAND: VARY TCPIP,,DROP,
CONN=0000049D
EZZ0053I COMMAND VARY DROP COMPLETED SUCCESSFULLY
```

- Terminating TCP/IP connection for a server thread::

1. Issue the DB2 command `DISPLAY THREAD(*) LUWID(nnnn) DETAIL`. (The value of *nnnn* is the token or LUWID provided by `CANCEL THREAD`.)
Find the IP address and local port for the connection to the partner, as shown in the following `DISPLAY THREAD` output:

```
!display thread(*) detail

DSNV401I ! DISPLAY THREAD REPORT FOLLOWS -
DSNV402I ! ACTIVE THREADS -
NAME      ST A   REQ ID          AUTHID  PLAN    ASID TOKEN
TEST0001 RA *    2 CTHDCORID001 SYSADM  DONSQ1  002D    11
V445-USIBMSY.SYEC715B.B4FA9BB94FA7=11 ACCESSING DATA FOR
9.112.114.103
V447--LOCATION          SESSID          A ST TIME
V448--9.112.114.103    446:1029        W R2 0032609061159
DISPLAY ACTIVE REPORT COMPLETE
DSN9022I ! DSNVDT '-DIS THD' NORMAL COMPLETION
```

In this case, the partner's IP address is 9.112.114.103 and the local port is 1029.

2. Determine the associated TCP/IP connection ID:

```
d tcpip,,netstat,conn,ipaddr=9.112.114.103

EZZ2500I NETSTAT CS V2R8 TCPIP 126
USER ID  CONN    LOCAL SOCKET          FOREIGN SOCKET          STATE
V61ADIST 0000048E 9.112.114.102..446    9.112.114.103..1029    ESTABLS
1 OF 1 RECORDS DISPLAYED
```

-CANCEL THREAD (DB2)

Find the entry where the foreign socket shows the partner's IP address and port (9.112.114.103 1029) and note the CONN.

3. Terminate the connection:

```
v tcpip,,drop,conn=0000048e
```

```
EZZ0060I PROCESSING COMMAND: VARY TCPIP,,DROP,  
CONN=0000048E  
EZZ0053I COMMAND VARY DROP COMPLETED SUCCESSFULLY
```

Examples

Example 1: To cancel a non-distributed thread whose token you found through -DISPLAY THREAD and to produce a diagnostic dump, issue:

```
-CANCEL THREAD (123) DUMP
```

Example 2: To cancel a distributed thread whose LUWID you found through -DISPLAY THREAD, issue:

```
-CANCEL DDF THREAD (LUDALLAS.DB2SQL1.3042512B6425)
```

Assume that the output from -DISPLAY THREAD shows that the thread-ID and token associated with this LUWID is 45162. You can also cancel this thread by issuing:

```
-CANCEL DDF THREAD (45162)
```

or

```
-CANCEL THREAD (45162)
```

As in the first example, specifying DUMP with any of the commands shown in this example causes a diagnostic dump to be produced.

/CHANGE (IMS)

/CHANGE (IMS)

The IMS command /CHANGE resets an indoubt unit of recovery as identified by the OASN keyword of the /DISPLAY command. That command deletes the item from the standpoint of IMS, but it does not communicate to DB2.

Abbreviation: /CHA

Environment


This command can be issued only from an IMS terminal.

Data sharing scope: Member

Authorization

This command requires an appropriate level of IMS authority, as described in *IMS Administration Guide: System*.

Syntax



Option descriptions

SUBSYS

Deletes IMS recovery elements from one or more subsystems.

One of the following subparameters must be coded:

subsystem-name, ...

Specifies one or more subsystems from which recovery elements will be deleted.

ALL

Deletes IMS recovery elements from all subsystems.

subsystem-name **OASN** *schedule-number, ...*

Deletes one or more origin application schedule numbers from one subsystem, specified by *subsystem-name*.

schedule-number can be a list of up to 32768 origin application schedule numbers. The numbers are displayed using the OASN parameter of the /DISPLAY command.

RESET

Deletes the indoubt recovery unit. The recovery unit represents an incomplete unit of work assigned to an external subsystem as the result of an application request.

Usage note

The preceding description of the /CHANGE command is a partial description only. For a complete description, see *IMS Command Reference*.

Examples

Example 1: Reset all indoubt recovery units for subsystem DB2.

```
/CHA SUBSYS DB2 RESET
```

Example 2: Reset all indoubt recovery units for all subsystems.

```
/CHA SUBSYS ALL RESET
```

Example 3: Reset indoubt recovery units identified by OASN numbers 99, 685, and 2920 for subsystem DB2.

```
/CHA SUBSYS DB2 OASN 99 685 2920 RESET
```

DCLGEN (DSN)

DCLGEN (DECLARATIONS GENERATOR) (DSN)

The declarations generator (DCLGEN) produces an SQL DECLARE TABLE statement and a COBOL, PL/I, or C data declaration for a table or view named in the catalog.

For further information regarding the DCLGEN command and uses for its output, see Part 2 of *DB2 Application Programming and SQL Guide*.

Environment

The declarations generator is executed by the DSN subcommand DCLGEN. That subcommand can be issued from a DSN session, running in either foreground or background mode, or it can be issued through DB2I.


Data sharing scope: Group

Authorization

To execute this command, the privilege set of the process must include one of the following:

- SELECT privilege on the table or view
- Ownership of the table or view
- DBADM authority on the database containing the table
- SYSADM authority
- SYSCTRL authority (catalog tables only)

Syntax



Option descriptions

TABLE

Specifies what table or view for which to generate a declaration. *table-name* or *view-name* is the qualified or unqualified name of the table or view.

The name must follow the following rules:

- If the name is a single-byte or mixed string and contains special characters other than underscores (_), it must be enclosed between apostrophes ('). If the language is COBOL, single-byte underscores in the name are translated into hyphens (-) by DCLGEN. Double-byte character set (DBCS) names need not be enclosed in apostrophes.
- If the name contains single-byte apostrophes, each one must be doubled ("). (Some host languages do not permit apostrophes in variable names.)

A table or view name that contains a period and is not enclosed by apostrophes is a qualified table name. The characters to the left of the period constitute the table owner, and those to the right of the period constitute the table name. Any table name enclosed in apostrophes is an unqualified table name. To understand how DCLGEN determines the table name qualifier, see the description of the OWNER option, which follows.

OWNER(*owner-name*)

Specifies a qualifier for the table name. *owner-name* is the qualifier for the table name.

If you specify a qualified table name for the TABLE(*table-name*) option, and you also specify OWNER(*owner-name*), the qualifier portion of *table-name* supersedes *owner-name* as the table name qualifier. If you specify an unqualified table name for the TABLE(*table-name*) option, and you do not specify OWNER(*owner-name*), the SQL authorization ID is the table name qualifier.

DCLGEN supports the use of underscore (_) as a valid character in the *owner-name* keyword parameter.

The following table illustrates the decision process for determining the DCLGEN table name qualifier.

Table name	OWNER(<i>owner-name</i>) specified	OWNER(<i>owner-name</i>) not specified
TABLE(<i>table-name</i>) qualified	<i>table-name</i> qualifier	<i>table-name</i> qualifier
TABLE(<i>table-name</i>) unqualified	<i>owner-name</i>	SQL authorization ID

AT(*location-name*)

Identifies the location of the table or view name specified in TABLE (*table-name*). *location-name*, which can consist of 1 to 16 characters, uniquely identifies an instance of a table or view in a network.

If you specify AT, *location-name* is used as the prefix for the table name, and *table-name* or *table-view* must be a qualified name.

DCLGEN supports the use of underscore (_) as a valid character in the *location-name* keyword parameter.

DCLGEN (DSN)

LIBRARY(*library-name*(*member-name*)/*password*)

Specifies the data set into which the declarations go. This data set must already exist and be accessible to the declarations generator. It can be either sequential or partitioned.

If the library name is not enclosed within apostrophes, DCLGEN constructs the following full data set name:

user-prefix.library-name.language.(member-name)

where:

user-prefix

The user prefix of the primary authorization ID of the transaction.

language

The value of the LANGUAGE option: COBOL, COB2, PLI, or C;

(*member-name*)

Optional; if not used, the output goes to a sequential data set.

password is optional.

ACTION

Indicates whether to add or replace the data set.

(ADD)

Adds the data set as a new member, if it does not already exist.

The **default** is **ACTION(ADD)**.

(REPLACE)

Replaces an existing member or data set with the new one. If the output is to a partitioned data set, and no member exists with the given name, one is added.

LANGUAGE

Specifies the language of the generated declaration.

Possible languages are:

- **(COBOL)**, for OS/VS COBOL
- **(COB2)**, for other COBOL languages
- **(PLI)**, for PL/I
- **(C)**, for C/370
- **(IBMCOB)**, for IBM COBOL
- **(CPP)**, for C++

NAMES(*prefix*)

Allows field names to be formed in the declaration.

Avoid possible name conflicts between DCLGEN output and the source program. If a conflict occurs, use NAMES or STRUCTURE, or manually edit the generated declaration or source program.

prefix can contain double-byte characters.

The field names consist of *prefix* concatenated with a number from one to three digits in length. *prefix* can have up to 28 characters. If *prefix* is a single-byte or mixed string and the first character is not alphabetic, it must be enclosed in apostrophes. For example, if *prefix* is ABCDE, the field names will be ABCDE1, ABCDE2, and so on, up to a maximum of ABCDE999. Special characters can be used, but use caution to avoid possible name conflicts.

For COBOL and PL/I, if the prefix is a DBCS string, the field name will be the DBCS prefix concatenated with the DBCS representation of the number. For example, if *prefix* is <D1D2D3> (where “<” and “>” represent shift-out and shift-in characters, respectively, and D1D2D3 represent double-byte characters), generated field names will be <D1D2D3.1>, <D1D2D3.2>, and so on. The period (.) represents X'42'.

The column names in the table are taken as default names for the fields in the output.

STRUCTURE(*structure-name*)

Specifies the generated data structure.

structure-name can have up to 31 characters. If *structure-name* is a single-byte or mixed string and the first character is not alphabetic, it must be enclosed in apostrophes. Special characters can be used, but use caution to avoid possible name conflicts.

structure-name can contain double-byte characters.

For SQL output, the name is the same as the table or view name. If the host language is C, the default structure name is the prefix DCL concatenated with the table name. If the host language is COBOL or PL/I and the table name is a single-byte or mixed string, the default structure name is also the prefix DCL concatenated with the table name. If the host language is COBOL or PL/I and the table name is a DBCS string, the default structure name is the prefix <.D.C.L> concatenated with the table or view name. “<” and “>” represent shift-out and shift-in characters, respectively. You must guard against possible conflicts with names in the source program. DCLGEN allows the specified structure name to be the same as the table or view name, but will issue a warning message.

APOST or QUOTE

Specifies the string delimiter character used in the host language. This option is effective only for COBOL programs.

APOST specifies the apostrophe (') as the host language string delimiter; the SQL delimiter is the quotation mark (").

QUOTE specifies the quotation mark (") as the host language delimiter; the SQL delimiter is the apostrophe (').

If neither APOST nor QUOTE is specified, the **default** is either APOST or QUOTE for COBOL, depending on what was specified on DB2 installation panel DSNTIPF.

The string delimiter delimits strings in host language statements. The SQL escape character delimits table and column names in the SQL DECLARE TABLE statement produced by DCLGEN. It is possible, by a choice made during DB2 installation, to make both delimiters the quotation mark or both the apostrophe.

LABEL

Indicates whether to include column labels in the output as comments. (Column labels can be assigned by the LABEL ON statement.)

NO

Omits the column labels.

YES

Includes the column labels.

DCLGEN (DSN)

DBCSSYMBOL

Specifies the symbol used to denote a graphic data type in a COBOL PICTURE clause.

(G)

Graphic data is denoted using G.

(N)

Graphic data is denoted using N.

DBCSDELIM

Specifies whether the DBCS table and column names in the generated DECLARE table statement will be delimited.

(YES)

DBCS table and column names will be delimited in the DCLGEN table declaration.

(NO)

DBCS table and column names will not be delimited in the DCLGEN table declaration.

COLSUFFIX

Determines whether to form field names by attaching the column name to the prefix given by the NAMES option.

(NO)

The column name is not used as a suffix, and field names are controlled by the option NAMES, as in Version 3.

(YES)

If NAMES is specified, DCLGEN forms field names by adding column names as a suffix to the value of NAMES. For example, if the prefix given by NAMES is "NEW" and the column name is EMPNO, then the field name is "NEWEMPNO".

If NAMES is *not* specified, DCLGEN issues a warning message and uses the column names as the field names, as in Version 3.

INDVAR

Determines whether to create an indicator variable array for the host variable structure.

(NO)

DCLGEN does not create an indicator variable array.

(YES)

DCLGEN creates an indicator array for the host variable structure. The array name is the table name with a prefix of "I" (or DBCS letter "<I>" if the table name is double-byte).

Usage notes

Parsing of the DCLGEN command conforms to standard TSO parsing conventions. For information about TSO command parsing, see the *OS/390 TSO/E Programming Services*.

The DECLARE statement: The DECLARE statement generated by DCLGEN will define all columns created with a data type of VARCHAR or LONG VARCHAR as VARCHAR. Columns created with a data type of VARGRAPHIC or LONG VARGRAPHIC will be defined as VARGRAPHIC.

Comments: The output for all host languages includes comments. The leading comment block echoes the DCLGEN subcommand that requested the declarations. The trailing comment block indicates the number of variables declared.

Using the output: To include the DCLGEN output in an application program, use the SQL INCLUDE statement. The same member name specified in the DCLGEN LIBRARY parameter is specified on the INCLUDE statement.

Prompts: Online TSO will prompt for missing or incorrectly specified options.

Editing the output: It is expected that the output of DCLGEN will not meet every need. You can freely edit the output before including it in a program. For example, you might want to change a variable name, or include SQL escape characters.

You can edit the output to add WITH DEFAULT to NOT NULL for columns that do not allow null values. If you edit the output, you must provide a default value.

If your column names contain embedded blanks, they will also be reflected in the host variable declarations, and you will have to remove, or translate, any blank characters to some other value.

C: DCLGEN support of the C language is unique in the following ways:

- DCLGEN does not fold the STRUCTURE, NAMES, or TABLE values to uppercase.
- For any DB2 column that has the data type CHAR(*n*), where *n* > 1, DCLGEN generates the corresponding host variable as CHAR(*n* + 1) to avoid the DB2 warning. For *n* = 1, the corresponding host variable is CHAR.

COBOL and binary integers: DB2 uses the full size of binary integers. It can place larger values than allowed in the specified number of digits in the COBOL declaration, which can result in truncated values.

For small integers that can exceed 9999, use S9(5). For large integers that can exceed 999,999,999, use S9(10) COMP-3 to obtain the decimal data type. If COBOL is used for integers that exceed the COBOL PICTURE, specify the column as decimal to ensure that the data types match and perform well.

COBOL and the underscore character: Because COBOL does not allow the use of the underscore character, DCLGEN translates any underscore characters in the table's column names into hyphens (-) for use in the generated structure.

COBOL and DBCS: OS/VS COBOL does not support DBCS, but later versions of COBOL (VS COBOL II and COBOL/370) do. Although DB2 accepts values outside of the range from X'41' to X'FE', in COBOL data definition statements, both bytes of each double-byte character in data names must be within this range. Data names must also contain at least one DBCS character that does not have X'42' as its first byte.

Data declarations for arrays of indicator variables: If DCLGEN creates an array of indicator variables, data declarations have the following form:

Language

Data declaration

C short int *Itable-name*[*n*];

COBOL

01 *Itable-name* PIC S9(4) USAGE COMP OCCURS *n* TIMES.

DCLGEN (DSN)

PL/I DCL *ltable-name*(*n*) BIN FIXED (15);

where *n* is the number of columns in the table.

Examples

Example 1: This example shows the use of the DCLGEN. The statement

```
DCLGEN TABLE(VEMPL) -  
    LIBRARY('prefix.SRCLIB.DATA(DSN8MPPEM)') -  
    LANGUAGE(PLI) -  
    APOST
```

produces the following statements in *prefix.SRCLIB.DATA(DSN8MPPEM)*:

```
/******  
/* DCLGEN TABLE(VEMPL) -  
/* LIBRARY('prefix.SRCLIB.DATA(DSN8MPPEM)') -  
/* LANGUAGE(PLI) -  
/* APOST  
/* ... IS THE DCLGEN COMMAND THAT MADE THE FOLLOWING STATEMENTS  
/******  
EXEC SQL DECLARE VEMPL TABLE  
    ( EMPNO CHAR(6) NOT NULL,  
      FIRSTNME VARCHAR(12) NOT NULL,  
      MIDINIT CHAR(1) NOT NULL,  
      LASTNAME VARCHAR(15) NOT NULL,  
      WORKDEPT CHAR(3) NOT NULL  
    );  
/******  
/* PLI DECLARATION FOR TABLE VEMPL  
/******  
DCL 1 DCLVEMPL,  
    5 EMPNO CHAR(6),  
    5 FIRSTNME CHAR(12) VAR,  
    5 MIDINIT CHAR(1),  
    5 LASTNAME CHAR(15) VAR,  
    5 WORKDEPT CHAR(3);  
/******  
/* THE NUMBER OF COLUMNS DESCRIBED BY THIS DECLARATION IS 5  
/******
```

Example 2: This example shows the use of NAMES and STRUCTURE. The statement

```
DCLGEN TABLE(VEMPL) -  
    LIBRARY('prefix.SRCLIB.DATA(DSN8MPPEM)') -  
    LANGUAGE(PLI) -  
    NAMES(FIELD) -  
    STRUCTURE(EMPRecord) -  
    APOST
```

produces the following statements in *prefix.SRCLIB.DATA(DSN8MPPEM)*:

```

/*****/
/* DCLGEN TABLE(VEML) - */
/* LIBRARY('prefix.SRCLIB.DATA(DSN8MPPEM)') - */
/* LANGUAGE(PLI) - */
/* NAMES(FIELD) - */
/* STRUCTURE(EMPREGORD) - */
/* APOST */
/* ... IS THE DCLGEN COMMAND THAT MADE THE FOLLOWING STATEMENTS */
/*****/
EXEC SQL DECLARE VEML TABLE
      ( EMPNO          CHAR(6) NOT NULL,
        FIRSTNME       VARCHAR(12) NOT NULL,
        MIDINIT        CHAR(1) NOT NULL,
        LASTNAME       VARCHAR(15) NOT NULL,
        WORKDEPT       CHAR(3) NOT NULL
      ) ;

/*****/
/* PLI DECLARATION FOR TABLE VEML */
/*****/
DCL 1 EMPREGORD,
      5 FIELD1  CHAR(6),
      5 FIELD2  CHAR(12) VAR,
      5 FIELD3  CHAR(1),
      5 FIELD4  CHAR(15) VAR,
      5 FIELD5  CHAR(3);

/*****/
/* THE NUMBER OF COLUMNS DESCRIBED BY THIS DECLARATION IS 5 */
/*****/

```

/DISPLAY (IMS)

/DISPLAY (IMS)

The IMS command /DISPLAY displays the status of the connection between IMS and an external subsystem (as well as all application programs communicating with the external subsystem), or the outstanding recovery units associated with the subsystem.

Environment


This command can be issued only from an IMS terminal.

Data sharing scope: Member

Authorization

This command requires an appropriate level of IMS authority, as described in the *IMS Administration Guide: System*.

Syntax



Option descriptions

One of the following options is required:

SUBSYS

Identifies the subsystems to display information about.

subsystem-name, ...

Specifies one or more subsystems. See “Output” on page 93 for a description of possible subsystem status.

ALL

Displays information about all subsystems.

OASN SUBSYS

Displays the outstanding recovery units (origin application schedule numbers, or OASN) associated with the external subsystems. The OASN is assigned by IMS when it schedules an application into a dependent region. That, coupled with the IMS ID, becomes the recovery token for units of work distributed to other subsystems.

subsystem-name, ...

Specifies one or more subsystems to display information about.

ALL

Displays the outstanding recovery units associated with all external subsystems.

Output

The command recognition character (CRC) is displayed for each external subsystem. Subsystem status is one of the following:

CONNECTED

An IMS control region or dependent region has successfully connected to the external subsystem. At this point, the two systems can begin a normal dialog.

NOT CONNECTED

The external subsystem is in an idle state. That is, either it has not been the object of the /START SUBSYS command, or the external subsystem initialization exit routine indicated not to connect.

CONNECT IN PROGRESS

The connection process for the specified subsystem is in progress.

STOPPED

The specified subsystem has been stopped with the /STOP SUBSYS command. All region connections to the specified external subsystem have been terminated.

STOP IN PROGRESS

The /STOP SUBSYS command is in progress. Before it completes successfully, all active connections to the specified subsystem from all IMS regions must be quiesced.

INVALID SUBSYSTEM NAME = *subsystem-name*

The indicated subsystem name has not been defined to the IMS subsystem PROCLIB member. Add the subsystem definition to the subsystem member and issue the /START SUBSYS command.

SUBSYSTEM *subsystem-name* NOT DEFINED BUT RECOVERY OUTSTANDING

The indicated subsystem name has not been defined to IMS in the external subsystem PROCLIB member, but IMS still has outstanding recovery elements from a previous execution when the name was known. To resolve the recovery element problem, either add the indicated subsystem definition to the external subsystem PROCLIB member and then issue the /START SUBSYS command, or issue the /DISPLAY OASN SUBSYS command to determine the identification of the OASNs and then manually resolve the recovery elements by issuing the /CHANGE SUBSYS RESET command.

TERM IN PROGRESS

An internal termination of the subsystem is underway. This type of termination was instigated by IMS abnormal condition processing, an external subsystem exit, or the external subsystem.

A thread between an IMS dependent region and an external subsystem is created when an application program in the region establishes a connection to the external subsystem. The status of threads to an external subsystem is listed under the status of the subsystem. The absence of a list of threads under a connected subsystem indicates that no threads to the specified subsystem have been established.

Thread status can be:

CONNECTED(CONN)

An IMS control region or dependent region has successfully connected to the external subsystem.

/DISPLAY (IMS)

ACTIVE

An IMS application program has established communication with an external subsystem.

The absence of a PSB name for a thread indicates that a connection to the external subsystem exists, but an application program is not currently occupying the region. The presence or absence of an LTERM name indicates whether a region is message-driven.

The preceding description of the /DISPLAY command is a partial description only. For a complete description, see *IMS Command Reference*.

Example

Display the status of connections between IMS and all subsystems.

```
/DISPLAY SUBSYSTEM ALL
```

SUBSYS	CRC	REGID	PROGRAM	LTERM	STATUS
SSTR	?				CONN
		1	DDLTL17	PTERM01	CONN,ACTIVE
		2	DDLTL06	PTERM02	CONN

85202/065933

-DISPLAY ARCHIVE (DB2)

The DB2 command DISPLAY ARCHIVE displays input archive log information.

Abbreviation: -DIS ARC

Environment

This command can be issued from an MVS console, a DSN session under TSO, a DB2I panel (DB2 COMMANDS), an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

Data sharing scope: Member

Authorization

To execute this command, the privilege set of the process must include one of the following:

- ARCHIVE or DISPLAY system privilege
- SYSOPR, SYSCTRL, or SYSADM authority

DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.

Syntax

```
►►—DISPLAY ARCHIVE—◄◄
```

Usage note

Data sharing members: Although the command ARCHIVE LOG SCOPE(GROUP) or ARCHIVE LOG MODE(QUIESCE) initiates archive processing for all members of a data sharing group, the command DISPLAY ARCHIVE shows information only for the member for which it is issued. To display input archive log information for all members of a data sharing group, enter the command to each member.

Example

Display tape unit information about input archive logs.

```
-DISPLAY ARCHIVE
DSNJ322I - DISPLAY ARCHIVE REPORT FOLLOWS-
              COUNT              TIME
              (TAPE UNITS)        (MIN,SEC)
DSNZPARM          2              0,00
CURRENT           2              5,30
=====
ADDR STATUS CORR-ID  VOLSER DATASET_NAME
 290 AVAIL  ***** TAPE1  DSNCAT.ARCHLOG1.A0000033
 294 PREM   ***** TAPE3  DSNCAT.ARCHLOG1.A0000035
 293 BUSY  RECOVER2 TAPE2  DSNCAT.ARCHLOG1.A0000034
END OF DISPLAY ARCHIVE REPORT.
DSN9022I - DSNJC001 '-DISPLAY ARCHIVE' NORMAL COMPLETION
```

This example report shows:

- The subsystem parameter values for MAX RTU (COUNT) and DEALLC PERIOD TIME as recorded in the DSNZPxxx load module

-DISPLAY ARCHIVE (DB2)

- Current specifications for the COUNT and TIME parameters
- Availability status of allocated dedicated tape units
- Volume and data set names associated with all busy tape units

-DISPLAY BUFFERPOOL (DB2)

The DB2 command DISPLAY BUFFERPOOL displays the current status for one or more active or inactive buffer pools.

Abbreviation: -DIS BPOOL

Environment

This command can be issued from an MVS console, a DSN session under TSO, a DB2I panel (DB2 COMMANDS), an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

Data sharing scope: Member


Authorization

To execute this command, the privilege set of the process must include one of the following:

- DISPLAY system privilege
- SYSOPR, SYSCTRL, or SYSADM authority

DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.

Syntax



Option descriptions

(ACTIVE)

Displays the current buffer pool status for all active buffer pools.

(*) Displays the current buffer pool status for all active or inactive buffer pools.

-DISPLAY BUFFERPOOL (DB2)

(*bpname*)

Names the buffer pool for which current status is to be displayed.

- 4-KB page buffer pools are named BP0, BP1, ..., BP49.
- 8-KB page buffer pools are named BP8K0, BP8K1, ..., BP8K9.
- 16-KB page buffer pools are named BP16K0, BP16K1, ..., BP16K9.
- 32-KB page buffer pools are named BP32K, BP32K1, ..., BP32K9.

DETAIL

Produces a detail report for one or more buffer pools. If DETAIL is not specified, a summary report is produced.

(INTERVAL)

Requests statistics accumulated since the last incremental display, or since the buffer pool was first activated if there was no previous incremental display.

- (*) Requests statistics accumulated since the buffer pool was first activated.

LIST

Lists the open index spaces and table spaces associated with the buffer pools included in the report. Basic information is provided for no-data-sharing systems while more detail is provided if data-sharing is active.

(ACTIVE)

Restricts the list of open index spaces and table spaces to those that are currently in use.

- (*) Requests a list of all open index spaces and table spaces, whether currently in use or not.

LSTATS

Lists data set statistics for the open index spaces and table spaces associated with the buffer pools included in the report. The statistics displayed are incremental since the last time they were displayed.

(ACTIVE)

Restricts the list statistics to those data sets that are currently in use.

The **default** is **ACTIVE** when LIST is not specified or if LIST is specified with no parameter. If LIST is specified with a parameter and LSTATS has no parameter, then the parameter specified for LIST is used for LSTATS.

- (*) Includes statistics for all open index spaces and table spaces, whether currently in use or not.

DBNAME

Specifies which databases are included in the LIST display and the LSTATS display. If you specify DBNAME without LIST, LIST(ACTIVE) is assumed.

ABBREVIATION: DBN

(*database-name*, ...)

Identifies one or more databases to be included in the LIST and LSTATS displays. *database-name* can have any of the forms in the following list. In the list, *name1* and *name2* represent strings of from one to eight characters. *name* represents a string of from one to eight characters.

Form Displays the status of...

name1

The database *name1*

-DISPLAY BUFFERPOOL (DB2)

name1:name2

All databases with names from *name1* to *name2* in a sorted list of database names.

*name** All databases whose names begin with the string *name*

- (*) Displays information on all databases that match the LIST specification. This is the default.

SPACENAM

Specifies which table spaces or index spaces within the specified databases to include in the LIST display and the LSTATS display. If you use SPACENAM without DBNAME, DBNAME(*) is assumed.

ABBREVIATION: SPACE

- (*) Displays information about all table spaces and index spaces of the specified databases. This is the default.

(*space-name, ...*)

Identifies one or more spaces to be included in the LIST and LSTATS displays. You can write *space-name* like *database-name* to designate:

- The name of a single table space or index space
- A range of names
- A partial name followed by a pattern character

GBPDEP

Indicates whether to restrict the list of data sets to those that are group-buffer-pool-dependent. This option is not valid if this is a non-data sharing DB2.

(YES)

Restricts the list of page sets to those that are "group buffer pool dependent" (GBP-dependent). An index space or table space is GBP-dependent if either of these conditions are true:

- There is inter-DB2 R/W interest in it.
- There are changed pages from it in the group buffer pool that have not yet been written to disk.

(NO)

Restricts the list of page sets to those that are non-group buffer pool dependent.

CASTOWNR

Indicates whether to restrict the list of data sets to those for which this DB2 member is the castout owner. This option is not valid if this is a non-data sharing DB2.

(YES)

Restricts the list of page sets for which this DB2 member is the castout owner.

(NO)

Restricts the list of page sets for which this DB2 member is not the castout owner.

Output

You can request a summary report or a detail report.

-DISPLAY BUFFERPOOL (DB2)

Summary report

A summary report contains the following information, as seen in “Example 1” on page 103:

Identification:

BUFFERPOOL NAME

Buffer pool external name (BP0, BP1, ..., BP49, or BP32K, BP32K1, ..., BP32K9).

BUFFERPOOL ID

Buffer pool internal identifier (0-49, 80-89, 100-109, 120-129).

USE COUNT

Number of open table spaces or index spaces that reference this buffer pool. (Inactive pools have a zero use count.)

VIRTUAL BUFFERPOOL SIZE

User-specified virtual buffer pool size

BUFFERS ALLOCATED

Number of allocated buffers in an active virtual buffer pool.

TO BE DELETED

Number of buffers to be deleted in an active virtual buffer pool (because of pool contraction).

IN-USE/UPDATED

Number of currently active (not stealable) buffers in the virtual buffer pool.

Hiperpool Values:

HIPERPOOL SIZE

User-specified hiperpool size.

CASTOUT

Hiperpool CASTOUT attribute.

ALLOCATED

Number of allocated buffers in an active hiperpool.

TO BE DELETED

Number of buffers to be deleted in an active hiperpool (because of pool contraction).

BACKED BY ES

Number of hiperpool buffers backed by expanded storage.

Thresholds:

VP SEQUENTIAL

Sequential steal threshold for the virtual buffer pool.

HP SEQUENTIAL

Sequential steal threshold for the hiperpool.

DEFERRED WRITE

Deferred write threshold for the virtual buffer pool.

VERTICAL DEFERRED WRT

Vertical deferred write threshold for the virtual buffer pool.

PARALLEL SEQUENTIAL

Parallel sequential threshold for the virtual buffer pool.

ASSISTING PARALLEL SEQT

Assisting parallel sequential threshold for the virtual buffer pool.

Names of hiperspaces allocated to the hiperpool: A hiperspace name consists of 3 parts, with a total length of 8 characters. A hiperspace name always starts with an indicator of '@' followed by:

1. The buffer pool's internal ID (two characters, using Hex)
2. A sequence number about hiperspace allocation (one character)
3. The DB2 subsystem name (four characters)

Detail report

A detail report includes all summary report information and additional buffer pool related statistics. You can request cumulative statistics (accumulated since DB2 startup) or incremental statistics (accumulated since the last incremental display). A sample report appears in "Example 2" on page 103. The statistics in a detail report are grouped in the following categories:

Getpage information (message DSNB411I):**RANDOM GETPAGE**

Non-sequential getpage requests

SYNC READ I/O(R)

Synchronous read I/O operations for non-sequential getpage

SEQ. GETPAGE

Sequential getpage requests

SYNC READ I/O(S)

Synchronous read I/O operations for sequential getpage

DMTH HIT

Number of times data management threshold reached

Sequential prefetch statistics (message DSNB412I):**REQUESTS**

Sequential prefetch requests

PREFETCH I/O

Sequential prefetch read I/O operations

PAGES READ

Number of pages read with sequential prefetch

List prefetch statistics (message DSNB413I):**REQUESTS**

List prefetch requests

PREFETCH I/O

List prefetch read I/O operations

PAGES READ

Number of pages read due to list prefetch

Dynamic prefetch statistics (message DSNB414I):**REQUESTS**

Dynamic prefetch requests

PREFETCH I/O

Dynamic prefetch read I/O operations

-DISPLAY BUFFERPOOL (DB2)

PAGES READ

Number of pages read with dynamic prefetch

Disabled prefetch statistics (message DSNB415I):

NO BUFFER

Prefetch disabled - no buffer

NO READ ENGINE

Prefetch disabled - no read processor

Page update statistics (message DSNB420I):

SYS PAGE UPDATES

System page updates

SYS PAGES WRITTEN

System pages written

ASYNCR WRITE I/O

Asynchronous write I/O operations

SYNC WRITE I/O

Synchronous write I/O operations

Page write statistics (message DSNB421I):

DWT HIT

Number of times deferred write threshold reached

VERTICAL DWT HIT

Number of times vertical deferred write threshold reached

NO WRITE ENGINE

Number of times write processor not available for I/O operations

Hiperpool activity (not using the Asynchronous Data Mover Facility): (message DSNB430I)

SYNC HP READS

Number of times that a requested page was found in hiperpool and synchronously moved to virtual buffer pool

SYNC HP WRITES

Number of pages synchronously moved from the virtual buffer pool to the hiperpool

ASYNCR HP READS

Number of times that a requested page was found in hiperpool and asynchronously moved to virtual buffer pool without the use of the Asynchronous Data Mover Facility

ASYNCR HP WRITES

Number of pages asynchronously moved from the virtual buffer pool to the hiperpool without the use of the Asynchronous Data Mover Facility

READ FAILURES

Number of page read failures (other than those that occurred using the Asynchronous Data Mover Facility)

WRITE FAILURES

Number of page write failures (other than those that occurred using the Asynchronous Data Mover Facility)

-DISPLAY BUFFERPOOL (DB2)

Hiperpool activity (using the Asynchronous Data Mover Facility) (message DSNB431I):

Note: When Fast Synchronous Data Mover Facility (FSDMF) is installed, these counters will be zero.

HP READS

Number of pages moved asynchronously from the hiperpool to the virtual pool using the Asynchronous Data Mover Facility

HP WRITES

Number of pages moved asynchronously from the virtual pool to the hiperpool using the Asynchronous Data Mover Facility

READ FAILURES

Number of page read failures that occurred using the Asynchronous Data Mover Facility

WRITE FAILURES

Number of page write failures using that occurred the Asynchronous Data Mover Facility

Parallel processing activity (message DSNB440I):

PARALLEL REQUEST

Number of negotiations for task streams for parallel processing activity

DEGRADED PARALLEL

Number of times negotiation resulted in a degraded mode of operation

Examples

Example 1: A summary report is the default report if the DETAIL option is not specified. The following is an example of a summary report which could be produced by the command:

```
-DIS BUFFERPOOL(BP0) LIST(*) DBNAME(DSN8*)
```

```
DSNB401I - BUFFERPOOL NAME BP0, BUFFERPOOL ID 0, USE COUNT 20
DSNB402I - VIRTUAL BUFFERPOOL SIZE = 500 BUFFERS 736
           ALLOCATED      =      500   TO BE DELETED   =          0
           IN-USE/UPDATED  =          0
DSNB403I - HIPERPOOL SIZE = 10000 BUFFERS, CASTOUT = YES
           ALLOCATED      =      0   TO BE DELETED   =          0
           BACKED BY ES   =          0
DSNB404I - THRESHOLDS - 739
           VP SEQUENTIAL  = 80   HP SEQUENTIAL      = 75
           DEFERRED WRITE = 85   VERTICAL DEFERRED WRT = 80,0
           PARALLEL SEQUENTIAL = 50 ASSISTING PARALLEL SEQT = 0
DSNB406I - VIRTUAL BUFFERPOOL TYPE = -737
           CURRENT        = PRIMARY
           PENDING        = PRIMARY
           PAGE STEALING METHOD = LRU
DSNB460I - 740
```

Example 2: A detail report can be generated that includes all summary report information and additional buffer pool related statistics. The following is an example of a detail report that could be produced by the command:

```
-DISPLAY BUFFERPOOL(BP0) DETAIL
```

-DISPLAY BUFFERPOOL (DB2)

```

DSNB401I - BUFFERPOOL NAME BP0, BUFFERPOOL ID 0, USE COUNT 10
DSNB402I - VIRTUAL BUFFERPOOL SIZE = 1000 BUFFERS
          ALLOCATED      =      1000    TO BE DELETED    =          0
          IN-USE/UPDATED  =       200
DSNB403I - HIPERPOOL SIZE = 600000 BUFFERS, CASTOUT = YES
          ALLOCATED      =     600000    TO BE DELETED    =          0
          BACKED BY ES   =     483651
DSNB404I - THRESHOLDS -
          VP SEQUENTIAL   =      80      HP SEQUENTIAL     =      80
          DEFERRED WRITE  =      50      VERTICAL DEFERRED WRT = 10
          PARALLEL SEQUENTIAL = 50
DSNB405I - HIPERSPACE NAMES - @001SSOP @002SSOP

DSNB409I - INCREMENTAL STATISTICS SINCE 10:32:48 OCT 23, 1993

DSNB411I - RANDOM GETPAGE      =      230 SYNC READ I/O (R) =      180
          SEQ.  GETPAGE        =      610 SYNC READ I/O (S) =       20
          DMTH HIT              =          0

DSNB412I - SEQUENTIAL PREFETCH -
          REQUESTS             =          0    PREFETCH I/O   =          0
          PAGES READ           =          0

DSNB413I - LIST PREFETCH -
          REQUESTS             =          0    PREFETCH I/O   =          0
          PAGES READ           =          0

DSNB414I - DYNAMIC PREFETCH -
          REQUESTS             =          0    PREFETCH I/O   =          0
          PAGES READ           =          0

DSNB415I - PREFETCH DISABLED -
          NO BUFFER            =          0    NO READ ENGINE  =          0
DSNB420I - SYS PAGE UPDATES    =          0    SYS PAGES WRITTEN =          0
          ASYNC WRITE I/O      =          0    SYNC WRITE I/O   =          0
DSNB421I - DWT HIT             =          0    VERTICAL DWT HIT =          0
          NO WRITE ENGINE      =          0

DSNB430I - HIPERPOOL ACTIVITY (NOT USING ASYNCHRONOUS
          DATA MOVER FACILITY) -
          SYNC HP READS        =      100    SYNC HP WRITES   =          0
          ASYNC HP READS       =          0    ASYNC HP WRITES  =          0
          READ FAILURES        =          0    WRITE FAILURES   =          0

DSNB431I - HIPERPOOL ACTIVITY (USING ASYNCHRONOUS
          DATA MOVER FACILITY) -
          HP READS              =      244    HP WRITES        =          3
          READ FAILURES         =          0    WRITE FAILURES   =          0

DSNB440I - PARALLEL ACTIVITY -
          PARALL REQUEST        =          0    DEGRADED PARALL =          0

DSN9022I - DSNB1CMD '-DISPLAY BUFFERPOOL' NORMAL COMPLETION

```

Example 3: With the summary or detail report, you can list open table spaces and index spaces associated with the buffer pool. You can also request a display of statistics for each listed table space and index space. An example of a report generating this information could be produced by the command:

```
-DISPLAY BUFFERPOOL(BP0) LIST LSTATS
```

-DISPLAY BUFFERPOOL (DB2)

```
DSNB401I - BUFFERPOOL NAME BP0, BUFFERPOOL ID 0, USE COUNT 3
DSNB402I - VIRTUAL BUFFERPOOL SIZE = 1000 BUFFERS
          ALLOCATED      =      1000   TO BE DELETED   =          0
          IN-USE/UPDATED =       200
DSNB403I - HIPERPOOL SIZE = 100000 BUFFERS, CASTOUT = YES
          ALLOCATED      =     100000   TO BE DELETED   =          0
          BACKED BY ES   =      89152
DSNB404I - THRESHOLDS -
          VP SEQUENTIAL      = 80   HP SEQUENTIAL      = 80
          DEFERRED WRITE     = 50   VERTICAL DEFERRED WRT = 10
          PARALLEL SEQUENTIAL = 50
DSNB405I - HIPERSPACE NAMES - @001SSOP
DSNB455I - SYNCHRONOUS I/O DELAYS -
          AVERAGE DELAY = 22   MAXIMUM DELAY   = 35
          TOTAL PAGES   = 23
DSN9022I - DSNB1CMD '-DISPLAY BUFFERPOOL' NORMAL COMPLETION
```

-DISPLAY DATABASE (DB2)

-DISPLAY DATABASE (DB2)

The DB2 command DISPLAY DATABASE displays information about the status of DB2 databases, table spaces, tables in segmented table spaces, LOB table spaces, index spaces within a database, indexes on auxiliary tables, and partitions of partitioned table spaces and index spaces.

DISPLAY DATABASE RESTRICT indicates if a table space, index space, or partition is in any pending status. Use the ADVISORY option without the RESTRICT option to display any objects that are in an advisory pending status, such as the informational COPY pending or auxiliary warning advisory status.

In a data sharing environment, the command can be issued from any DB2 in the group that has access to the database.

Abbreviation: -DIS DB

Environment

This command can be issued from an MVS console, a DSN session under TSO, a DB2I panel (DB2 COMMANDS), an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

Data sharing scope: Group

Authorization


No special privilege is required to issue -DISPLAY DATABASE.

The DISPLAY system privilege allows you to display status information for any database. The resulting display lists those databases for which the primary authorization ID or any of the secondary authorization IDs has the DISPLAYDB privilege. Error messages are produced for those databases specified over which the set of privileges does not include one of the following:

- DISPLAYDB privilege
- DISPLAY privilege
- DBMAINT, DBCTRL, or DBADM authority
- SYSOPR, SYSCTRL, or SYSADM authority

DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.

Syntax



Notes:

- 1 If you specify the ONLY option without the SPACENAM() keyword, only the LIMIT, AFTER, and RESTRICT keywords apply.

-DISPLAY DATABASE (DB2)

Option descriptions

(*database-name*, ...)

Identifies one or more databases whose status is to be displayed.

- (*) Displays information on all databases that are defined to the DB2 subsystem for which the privilege set of the process has the required authorization.

dbname and *dbstring* can have any of the forms in the following table (where *dbname1* and *dbname2* represent any strings of from one to eight characters, and *dbname* represents any string of from one to seven characters):

Table 14. Forms of *dbname* and *dbstring*

Form	Displays the status of...
<i>dbname1:dbname2</i>	All databases whose names collate greater than or equal to <i>dbname1</i> and less than or equal to <i>dbname2</i>
<i>dbname*</i>	All databases whose names begin with the string <i>dbname</i>
<i>*dbname</i>	All databases whose names end with the string <i>dbname</i>
<i>*dbname*</i>	All databases whose names contain the string <i>dbname</i>
<i>*dbstring1*dbstring2*</i>	All databases whose names contain the strings <i>dbstring1</i> and <i>dbstring2</i>

SPACENAM

Specifies what space to display. If you use SPACENAM, you must also specify the corresponding database name. If (*) is used to specify multiple databases, SPACENAM(*) can be specified to display all objects in these databases.

Abbreviation: SPACE, SP

(*space-name*, ...)

Lists one or more spaces whose status is to be displayed. You can write *space-name* like *database-name* to designate:

- The name of a single table space or index space
- A range of names
- A partial name, including a beginning or ending pattern-matching character (*), a pattern-matching character between two strings, or any combination of these³

- (*) Displays information about all table spaces and index spaces of the specified database.

spacename and *spacestring* can have any of the forms in the following table (where *spacename1* and *spacename2* represent any strings of from one to eight characters, and *spacename* represents any string of from one to seven characters):

Table 15. Forms of *spacename* and *spacestring*

Form	Displays the status of...
<i>spacename1::spacename2</i>	All table spaces or index spaces whose names collate greater than or equal to <i>spacename1</i> and less than or equal to <i>spacename2</i>

3. Consecutive pattern-matching characters (*) are not allowed, and you cannot specify two pattern-matching characters in the middle of a keyword string.

Table 15. Forms of spacename and spacestring (continued)

<code>spacename*</code>	All table spaces or index spaces whose names begin with the string <i>spacename</i>
<code>*spacename</code>	All table spaces or index spaces whose names end with the string <i>spacename</i>
<code>*spacename*</code>	All table spaces or index spaces whose names contain the string <i>spacename</i>
<code>*spacestring1*spacestring2*</code>	All table spaces or index spaces whose names contain the strings <i>spacestring1</i> and <i>spacestring2</i>

USE

Displays information about the following:

- The applications and subsystems of the database or space that has internal DB2 resources allocated
- The applications and subsystems of the database or space on whose behalf locks for the space are held or waited upon
- The connection IDs, correlation IDs, and authorization IDs for all applications allocated to spaces and partitions whose statuses are displayed
- The LUWID and location of any remote threads accessing the local database

CLAIMERS

Displays information about the following:

- The claims on all table spaces, index spaces and partitions whose statuses are displayed
- The LUWID and location of any remote threads accessing the local database
- The connection IDs, correlation IDs, and authorization IDs for all applications allocated to spaces whose statuses are displayed
- The logical partitions that have logical claims and the claims associated with them

CLAIMERS overrides both LOCKS and USE. If you specify CLAIMERS, any references to LOCKS or USE are ignored.

LOCKS

Displays information about the following:

- The applications and subsystems on whose behalf locks are held, waited upon, or retained for the database or space
- The transaction locks for all table spaces, tables, index spaces and partitions whose statuses are displayed
- The connection IDs, correlation IDs, and authorization IDs for all applications allocated to spaces whose statuses are displayed
- The LUWID and location of any remote threads accessing the local database
- The drain locks for a resource held by running jobs
- The logical partitions that have drain locks and the drain locks associated with them
- The retained locks for a resource
- The page set or partition physical locks (P-locks) for a resource

LOCKS overrides USE. If both LOCKS and USE are specified, USE is ignored.

For a description of DB2 locking, see Part 5 (Volume 2) of *DB2 Administration Guide*.

LPL

Displays logical page list entries.

-DISPLAY DATABASE (DB2)

WEPR

Displays write error page range information.

ONLY

Displays information about the specified object.

without SPACENAM() keyword

Displays only database information. DB2 does not display information for the spaces within the database you specified with the DISPLAY DATABASE command. If you specify ONLY, the following keywords are valid:

- RESTRICT
- LIMIT
- AFTER

with SPACENAM() keyword

Displays the table spaces or indexes that have information requested by the DISPLAY DATABASE command. If you specify SPACENAM() ONLY, you must also specify one of the following keywords:

- USE
- CLAIMERS
- LOCKS
- LPL
- WEPR

DB2 displays tables with table locks when you specify both the LOCKS and ONLY keywords.

PART (*integer*, ...)

Indicates the partition number of one or more partitions whose status is to be displayed. The *integer* specified must identify a valid partition number for the corresponding space name and database name. *integer* can be written to designate either:

- A list of one or more partitions, or
- A range of all partition numbers that collate greater than or equal to *integer1* and less than or equal to *integer2*

Both a list and a range cannot be specified.

LIMIT

Limits the number of messages to be displayed by the command.

(*integer*)

Is the maximum number of messages that are to be displayed. The **default** is **50**. The maximum number of messages that can be displayed is limited by the space available.

(*) Limits the display to the space available.

AFTER

Displays the following information:

- If only a database name is used, AFTER continues the display of all other databases whose names collate greater than that name.
- If SPACENAM and a table space or index space name are used, AFTER continues the display to all other table spaces or index spaces in the same database whose names collate greater than that name.

AFTER cannot be used with more than one database name, table space name, index space name, with any pattern-matching character (*) within the database name, or with the **SPACENAM()** keyword.

ACTIVE

Limits the display to table spaces or index spaces that have had internal DB2 resources allocated to applications and are in a started state or to databases that contain such spaces.

Abbreviation: A

Default: Using neither ACTIVE nor RESTRICT displays information on all databases defined to DB2.

RESTRICT

Limits the display to databases, table spaces, or indexes in a restricted status. This includes those page sets that have logical page list entries. Specifying one or more keywords further limits the display to the named objects only.

Abbreviation: RES

Use of a database is restricted if the database is in any one of the following situations:

- It is started for read-only processing.
- It is started for utility-only processing.
- It is stopped.

Use of a table space or index space is restricted if:

- It is in one of the three situations above.
- It is being processed by a utility.
- It is in COPY-pending, CHECK-pending, RECOVER-pending, group buffer pool RECOVER-pending, auxiliary CHECK-pending, or REORG-pending status.
- It contains a page error range.
- It contains pages in the logical page list (LPL).

Specify one or more of the following keywords to limit objects that are to be listed.

ACHKP

Displays objects in the auxiliary warning advisory state.

CHKP Displays objects that are in CHECK-pending status.

COPY Display objects that are in COPY-pending status.

GRECP

Displays objects that are in group buffer pool RECOVER-pending status.

LPL Displays logical page list entries.

RBDP Displays index objects that are in REBUILD- or RECOVER-pending status. This includes the restricted states RBDP, LPL, and WEPR.

RECP Displays objects that are in RECOVER-pending status, including the restricted states RECP, RECP*, LPL, and WEPR (write error page range).

REORP

Displays objects that are in REORG-pending status.

RO Displays objects that are in read-only mode.

STOP Displays objects that are stopped, including the restricted states STOP, STOPE, STOPP, and LSTOP.

UT Displays objects that are in utility access mode.

-DISPLAY DATABASE (DB2)

- UTRO** Display objects that are serialized for utility access and available for read-only access.
- UTRW** Display objects that are serialized for utility access and available for read-write access.
- UTUT** Displays objects that are serialized for utility access and unavailable.
- UT*** Displays objects that are in any utility access mode: UT, UTRW, UTRO, or UTUT.
- WEPR** Displays write error page range information.

ADVISORY

Limits the display to indexes and table spaces to which read-write access is allowed, but for which some action is recommended.

Abbreviation: ADV

Use the DISPLAY DATABASE ADVISORY command without the RESTRICT option to determine when:

- An index space is in the informational COPY pending (ICOPY) advisory status.
- A base table space or LOB table space is in the auxiliary warning (AUXW) advisory status.

Specify one or more of the following keywords to limit the objects listed.

AUXW

Displays objects that are in the auxiliary warning advisory state.

ICOPY

Displays objects that are in the informational copy pending advisory state.

For information about resetting an advisory status, see Part 2 of *DB2 Utility Guide and Reference*.

Usage notes

Displaying DB2 catalog tables: You can always display the DB2 catalog tables. However, if a table space in the catalog containing information about user databases or user table spaces is stopped, those databases or table spaces cannot be displayed. Trying to display them will cause an error. See Appendix D of *DB2 SQL Reference* for a list of table space names and assigned tables.

If you issue DISPLAY DATABASE LOCKS on the catalog (DSNDB06), you may see a lock held on SYSDBASE with the correlation ID 020.DBCMD_05 or 020.DBCMD_06. This simply indicates the lock that DISPLAY DATABASE itself needs and is normal.

Displaying restricted and advisory status objects: To display all resources that are in restricted status, you must issue the DISPLAY DATABASE command twice. To display table spaces and indexes in restricted status, use the SPACENAM parameter with RESTRICT. To display databases in restricted status, do NOT use the SPACENAM parameter. Spaces could be unavailable even if they show RW mode if the database is in restricted status.

-DISPLAY DATABASE (DB2)

To display all resources that are in advisory status, issue the DISPLAY DATABASE ADVISORY command without the RESTRICT option. For information about resetting a restrictive or advisory status, see Part 2 of *DB2 Utility Guide and Reference*.

Communications Database and Resource Limit Facility: If the command specifies a table space or index space in the communications database or in the active resource limit facility database, then the USE option displays the names of all members of the data sharing group that are using the specified table space or index space. Knowing which other members of the data sharing group might be using these spaces is useful when considering whether to drop table spaces and index spaces in the communications database and the resource limit facility database.

Displaying logical partitions: If you issue DISPLAY DATABASE with the PART parameter for a logical partition of a type 2 index, DB2 does not display physical claimers and physical locks in the output.

Displaying databases for declared temporary tables: DISPLAY DATABASE displays information about databases that are created with the AS TEMP option and the associated table spaces, but does not display information for declared temporary tables or index spaces that the database contains.

Output

Message DSNT392I status information: The status codes that are displayed by the DISPLAY DATABASE command and their respective descriptions are as follows:

ACHKP

Indicates an error in the LOB column of the base table space. The base table space has the auxiliary CHECK-pending restrictive status.

AREST

Indicates that an object (a table space, index space, or a physical partition of a table space or index space) is in an advisory RESTART-pending state. If backout activity against the object is not already underway, initiate it either by issuing the RECOVER POSTPONED command, or by recycling the system with the system parameter LBACKOUT=AUTO.

AUXW

Either the base table space is in the auxiliary warning advisory status, indicating an error in the LOB column, or the LOB table space is in the auxiliary warning advisory status, indicating an invalid LOB.

CHKP The object (a table space, a partition within a table space, or an index) is in the CHECK-pending status.

COPY The object (a table space or a partition within a table space) is in the COPY-pending status. An image copy is required for this object.

GRECP

The object is GBP-dependent and a group buffer pool RECOVER is pending.

ICOPY

The index space is in the informational COPY-pending advisory status.

LPL The object has entries in the logical page list.

LSTOP

The logical partition of a nonpartitioning index is stopped.

-DISPLAY DATABASE (DB2)

PSRBD

The entire nonpartitioning index space is in a page set REBUILD pending status.

RBDP The physical or logical index partition is in the REBUILD pending status.

RBDP*

The logical partition of a nonpartitioning index is in the REBUILD pending status, and the entire index is inaccessible to SQL applications. However, only the logical partition needs to be rebuilt.

RECP The object (a table space, table space partition, index space, index partition, or logical index partition) is in the RECOVER-pending status.

REFP The object (a table space, index space, or an index) is in the REFRESH-pending status.

RELDP

The object has a release dependency.

REORP

The data partition is in the REORG-pending status.

RESTP

The table space or index space is in the restart-pending status.

RO The database, table space, table space partition, index space, or index space partition is started for read-only activity.

RW The database, table space, table space partition, index space, or index space partition is started for read and write activity.

STOP The database, table space, table space partition, index space, or index space partition is stopped.

STOPE

The table space or index space was implicitly stopped because there is a problem with the log RBA in a page. Message DSNT500I or DSNT501I is issued when the error is detected, indicating the inconsistency.

STOPP

A stop is pending for the database, table space, table space partition, index space, or index space partition.

UT The database, table space, table space partition, index space, or index space partition is started for utility processing only.

UTRO A utility is in process, on the table space, table space partition, index space, or index space partition, that allows only RO access. If the utility was canceled before the object was drained, the object can allow SQL access because the object was not altered by the utility.

UTRW A utility is in process, on the table space, table space partition, index space, or index space partition, that allows RW access.

UTUT A utility is in process, on the table space, table space partition, index space, or index space partition, that allows only UT access. If the utility was canceled before the object was drained, the object can allow SQL access because the object was not altered by the utility.

WEPR Displays write error page range information.

Examples

Example 1: Display information about table space TBS33 in database CB3. USE causes *connection-name*(CONNID), *correlation-id*(CORRID), and *authorization ID*(USERID) information to be displayed.

```
-DISPLAY DATABASE(CB3) SPACENAM(TBS33) USE
```

The following output is generated:

```
DSNT360I - *****
DSNT361I - *   DISPLAY DATABASE SUMMARY
          *   GLOBAL USE
DSNT360I - *****
DSNT362I -   DATABASE = CB3  STATUS = RW
          DBD LENGTH = 4028
DSNT397I -
NAME      TYPE PART STATUS          CONNID   CORRID      USERID
-----
TBS33     TS    01  RW              LSS001   DSN2SQL    SYSADM
TBS33     TS    02  RW              LSS001   DSN2SQL    SYSADM
TBS33     TS    03  RW              LSS001   DSN2SQL    SYSADM
TBS33     TS    04  RW              LSS001   DSN2SQL    SYSADM
***** DISPLAY OF DATABASE CB3      ENDED *****
DSN9022I . DSNTDDIS 'DISPLAY DATABASE' NORMAL COMPLETION
```

Example 2: Display information about table space TBS33 in database CB3 when the table space is defined with LOCKPART YES. LOCKS displays lock information for table spaces and tables specified; LUWIDs and locations of any remote threads; and *connection-name*, *correlation-id*, and *authorization ID* information.

```
-DISPLAY DATABASE(CB3) SPACENAM(TBS33) LOCKS
```

The following output is generated:

```
DSNT360I - *****
DSNT361I - *   DISPLAY DATABASE SUMMARY
          *   GLOBAL LOCKS
DSNT360I - *****
DSNT362I -   DATABASE = CB3  STATUS = RW
          DBD LENGTH = 4028
DSNT397I -
NAME      TYPE PART STATUS          CONNID   CORRID      LOCKINFO
-----
TBS33     TS    01  RW
TBS33     TS    02  RW
TBS33     TS    03  RW
TBS33     TS    04  RW              LSS004   DSN2SQL    H(IS,S,C)
TBS33     TS    04  RW              LSS005   DSN2SQL    H(IS,S,C)
***** DISPLAY OF DATABASE CB3      ENDED *****
```

Example 3: Display information about table space TBS33 in database CB3. CLAIMERS displays claim types and durations; LUWIDs and locations of any remote threads; and *connection-name*, *correlation-id*, and *authorization ID* information.

```
-DISPLAY DATABASE(CB3) SPACENAM(TBS33) CLAIMERS
```

The following output is generated:

-DISPLAY DATABASE (DB2)

```

DSNT360I - *****
DSNT361I - *   DISPLAY DATABASE SUMMARY
          *   GLOBAL CLAIMERS
DSNT360I - *****
DSNT362I -   DATABASE = CB3  STATUS = RW
          DBD LENGTH = 4028
DSNT397I -
NAME      TYPE PART STATUS          CONNID  CORRID      CLAIMINFO
-----
TBS33    TS    01  RW
TBS33    TS    02  RW
TBS33    TS    03  RW
TBS33    TS    04  RW          LSS001  DSN2SQL      (RR,C)
TBS33    TS    04  RW          LSS001  DSN2SQL      (WR,C)
***** DISPLAY OF DATABASE CB3      ENDED      *****

```

Example 4: In a data sharing environment, display information about locks held when the table space is defined with LOCKPART YES. The application identified as LSS001 on member DB1G has locked partitions 1 and 2. LSS002 on member DB2G has locked partitions 1 and 3. Partition 4 has no locks held on it.

-DISPLAY DATABASE(DSN8D51A) SPACENAM(TSPART) LOCKS

Output similar to the following output is generated:

NAME	TYPE	PART	STATUS	CONNID	CORRID	LOCKINFO
TSPART	TS	01	RO	LSS001	DSN2SQL	H-IS,P,C
-			MEMBER NAME DB1G			
TSPART	TS	01	RO			H-S,PP,I
-			MEMBER NAME DB1G			
TSPART	TS	01	RO	LSS002	DSN2SQL	H-IS,P,C
-			MEMBER NAME DB2G			
TSPART	TS	01	RO			H-S,PP,I
-			MEMBER NAME DB2G			
TSPART	TS	02	RW	LSS001	DSN2SQL	H-IS,P,C
-			MEMBER NAME DB1G			
TSPART	TS	02	RW			H-S,PP,I
-			MEMBER NAME DB1G			
TSPART	TS	03	RW	LSS002	DSN2SQL	H-IS,P,C
-			MEMBER NAME DB2G			
TSPART	TS	03	RW			H-S,PP,I
-			MEMBER NAME DB2G			
TSPART	TS	04	RW			

If the table space is defined with LOCKPART NO, the display looks like this. The LOCKINFO field shows a value of S, indicating that this is a table space lock. If partitions are held in different statuses, those statuses are listed below the table space locks.

NAME	TYPE	PART	STATUS	CONNID	CORRID	LOCKINFO
TSPART	TS			LSS001	DSN2SQL	H-IS,S,C
-			MEMBER NAME DB1G			
TSPART	TS			LSS002	DSN2SQL	H-IS,S,C
-			MEMBER NAME DB2G			
TSPART	TS	01	RO			H-S,PP,I
-			MEMBER NAME DB1G			
TSPART	TS	02	RW			H-S,PP,I
-			MEMBER NAME DB2G			
TSPART	TS	03	RW			H-S,PP,I
-			MEMBER NAME DB2G			
TSPART	TS	04	RW			

-DISPLAY DATABASE (DB2)

Example 5: Display information about page sets in database DSNDB01 that have entries in the logical page list. Limit the number of messages displayed to the space available.

```
-DB1G DISPLAY DATABASE(DSNDB01) SPACENAM(*) LIMIT(*) LPL
```

Output similar to the following output is generated:

```
*****
DSNT361I -DB1G *   DISPLAY DATABASE SUMMARY
              *   GLOBAL LPL
DSNT360I -DB1G
*****
DSNT362I -DB1G   DATABASE = DSNDB01   STATUS = RW
              DBD LENGTH = 8000
DSNT397I -DB1G
NAME      TYPE PART STATUS              LPL PAGES
-----
DBD01     TS      RW,LPL,GRECP          000001,000004,00000C,000010
-----
          TS      RW                    000039-00003C
SPT01     TS      RW
SCT02     TS      RW
SYSLGRNG  TS      RW
SYSUTILX  TS      RW
SYSLGRNX  TS      RW,LPL,GRECP          000000-FFFFFF
DSNSCT02  IX      RW
DSNSPT01  IX      RW
DSNSPT02  IX      RW
DSNLUX01  IX      RW
DSNLUX02  IX      RW
DSNLLX01  IX      RW
DSNLLX02  IX      RW
***** DISPLAY OF DATABASE DSNDB01 ENDED *****
DSN9022I -DB1G DSNTDDIS 'DISPLAY DATABASE' NORMAL COMPLETION
```

Example 6: Suppose that table space TSPART, which is in database DSN8D71A, is defined with the keyword LOCKPART NO, which means that DB2 does not do selective partition locking on TSPART. When you specify this command:

```
-DB1G DISPLAY DATABASE(DSN8D71A) SPACE(TSPART) PART(1,4) LOCKS
```

two applications are accessing TSPART, and the partitions have different statuses. In the output, DB2 displays the locks as table space locks, as shown here:

NAME	TYPE	PART	STATUS	CONNID	CORRID	LOCKINFO
TSPART	TS			LSS001	DSN2SQL	H-IS,S,C
TSPART	TS			LSS002	DSN2SQL	H-IS,S,C
TSPART	TS	01	RO			
TSPART	TS	04	RW			

Example 7: Suppose that you have executed the ALTER TABLESPACE statement on table space TSPART so that TSPART is now defined with LOCKPART YES. LOCKPART YES causes DB2 to do selective partition locking on TSPART. When you specify this command:

```
-DB1G DISPLAY DATABASE(DSN8D71A) SPACE(TSPART) PART(1:4) LOCKS
```

two applications are accessing TSPART. The application identified by connection ID LSS001 has locked partitions 1 and 2. The application identified by connection ID LSS002 has locked partitions 1 and 3. In the output, DB2 displays the locks as partition locks, as shown here:

NAME	TYPE	PART	STATUS	CONNID	CORRID	LOCKINFO
TSPART	TS	01	RO	LSS001	DSN2SQL	H-IS,P,C

-DISPLAY DATABASE (DB2)

TSPART	TS	01	RO	LSS002	DSN2SQL	H-IS,P,C
TSPART	TS	02	RW	LSS001	DSN2SQL	H-IS,P,C
TSPART	TS	03	RW	LSS002	DSN2SQL	H-IS,P,C
TSPART	TS	04	RW			

Example 8: Display information about all table spaces and index spaces in the range of databases from DBKD0101 to DBKD0106 that are in a restrictive status. Limit the number of messages that are displayed to the available space.

```
-DISPLAY DATABASE(DBKD0101,DBKD0103) SPACENAM(*) RESTRICT LIMIT(*)
```

Output similar to the following output is generated:

```
DSNT360I - *****
DSNT361I - *   DISPLAY DATABASE SUMMARY
          *   RESTRICTED
DSNT360I - *****
DSNT362I -          DATABASE = DBKD0101  STATUS = RW
          DBD LENGTH = 4028
DSNT397I -
NAME      TYPE PART STATUS          PHYERRLO PHYERRHI CATALOG  PIECE
-----
TLKD0101 TS      RW,RESTP
IUKD011A IX      RW,RESTP
IXKD011B IX      RW,RESTP
```

Example 9: Display information about all table spaces that are in the auxiliary warning advisory status (AUXW), and all index spaces that are in informational COPY pending status (ICOPY) in database DBIQUQ01. Limit the number of messages that are displayed to the available space.

```
-DISPLAY DATABASE(DBIQUQ01) SPACENAM(*) LIMIT(*) ADVISORY
```

Output similar to the following output is generated:

```
DSNT360I - *****
DSNT361I - *   DISPLAY DATABASE SUMMARY
          *   ADVISORY
DSNT360I - *****
DSNT362I -          DATABASE = DBIQUQ01  STATUS = RW
          DBD LENGTH = 8066
DSNT397I -
NAME      TYPE PART STATUS          PHYERRLO PHYERRHI CATALOG  PIECE
-----
TPIQUQ01 TS      001 RW,AUXW
TPIQUQ01 TS      002 RW,AUXW
TPIQUQ01 TS      003 RW,AUXW
TPIQUQ01 TS      004 RW,AUXW
IAIQUQ01 IX      RW,ICOPY
IAIQUQ02 IX      RW,ICOPY
IAIQUQ03 IX      RW,ICOPY
IAIQUQ04 IX      RW,ICOPY
IPIQUQ01 IX      001 RW,ICOPY
IPIQUQ01 IX      002 RW,ICOPY
IPIQUQ01 IX      003 RW,ICOPY
IPIQUQ01 IX      004 RW,ICOPY
IUIQUQ03 IX      RW,ICOPY
IXIQUQ02 IX      RW,ICOPY
***** DISPLAY OF DATABASE DBIQUQ01 ENDED *****
DSN9022I - DSNTDDIS 'DISPLAY DATABASE' NORMAL COMPLETION
```


-DISPLAY DDF (DB2)

The -DISPLAY DDF command displays information regarding the status and configuration of DDF, as well as statistical information regarding connections or threads controlled by DDF.

Abbreviation: -DIS DDF

Environment

This command can be issued from an MVS console, a DSN session under TSO, a DB2I panel (DB2 COMMANDS), an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

Data sharing scope: Member

Authorization

To execute this command, the privilege set of the process must include one of the following:

- DISPLAY privilege
- SYSOPR, SYSCTRL, or SYSADM authority

DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.

Syntax

```
►►—DISPLAY DDF—[DETAIL]—◄◄
```

Option descriptions

DETAIL

Displays additional configurational and statistical information.

Output

The -DISPLAY DDF command displays the following output:

STATUS

The operational status of DDF.

LOCATION

The location name of DDF.

LUNAME

The fully qualified LUNAME of DDF.

GENERICLU

The fully qualified generic LUNAME of DDF.

IPADDR

The IP address of DDF.

TCPPORT

The SQL listener port used by DDF.

-DISPLAY DDF (DB2)

RESPORT

The resync listener port used by DDF.

DOMAIN

The SQL and resync domains used by DDF.

Examples

Example 1: Display DDF detail report where DDF has not yet been started:

```
#dis ddf det
DSNL080I # DSNLTDDF DISPLAY DDF REPORT FOLLOWS:
DSNL081I STATUS=STOPDQ
DSNL082I LOCATION          LUNAME          GENERICLU
DSNL083I STL715B           -NONE.SYEC715B  -NONE
DSNL084I IPADDR            TCPPOORT RESPORT
DSNL085I -NONE             447      5002
DSNL086I SQL      DOMAIN=-NONE
DSNL086I RESYNC  DOMAIN=-NONE
DSNL090I DT=A  CONDBAT=    64  MDBAT=    64
DSNL092I ADBAT=    0  QUEDBAT=    0  IN1DBAT=    0  CONQUED=    0
DSNL093I DSCDBAT=    0  IN2CONS=    0
DSNL099I DSNLTDDF DISPLAY DDF REPORT COMPLETE
```

Example 2: Display DDF report where DDF is started:

```
#dis ddf det
DSNL080I # DSNLTDDF DISPLAY DDF REPORT FOLLOWS:
DSNL081I STATUS=STARTD
DSNL082I LOCATION          LUNAME          GENERICLU
DSNL083I STL715B           USIBMSY.SYEC715B -NONE
DSNL084I IPADDR            TCPPOORT RESPORT
DSNL085I 9.112.114.103     447      5002
DSNL086I SQL      DOMAIN=v7ec103.stl.ibm.com
DSNL086I RESYNC  DOMAIN=v7ec103.stl.ibm.com
DSNL099I DSNLTDDF DISPLAY DDF REPORT COMPLETE
```

Example 3: Display DDF detail report where DDF is started:

```
#dis ddf det
DSNL080I # DSNLTDDF DISPLAY DDF REPORT FOLLOWS:
DSNL081I STATUS=STARTD
DSNL082I LOCATION          LUNAME          GENERICLU
DSNL083I STL715B           USIBMSY.SYEC715B -NONE
DSNL084I IPADDR            TCPPOORT RESPORT
DSNL085I 9.112.114.103     447      5002
DSNL086I SQL      DOMAIN=v7ec103.stl.ibm.com
DSNL086I RESYNC  DOMAIN=v7ec103.stl.ibm.com
DSNL090I DT=A  CONDBAT=    64  MDBAT=    64
DSNL092I ADBAT=    1  QUEDBAT=    0  IN1DBAT=    0  CONQUED=    0
DSNL093I DSCDBAT=    0  IN2CONS=    0
DSNL099I DSNLTDDF DISPLAY DDF REPORT COMPLETE
```

-DISPLAY FUNCTION SPECIFIC (DB2)

The DB2 command DISPLAY FUNCTION SPECIFIC displays statistics about external user-defined functions that DB2 applications access.

Abbreviation: -DIS FUNC SPEC

Environment

This command can be issued from an MVS console, a DSN session under TSO, a DB2I panel (DB2 COMMANDS), an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

#

Data sharing scope: Group or local, depending on the value of the SCOPE option.

Authorization

To execute this command, the privilege set of the process must include one of the following authorities for each function:


- DISPLAY privilege
- Ownership of the function
- SYSOPR authority
- SYSCTRL authority
- SYSADM authority

If -DISPLAY FUNCTION SPECIFIC *.* or schema.partial-name* is specified, the privilege set of the process must include one of the following authorities:

- SYSOPR authority
- SYSCTRL authority
- SYSADM authority

DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.

Syntax



Option descriptions

schema.specific-function-name

Displays information for the specific named function in the specified schema. You cannot specify a function name as you can in SQL; you must use the specific name. If a specific name was not specified on the CREATE FUNCTION statement, query SYSIBM.SYSROUTINES for the correct specific name:

DISPLAY FUNCTION SPECIFIC (DB2)

```
SELECT SPECIFICNAME, PARM_COUNT
FROM SYSIBM.SYSROUTINES
WHERE NAME='function_name'
AND SCHEMA='schema_name';
```

For overloaded functions, this query can return multiple rows.

*schema.partial-name**

Displays information for a set of functions in the specified schema.

The specific names of all functions in the set begin with *partial-name* and can end with any string, including the empty string. For example, *schema1.ABC** displays information for all functions with specific names that begin with ABC in *schema1*.

(*.*)

Displays information for all functions that have been accessed by DB2 applications since the DB2 subsystem was started.

SCOPE

Specifies the scope of the command.

(LOCAL)

Specifies that the display only includes information from the local member only.

(GROUP)

Specifies that the display includes information from all members of the data sharing group.

Usage notes

If you do not specify a partial or specific function name, DB2 displays information for all functions that DB2 applications have accessed since the DB2 subsystem was started.

This command does not apply to built-in functions or user-defined functions that are sourced on another function.

Output

This command displays one output line for each function that a DB2 application has accessed.

Information returned by this command reflects a dynamic status. By the time DB2 displays the information, the status might have changed.

Sample output: The DISPLAY FUNCTION SPECIFIC command generates the following output:

DSNX975I - DSNX9DIS DISPLAY FUNCTION SPECIFIC REPORT FOLLOWS -

----- SCHEMA=PAYROLL

FUNCTION	STATUS	ACTIVE	QUEUED	MAXQUE	TIMEOUT	WLM_ENV
APPL1	STARTED	1	0	0	0	PAYROLL
APPL2	STARTED	1	0	0	0	PAYROLL
APPL3	STARTED	0	1	2	0	PAYROLL
APPL5	STOPREJ	0	0	0	0	SANDBOX
APPL6	STOPABN	0	0	0	0	PAYROLL
FUNC1	STOPQUE	0	0	0	0	SANDBOX

DISPLAY FUNCTION SPECIFIC (DB2)

DSNX9DIS DISPLAY FUNCTION SPECIFIC REPORT COMPLETE
DSN9022I - DSNX9COM '-DISPLAY FUNC' NORMAL COMPLETION

DISPLAY FUNCTION SPECIFIC command output: The DISPLAY FUNCTION SPECIFIC command displays the following output:

FUNCTION

The specific name of the function.

STATUS

The status of the function. The possible values are:

STARTED

Requests for the function can be processed.

STOPQUE

Requests are queued.

STOPREJ

Requests are rejected.

STOPABN

Requests are rejected because of abnormal termination.

ACTIVE

The number of threads that are currently running the function.

QUEUED

The number of threads that are waiting for the function to be scheduled.

MAXQUE

The maximum number of threads that have waited concurrently for the function to be scheduled since the DB2 subsystem was started.

TIMEOUT

The number of times an SQL statement timed out while waiting for a request for the function to be scheduled.

WLM_ENV

The WLM environment where the function executes.

Message DSNX971I lists a range of functions that are stopped because a STOP FUNCTION SPECIFIC command included a partial name with the pattern-matching character (*). See “-STOP FUNCTION SPECIFIC” on page 321 for more information.

Examples

Example 1: Display information about functions in the PAYROLL schema and the HRPROD schema.

```
-DISPLAY FUNCTION SPECIFIC(PAYROLL.*, HRPROD.*)
```

This command produces output similar to the following output:

```
DSNX975I csect - DISPLAY FUNCTION SPECIFIC REPORT FOLLOWS-
```

```
----- SCHEMA=PAYROLL
```

FUNCTION	STATUS	ACTIVE	QUEUED	MAXQUE	TIMEOUT	WLM_ENV
PAYRFNC1	STARTED	0	0	1	0	PAYROLL
PAYRFNC2	STOPQUE	0	5	5	3	PAYROLL
PAYRFNC3	STARTED	2	0	6	0	PAYROLL
USERFNC4	STOPREJ	0	0	1	0	SANDBOX

DISPLAY FUNCTION SPECIFIC (DB2)

```
----- SCHEMA=HRPROD
FUNCTION      STATUS  ACTIVE  QUEUED  MAXQUE  TIMEOUT  WLM_ENV
HRFNC1        STARTED    0       0       1       0      HRFUNCS
HRFNC2        STOPREJ    0       0       1       0      HRFUNCS
DSNX9DIS DISPLAY FUNCTION SPECIFIC REPORT COMPLETE
DSN9022I - DSNX9COM '-DISPLAY FUNC' NORMAL COMPLETION
```

Example 2: Display information about specific functions in the PAYROLL schema.

```
-DISPLAY FUNCTION SPECIFIC(PAYROLL.USERFNC2,PAYROLL.USERFNC4)
```

This command produces output similar to the following output:

```
DSNX975I csect - DISPLAY FUNCTION SPECIFIC REPORT FOLLOWS-
```

```
----- SCHEMA=PAYROLL
FUNCTION      STATUS  ACTIVE  QUEUED  MAXQUE  TIMEOUT  WLM_ENV
USERFNC2      STOPQUE    0       5       5       3      SANDBOX
USERFNC4      STOPREJ    0       0       1       0      SANDBOX
DSNX9DIS DISPLAY FUNCTION SPECIFIC REPORT COMPLETE
DSN9022I - DSNX9COM '-DISPLAY FUNC' NORMAL COMPLETION
```

Example 3: Display information about all functions in the PAYROLL schema that DB2 applications have accessed. This example assumes that the STOP FUNCTION SPECIFIC(PAYROLL.*) ACTION(Queue) command is in effect at the time you issue the DISPLAY FUNCTION SPECIFIC command:

```
-DISPLAY FUNCTION SPECIFIC(PAYROLL.*)
```

This command produces output similar to the following output:

```
DSNX975I csect - DISPLAY FUNCTION SPECIFIC REPORT FOLLOWS-
```

```
----- SCHEMA=PAYROLL
FUNCTION      STATUS  ACTIVE  QUEUED  MAXQUE  TIMEOUT  WLM_ENV
USERFNC2      STOPQUE    0       5       5       3      SANDBOX
USERFNC4      STOPQUE    0       0       1       0      SANDBOX
FUNCTIONS USERFNC2      - USERFNC299999999999 STOP QUEUE
FUNCTIONS USERFNC4      - USERFNC499999999999 STOP QUEUE
DSNX9DIS DISPLAY FUNCTION SPECIFIC REPORT COMPLETE
DSN9022I - DSNX9COM '-DISPLAY FUNC' NORMAL COMPLETION
```

-DISPLAY GROUP (DB2)

The DB2 command DISPLAY GROUP displays information about the data sharing group to which a DB2 subsystem belongs.

Abbreviation: -DIS GROUP

Environment

This command can be issued from an MVS console, a DSN session under TSO, a DB2I panel (DB2 COMMANDS), an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

Data sharing scope: Group


Authorization

To execute this command, the privilege set of the process must include one of the following:

- DISPLAY privilege
- SYSOPR, SYSCTRL, or SYSADM authority

DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.

Syntax



Option descriptions

DETAIL

Displays information about the parallelism coordinator and parallelism assistant.

Usage notes

Member status: Message DSN7106I includes information about the XCF status of the members (STATUS in the display output). The status can be ACTIVE, QUIESCED, or FAILED.

ACTIVE indicates that the DB2 subsystem is active, and FAILED indicates that it is failed. A QUIESCED status results from a STOP DB2 command and consists of several subcategories:

QUIESCED

This is a normal quiesced state, as the result of a normal STOP DB2 command.

Q Q (quiesced) can be paired with one or more of the following letters:

I Indoubt or postponed abort units of recovery (URs) are outstanding. This means retained locks are held.

C There was a castout error. The last updater of the page set or partition could not write from the coupling facility to disk.

-DISPLAY GROUP (DB2)

Make sure there are no connectivity problems between the coupling facility and the processor before restarting DB2.

R There is retained information needed for DB2 to perform resynchronization with one or more remote locations.

When DB2 is restarted, this resynchronization occurs.

ACTIVE

This is a normal active state without conditions.

A A (active) can be paired with the following letter:

I Indoubt or postponed abort units of recovery (URs) are outstanding. This means retained locks are held.

Using this command in a non-data-sharing environment: DB2 issues the same response, except for information which does not exist: group name, member name, and member ID.

Output

DISPLAY GROUP command output: The DISPLAY GROUP command displays the following output:

*** BEGIN

The name of the DB2 group

DB2 MEMBER

The names of its members

ID The IDs of its members

SUBSYS

The subsystem names of its members

CMDPREF

The command prefix for each member

STATUS

The status of each member (ACTIVE, QUIESCED with or without additional conditions, or FAILED)

SYSTEM NAME

The names of the MVS system where the member is running, or was last running in cases when the member status is QUIESCED or FAILED

IRLM SUBSYS

The name of the IRLM subsystem to which the DB2 member is connected

IRLMPROC

The procedure names of the connected IRLM

SYSTEM NAME

The MVS system name where the data sharing member runs on.

LVL A string of three numeric characters that list as follows:

- DB2 version
- DB2 release
- DB2 modification level

SCA The SCA structure size in KB and the percentage currently in use

LOCK1

The LOCK1 structure size in KB.

-DISPLAY GROUP (DB2)

The display also shows the following:

- The maximum number of lock entries possible for the lock table and how many of those lock entries are currently in use. This number is an approximate value.
- The maximum number of modify lock list entries and how many of those list entries are currently in use.

For more information about the lock table and the list of modify locks, see Chapter 6 of *DB2 Data Sharing: Planning and Administration*.

PARALLELISM COORDINATOR

Indicates whether this DB2 member can coordinate parallel processing.

PARALLELISM ASSISTANT

Indicates whether this DB2 member can assist with parallel processing.

If the output indicates that either the lock structure or SCA are 0% in use, that does not necessarily mean that the structure is empty. It could mean that the structures are very large and that the number of locks held or the number of records in the SCA is less than 1%.

Description of message DSN7101I:

GROUP

The name of the data sharing group

GROUP LEVEL

A string of three numeric characters that denotes:

- DB2 version
- DB2 release
- DB2 modification level

This is the highest release with which any DB2 in the data sharing group have been started.

Examples

Example 1: The following sample output for a data sharing group can be generated by the command:

```
-DB1A DIS GROUP
```

-DISPLAY GROUP (DB2)

```

DSN7100I -DB1A DSN7GCMD
*** BEGIN DISPLAY OF GROUP(DSNDB10 ) GROUP LEVEL(610)
                                     GROUP ATTACH NAME(DB10)
-----
DB2      DB2 SYSTEM  IRLM
MEMBER   ID  SUBSYS  CMDPREF  STATUS  LVL NAME  SUBSYS  IRLMPROC
-----
DB1A     1  DB1A    -DB1A    ACTIVE  610 MVSA  DJ1A    DB1AIRLM
DB1B     2  DB1B    -DB1B    ACTIVE  610 MVSB  DJ1B    DB1BIRLM
DB1C     3  DB1C    -DB1C    ACTIVE  610 MVSC  DJ1C    DB1CIRLM
DB1D     4  DB1D    -DB1D    FAILED  610 MVSD  DJ1D    DB1DIRLM
DB1E     5  DB1E    -DB1E    QUIESCED 610 MVSE  DJ1E    DB1EIRLM
DB1F     6  DB1F    -DB1F    ACTIVE  610 MVSF  DJ1F    DB1FIRLM
DB1G     7  DB1G    -DB1G    ACTIVE  610 MVSG  DJ1G    DB1GIRLM
-----
SCA  STRUCTURE SIZE:      1024 KB, STATUS= AC,   SCA IN USE:      11 %
LOCK1 STRUCTURE SIZE:      1536 KB
      NUMBER LOCK ENTRIES:      262144
      NUMBER LIST ENTRIES:      7353, LIST ENTRIES IN USE:      0
*** END DISPLAY OF GROUP(DSNDB10 )
DSN9022I -DB1A DSN7GCMD 'DISPLAY GROUP ' NORMAL COMPLETION

```

Example 2: In a non-data-sharing environment, the following sample output is generated by the command:

```
-DB1A DISPLAY GROUP
```

```

DSN7100I -DB1A DSN7GCMD
*** BEGIN DISPLAY OF GROUP(.....) GROUP LEVEL(...)
                                     GROUP ATTACH NAME(....)
-----
DB2      DB2 SYSTEM  IRLM
MEMBER   ID  SUBSYS  CMDPREF  STATUS  LVL NAME  SUBSYS  IRLMPROC
-----
.....   0  DB1A    -DB1A    ACTIVE  610 MVSA  DJ1A    DB1AIRLM
-----
*** END DISPLAY OF GROUP(DSNDB10)
DSN9022I -DB1A DSN7GCMD 'DISPLAY GROUP ' NORMAL COMPLETION

```

Example 3: Using the DETAIL option, you can obtain more information about the data sharing group as shown in the following example using the command:

```
-DB1A DIS GROUP DETAIL
```

-DISPLAY GROUPBUFFERPOOL (DB2)

```
DSN7100I -DB1A DSN7GCMDB
*** BEGIN DISPLAY OF GROUP(DSNCAT ) GROUPELVEL(610)
-----
DB2      SYSTEM      IRLM
MEMBER   ID  SUBSYS  CMDPREF  STATUS  NAME    LVL  SUBSYS  IRLMPROC
-----
DB1A     1  DB1A    -DB1A    ACTIVE  MVSA     610  AR21    ARLM21
DB1B     2  DB1B    -DB1B    ACTIVE  MVSB     610  BR21    BRLM21
DB1C     3  DB1C    -DB1C    ACTIVE  MVSC     510  CRLM    CRLM21
DB2D     4  DB2D    -DB2D    FAILED  MVSD     610  DR21    DRLM21
DB2E     5  DB2E    -DB2E    QUIESCED MVSE     610  ER21    ERLM21
DB2F     6  DB2F    -DB2F    ACTIVE  MVSF     610  FR21    FRLM21
DB2G     7  DB2G    -DB2G    ACTIVE  MVSG     610  GR21    GRLM21
-----
DB2      PARALLEL    PARALLEL
MEMBER   COORDINATOR  ASSISTANT
-----
DB2A             YES      NO
DB2B             YES      YES
DB2B             YES      YES
DB1C             ****     ****
DB2D             ****     ****
DB2E             ****     ****
DB2F             NO       YES
DB2G             NO       NO
-----
SCA  STRUCTURE SIZE:    1024 KB, STATUS= AC,   SCA IN USE:    11 %
LOCK1 STRUCTURE SIZE:    1536 KB,   LOCK1 IN USE: <    1 %
NUMBER LOCK ENTRIES:    262144, LOCK ENTRIES IN USE:    33
NUMBER LIST ENTRIES:      7353, LIST ENTRIES IN USE:     0
*** END DISPLAY OF GROUP(DSNCAT )
DSN9022I -DB1A DSN7GCMDB 'DISPLAY GROUP ' NORMAL COMPLETION
```

-DISPLAY GROUPBUFFERPOOL (DB2)

The DB2 command DISPLAY GROUPBUFFERPOOL displays information about the status of DB2 group buffer pools. It can also display related statistics.

Abbreviation: -DIS GBPOOL

Environment

This command can be issued from an MVS console, a DSN session under TSO, a DB2I panel (DB2 COMMANDS), an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

Data sharing scope: Group

Authorization


To execute this command, the privilege set of the process must include one of the following:

- DISPLAY privilege
- SYSOPR, SYSCTRL, or SYSADM authority

DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.

-DISPLAY GROUPBUFFERPOOL (DB2)

Syntax



Option descriptions

(*) Displays the group buffer pool status for all group buffer pools.

gbpname

Names the group buffer pool for which status is to be displayed.

- 4-KB group buffer pools are named GBP0, GBP1, ..., GBP49.
- 8-KB group buffer pools are named GBP8K0, GBP8K1, ... , GBP8K9.
- 16-KB group buffer pools are named GBP16K0, GBP16K1, ... , GBP16K9.
- 32-KB group buffer pools are named GBP32K, GBP32K1, ... , GBP32K9.

(structure-name)

Names the backing coupling facility structure for the group buffer pool. The coupling facility structure name has the following format:

groupname_gbpname

where *groupname* is the DB2 data sharing group name and the underscore (`_`) separates *groupname* and *gbpname*.

TYPE

Indicates the type of group buffer pools (among those that are specified) for which information is displayed.

(*) All group buffer pools specified. This is the default.

(GCONN)

Group buffer pools that are currently connected to any member of the data sharing group. The connection can be “active” or “failed-persistent”.

(MCONN)

Group buffer pools that are currently connected to the member to which the command is directed.

(NOCACHE)

Group buffer pools that have the `GBPCACHE` attribute set to `NO`.

MDETAIL

Shows a detailed statistical report for the specified group buffer pools, reflecting

-DISPLAY GROUPBUFFERPOOL (DB2)

the member's activity for each group buffer pool. If the member to which the command is directed has never been actively connected to the group buffer pool, no detail report is shown.

(INTERVAL)

Shows incremental statistics. The values displayed are accumulated since the last MDETAIL(INTERVAL) report for this member, if there was one. This is the default.

- (*) Shows cumulative statistics. The values displayed are accumulated since this member first connected to the group buffer pool.

GDETAIL

Shows a detailed statistical report for the specified group buffer pools, reflecting the activity of the entire group for each group buffer pool. If the member to which the command is directed is not actively connected to the group buffer pool, no detail report is shown.

(INTERVAL)

Shows incremental statistics. The values displayed are accumulated since the last GDETAIL(INTERVAL) report, if there was one. This is the default.

- (*) Shows cumulative statistics. The values displayed are accumulated since the group buffer pool was most recently allocated or re-allocated.

CONNLIST

Specifies whether a connection list report is shown for the specified group buffer pools, listing the connection names of the subsystems that are currently connected to the group buffer pools and their connection status.

(NO)

Do not show the connection list report.

(YES)

Show the connection list report.

Output

The three report types are:

- A summary report
- A group detail report
- A member detail report

These reports are described here.

Summary report

You can display summary information about group buffer pools. The report indicates whether this DB2 is actively connected to the group buffer pools you requested information for. The summary report also shows the following information:

Group buffer pool characteristics:

- Threshold values
- Directory-to-data entry ratio (both pending and current)
- Checkpoint interval
- Recovery status (whether damage assessment is pending)

CFRM policy information about the group buffer pool:

- The allocation value specified in the CFRM policy and whether the group buffer pool is currently allocated in the coupling facility.

-DISPLAY GROUPBUFFERPOOL (DB2)

- The actual allocated size (which can be different from that specified in the CFRM policy) and volatility status. DB2 requests non-volatile storage; however, it can allocate in a volatile structure.
- The actual number of directory entries, data pages, and connection to the group buffer pool.

The summary report contains additional information as follows:

AUTOMATIC RECOVERY

Indicates whether automatic recovery is allowed for this group buffer pool.

DUPLEX

Indicates the current option for the group buffer pool that is specified in the active CFRM policy.

REBUILD STATUS

Indicates whether a rebuild is in progress for this group buffer pool. If so, the phase of the rebuild is indicated: QUIESCE, CONNECT, or CLEANUP. If the rebuild is in the process of stopping, the status indicates STOPPING.

DUPLEXING STATUS

Indicates the current state of the group buffer pool with respect to duplexing.

CFNAME, CFLEVEL

Indicates the name and level of the coupling facility in which the group buffer pool is allocated. If the group buffer pool is duplexed, this is the coupling facility name and level associated with the primary group buffer pool.

Note: The DB2 CFLEVEL displayed in the DISPLAY GROUPBUFFERPOOL Summary Report may be lower than the actual CFLEVEL (displayed by the MVS D CF Command), but will never be lower than what is required to perform your structure operations. For detailed CFLEVEL information, see "Understanding the CFLEVEL Returned by XCF and XES Services," in *OS/390 MVS Programming: Sysplex Services Guide*.

LAST GROUP BUFFER POOL CHECKPOINT

Indicates the date and time of the last group buffer pool checkpoint, the LRSN that was recorded at that checkpoint, and the member name of the group buffer pool structure owner.

Group detail report

The group detail report shows detailed statistical information reflecting the activity of the entire group for the specified group buffer pools. This statistical information is helpful in tuning the size and other characteristics of group buffer pools. See Chapter 6 of *DB2 Data Sharing: Planning and Administration* for more information about using this information. The report includes the same information as in the summary report with the addition of:

READS

Information about reads.

This is a detailed accounting of the number of reads against the group buffer pool, including the following:

- The number of reads where data was returned.

#

-DISPLAY GROUPBUFFERPOOL (DB2)

- The number of reads where data was not returned, broken down to include more detailed information about whether the page was cached in the coupling facility or not, and whether directory entries needed to be created to fulfill requests for data.

WRITES

Information about writes.

This includes the number of writes for clean pages and changed pages, and how many writes failed because there was not enough storage in the group buffer pool.

CHANGED PAGES SNAPSHOT VALUE

The number of changed pages currently in the group buffer pool (a snapshot value).

RECLAIMS

The number of reclaims of directory entries and data pages.

CASTOUTS

The number of castouts.

CROSS INVALIDATIONS

The number of cross-invalidations that occurred because of directory reclaims and because of writes.

DUPLEXING STATISTICS FOR GBP_n

This section of output indicates detailed duplexing statistics as follows:

CHANGED PAGES

Indicates the number of changed pages that are written to the secondary group buffer pool. If the group buffer pool has been duplexed for the entire reporting interval, this number approximates the CHANGED PAGES counter that is reported in message DSNB786I for the primary group buffer pool. The counts may not be exactly the same, due to timing periods for gathering the counter information for display or previous transaction failures that may have occurred.

FAILED DUE TO LACK OF STORAGE

Indicates the number of writes to the secondary group buffer pool that failed due to a lack of storage.

CHANGED PAGES SNAPSHOT VALUE

Indicates the number of changed pages that are currently cached in the secondary group buffer pool. This number approximates the CHANGED PAGES SNAPSHOT VALUE for the primary group buffer pool, but is probably not identical due to the asynchronous nature of gathering statistics for the two different coupling facility structures.

Member detail report

The member detail report includes the summary report and additional information about how a particular member's system is responding to the current environment. It categorizes reads and writes as synchronous or asynchronous. A large number of synchronous reads or writes can indicate that you need to tune your group buffer pools.

GBP CHECKPOINTS TRIGGERED

The number of checkpoints that occurred for this group buffer pool.

-DISPLAY GROUPBUFFERPOOL (DB2)

PARTICIPATION IN REBUILD

The number of times this member participated in a rebuild for this group buffer pool.

CASTOUTS

This section of output indicates detailed statistics for castout processing as follows:

PAGES CAST OUT

Indicates how many data pages were cast out of the group buffer pool by this member.

UNLOCK CASTOUT

The number of times that DB2 issued an unlock request to the coupling facility for castout I/Os that completed. As pages are cast out to disk, they are "locked for castout" in the coupling facility. The castout lock ensures that only one system is doing castout for a given page.

DB2 usually includes multiple pages in the write I/O request to disk for castout. Therefore, the UNLOCK CASTOUT counter should always be less than or equal to the value of the PAGES CASTOUT counter; it should be significantly less if multiple pages are written per I/O. For example, if there are 4 pages written per castout write I/O on average, then PAGES CASTOUT should be four times larger than UNLOCK CASTOUT.

READ CASTOUT CLASS

Number of requests made to the group buffer pool to determine which pages belonging to a given page set or partition are cached in the group buffer pool as changed pages and thus need to be cast out.

READ CASTOUT CLASS is issued by the page set or partition castout owner, and it is also issued by the group buffer pool structure owner when the GBPOOLT threshold has been reached.

READ CASTOUT STATISTICS

The number of requests that are issued by the group buffer pool structure owner when the GBPOOLT threshold is reached. This determines which castout classes have changed pages. Generally READ CASTOUT STATISTICS is issued only once or twice for each occurrence of the GBPOOLT threshold.

READ DIRECTORY INFO

The number of requests to read the directory entries of all changed pages in the group buffer pool. The group buffer pool structure owner issues these requests at group buffer pool checkpoints. The purpose of the request is to determine the oldest recovery LRSN to use in case the group buffer pool fails. This recovery LRSN is displayed in message DSNB798I.

The request to read directory information might be issued several times for each group buffer pool checkpoint. If you see an abnormally high number here, it might be that the requests are being cut short by the model-dependent timeout criteria of the coupling facility. To help alleviate this problem, upgrade those coupling facilities to CFLEVEL=2 or above.

OTHER INTERACTIONS

This section of the output lists details of other interactions that this DB2 has with this group buffer pool.

REGISTER PAGE

The number of times that DB2 registered interest to the group buffer pool for a single page. These are register-only requests, meaning that DB2 is not requesting that any data be returned for the page because it knows that there is no data cached in the group buffer pool for this page. The REGISTER PAGE request is made only to create a directory entry for the page for cross-invalidation when downgrading the P-lock on a page set or partition from S mode to IS mode, or from SIX mode to IX mode.

UNREGISTER PAGE

The number of times that DB2 reversed registered interest from the group buffer pool for a single page. This is generally done as DB2 uses pages from the local buffer pool that belong to partitions or pagesets that are group buffer pool dependent.

DELETE NAME

The number of times that DB2 issued a request to the group buffer pool to delete directory and data entries that were associated with a given page set or partition. DB2 issues this request:

- When it converts a page set or partition from group buffer pool dependent to non group buffer pool dependent.
- When the first DB2 member opens the object for GBPCACHE ALL objects.

READ STORAGE STATS

The number of times that DB2 requested statistics information from the group buffer pool. This number should usually be relatively low. It is issued once per group buffer pool checkpoint by the group buffer pool structure owner. It is also issued for DISPLAY GROUPBUFFERPOOL GDETAIL requests and to record IFCID 0254.

DUPLEXING STATISTICS FOR GBP0-SEC

This section of the output lists details of other interactions that this DB2 has with this group buffer pool.

CHANGED PAGES

Indicates the number of changed pages written to the secondary group buffer pool. This number approximates the sum of the synchronous writes of changed pages to the primary group buffer pool and the asynchronous writes of changed pages to the primary group buffer pool. The counts may not be exactly the same, due to timing periods for gathering the counter information for display or previous transaction failures that may have occurred.

FAILED DUE TO LACK OF STORAGE

Indicates the number of writes to the secondary group buffer pool that failed due to a lack of storage.

COMPLETION CHECKS SUSPENDED

Indicates the number of times DB2 checked for the completion of the write of a changed page to the secondary group buffer pool, but the write had not yet completed; DB2 suspends the execution unit until the write to the secondary group buffer pool completes.

-DISPLAY GROUPBUFFERPOOL (DB2)

DELETE NAME LIST

Indicates the number of DELETE NAME LIST requests to delete a set of pages from the secondary group buffer pool that have just been cast out from the primary group buffer pool.

READ CASTOUT STATISTICS

Indicates the number of READ CASTOUT STATISTICS requests to check for orphaned data entries in the secondary group buffer pool. The DB2 member that is the group buffer pool structure owner periodically issues these requests to determine whether garbage collection is necessary.

DELETE NAME

Indicates the number of DELETE NAME requests to delete orphaned data entries from the secondary group buffer pool. The DB2 member that is the group buffer pool structure owner issues these requests if it determines that garbage collection is necessary.

Examples

Example 1: This is an example of a summary report that can be produced by the following command:

```
-DISPLAY GROUPBUFFERPOOL(GBP29)
```

Message DSNB799I is displayed if the group buffer pool is duplexed and the secondary group buffer pool is currently allocated. If a secondary group buffer pool is not allocated, message DSNB799I is not included in the output.

-DISPLAY GROUPBUFFERPOOL (DB2)

```
DSNB750I - DISPLAY FOR GROUP BUFFER POOL GBP29 FOLLOWS
DSNB755I - DB2 GROUP BUFFER POOL STATUS
          CONNECTED = YES
          CURRENT DIRECTORY TO DATA RATIO = 5
          PENDING DIRECTORY TO DATA RATIO = 5
          CURRENT GBPCACHE ATTRIBUTE = YES
          PENDING GBPCACHE ATTRIBUTE = YES
DSNB756I - CLASS CASTOUT THRESHOLD = 10%
          GROUP BUFFER POOL CASTOUT THRESHOLD = 50%
          GROUP BUFFER POOL CHECKPOINT INTERVAL = 8 MINUTES
          RECOVERY STATUS = NORMAL
          AUTOMATIC RECOVERY = Y
DSNB757I - MVS CFPM POLICY STATUS FOR DSNCAT_GBP29 = NORMAL
          MAX SIZE INDICATED IN POLICY = 2048 KB
          DUPLEX INDICATOR IN POLICY = ENABLED
          CURRENT DUPLEXING MODE = DUPLEX
          ALLOCATED = YES
DSNB758I - ALLOCATED SIZE = 2048 KB
          VOLATILITY STATUS = VOLATILE
          REBUILD STATUS = DUPLEXED
          CFNAME = CACHE01
          CFLEVEL = 5
DSNB759I - NUMBER OF DIRECTORY ENTRIES = 1950
          NUMBER OF DATA PAGES = 389
          NUMBER OF CONNECTIONS = 2
DSNB798I - LAST GROUP BUFFER POOL CHECKPOINT
          17:08:41 OCT 16, 1997
          GBP CHECKPOINT RECOVERY LRSN = AF6BBAEF3307
          STRUCTURE OWNER = V61B
DSNB799I - SECONDARY GBP ATTRIBUTES
          ALLOCATED SIZE = 2048 KB
          VOLATILITY STATUS = VOLATILE
          CFNAME = LF01
          CFLEVEL = 5
          NUMBER OF DIRECTORY ENTRIES = 1950
          NUMBER OF DATA PAGES = 389
DSNB790I - DISPLAY FOR GROUP BUFFER POOL GBP29 IS COMPLETE
DSN9022I - DSNB1CMD '-DISPLAY GBPOOL' NORMAL COMPLETION
```

Example 2: Assume you want a summary report about group buffer pool twenty-nine, including all connections to that group buffer pool. Enter the following command:

```
-DISPLAY GROUPBUFFERPOOL(GBP29) CONNLIST(YES)
```

This command produces output similar to the following output:

-DISPLAY GROUPBUFFERPOOL (DB2)

```
DSNB750I - DISPLAY FOR GROUP BUFFER POOL GBP29 FOLLOWS
DSNB755I - DB2 GROUP BUFFER POOL STATUS
          CONNECTED = YES
          CURRENT DIRECTORY TO DATA RATIO = 5
          PENDING DIRECTORY TO DATA RATIO = 5
          CURRENT GBPCACHE ATTRIBUTE = YES
          PENDING GBPCACHE ATTRIBUTE = YES
DSNB756I - CLASS CASTOUT THRESHOLD = 10%
          GROUP BUFFER POOL CASTOUT THRESHOLD = 50%
          GROUP BUFFER POOL CHECKPOINT INTERVAL = 8 MINUTES
          RECOVERY STATUS = NORMAL
          AUTOMATIC RECOVERY = Y
DSNB757I - MVS CFPM POLICY STATUS FOR DSNCAT_GBP29 = NORMAL
          MAX SIZE INDICATED IN POLICY = 2048 KB
          DUPLEX INDICATOR IN POLICY = ENABLED
          CURRENT DUPLEXING MODE = SIMPLEX
          ALLOCATED = YES
DSNB758I - ALLOCATED SIZE = 2048 KB
          VOLATILITY STATUS = VOLATILE
          REBUILD STATUS = DUPLEXED
          CFNAME = CACHE01
          CFLEVEL = 5
DSNB759I - NUMBER OF DIRECTORY ENTRIES = 1950
          NUMBER OF DATA PAGES = 389
          NUMBER OF CONNECTIONS = 2
DSNB798I - LAST GROUP BUFFER POOL CHECKPOINT
          17:08:41 OCT 16, 1997
          GBP CHECKPOINT RECOVERY LRSN = AF6BBAEF3307
          STRUCTURE OWNER = V61B
DSNB799I - SECONDARY GBP ATTRIBUTES
          ALLOCATED SIZE = 2048 KB
          VOLATILITY STATUS = VOLATILE
          CFNAME = LF01
          CFLEVEL = 5
          NUMBER OF DIRECTORY ENTRIES = 1950
          NUMBER OF DATA PAGES = 389
DSNB766I - THE CONNLIST REPORT FOLLOWS
DSNB767I - CONNECTION NAME = DB2_V61B , CONNECTION STATUS = D
          CONNECTOR'S RELEASE = 6100
DSNB767I - CONNECTION NAME = DB2_V61A , CONNECTION STATUS = D
          CONNECTOR'S RELEASE = 6100
DSNB769I - THE CONNLIST REPORT IS COMPLETE
DSNB790I - DISPLAY FOR GROUP BUFFER POOL GBP29 IS COMPLETE
DSN9022I - DSNB1CMD '-DISPLAY GBPOOL' NORMAL COMPLETION
```

Example 3: This example shows a group detail report that is produced by the command:

```
-DISPLAY GROUPBUFFERPOOL(GBP29) GDETAIL(*)
```

Message DSNB762I is displayed in the output only if the secondary group buffer pool is allocated.

-DISPLAY GROUPBUFFERPOOL (DB2)

```

DSNB750I - DISPLAY FOR GROUP BUFFER POOL GBP29 FOLLOWS
DSNB755I - DB2 GROUP BUFFER POOL STATUS
            CONNECTED                                = YES
            CURRENT DIRECTORY TO DATA RATIO          = 5
            PENDING DIRECTORY TO DATA RATIO          = 5
            CURRENT GBPCACHE ATTRIBUTE                = YES
            PENDING GBPCACHE ATTRIBUTE                = YES
DSNB756I - CLASS CASTOUT THRESHOLD                    = 10%
            GROUP BUFFER POOL CASTOUT THRESHOLD        = 50%
            GROUP BUFFER POOL CHECKPOINT INTERVAL      = 8 MINUTES
            RECOVERY STATUS                            = NORMAL
            AUTOMATIC RECOVERY                        = Y
DSNB757I - MVS CFPM POLICY STATUS FOR DSNCAT_GBP29    = NORMAL
            MAX SIZE INDICATED IN POLICY               = 2048 KB
            DUPLEX INDICATOR IN POLICY                 = ENABLED
            CURRENT DUPLEXING MODE                    = DUPLEX
            ALLOCATED                                  = YES
DSNB758I - ALLOCATED SIZE                             = 2048 KB
            VOLATILITY STATUS                         = VOLATILE
            REBUILD STATUS                            = DUPLEXED
            CFNAME                                      = CACHE01
            CFLEVEL                                    = 5
DSNB759I - NUMBER OF DIRECTORY ENTRIES                = 1950
            NUMBER OF DATA PAGES                     = 389
            NUMBER OF CONNECTIONS                     = 2
DSNB798I - LAST GROUP BUFFER POOL CHECKPOINT
                                17:08:41 OCT 16, 1997
            GBP CHECKPOINT RECOVERY LRSN              = AF6BBAEF3307
            STRUCTURE OWNER                           = V61B
DSNB799I - SECONDARY GBP ATTRIBUTES
            ALLOCATED SIZE                             = 2048 KB
            VOLATILITY STATUS                         = VOLATILE
            CFNAME                                      = LF01
            CFLEVEL                                    = 5
            NUMBER OF DIRECTORY ENTRIES                = 1950
            NUMBER OF DATA PAGES                     = 389
DSNB783I - CUMULATIVE GROUP DETAIL STATISTICS SINCE 17:08:35 OCT 16,
1997
DSNB784I - GROUP DETAIL STATISTICS
            READS
            DATA RETURNED                             = 4
            DATA NOT RETURNED
            DIRECTORY ENTRY EXISTED                    = 0
            DIRECTORY ENTRY CREATED                    = 45
            DIRECTORY ENTRY NOT CREATED                = 0, 0
DSNB786I - WRITES
            CHANGED PAGES                             = 5
            CLEAN PAGES                                = 0
            FAILED DUE TO LACK OF STORAGE              = 0
            CHANGED PAGES SNAPSHOT VALUE               = 5
DSNB787I - RECLAIMS
            FOR DIRECTORY ENTRIES                      = 0
            FOR DATA ENTRIES                         = 0
            CASTOUTS                                   = 0

```

-DISPLAY GROUPBUFFERPOOL (DB2)

```
DSNB788I - CROSS INVALIDATIONS
           DUE TO DIRECTORY RECLAIMS           = 0
           DUE TO WRITES                       = 0
           EXPLICIT                           = 0
DSNB762I - DUPLEXING STATISTICS FOR GBP29-SEC
           WRITES
           CHANGED PAGES                      = 5
           FAILED DUE TO LACK OF STORAGE      = 0
           CHANGED PAGES SNAPSHOT VALUE      = 5
DSNB790I - DISPLAY FOR GROUP BUFFER POOL GBP29 IS COMPLETE
DSN9022I - DSNB1CMD '-DISPLAY GBPOOL' NORMAL COMPLETION
```

Example 4: This example shows the member detail section from the report that is produced by the command:

```
-DISPLAY GROUPBUFFERPOOL(GBP29) MDETAIL(*)
```

Messages DSNB764I and DSNB793I are displayed in the output only if the secondary group buffer pool is allocated.

-DISPLAY GROUPBUFFERPOOL (DB2)

```
DSNB750I - DISPLAY FOR GROUP BUFFER POOL GBP29 FOLLOWS
DSNB755I - DB2 GROUP BUFFER POOL STATUS
          CONNECTED                                = YES
          CURRENT DIRECTORY TO DATA RATIO         = 5
          PENDING DIRECTORY TO DATA RATIO         = 5
          CURRENT GBPCACHE ATTRIBUTE               = YES
          PENDING GBPCACHE ATTRIBUTE               = YES
DSNB756I - CLASS CASTOUT THRESHOLD                 = 10%
          GROUP BUFFER POOL CASTOUT THRESHOLD       = 50%
          GROUP BUFFER POOL CHECKPOINT INTERVAL     = 8 MINUTES
          RECOVERY STATUS                           = NORMAL
          AUTOMATIC RECOVERY                       = Y
DSNB757I - MVS CFPM POLICY STATUS FOR DSNCAT_GBP29 = NORMAL
          MAX SIZE INDICATED IN POLICY              = 2048 KB
          DUPLEX INDICATOR IN POLICY                = ENABLED
          CURRENT DUPLEXING MODE                    = DUPLEX
          ALLOCATED                                = YES
DSNB758I - ALLOCATED SIZE                          = 2048 KB
          VOLATILITY STATUS                        = VOLATILE
          REBUILD STATUS                           = DUPLEXED
          CFNAME                                    = CACHE01
          CFLEVEL                                   = 5
DSNB759I - NUMBER OF DIRECTORY ENTRIES             = 1950
          NUMBER OF DATA PAGES                    = 389
          NUMBER OF CONNECTIONS                    = 2
DSNB798I - LAST GROUP BUFFER POOL CHECKPOINT
                                     17:08:41 OCT 16, 1997
          GBP CHECKPOINT RECOVERY LRSN              = AF6BBAEF3307
          STRUCTURE OWNER                           = V61B
DSNB799I - SECONDARY GBP ATTRIBUTES
          ALLOCATED SIZE                          = 2048 KB
          VOLATILITY STATUS                        = VOLATILE
          CFNAME                                    = LF01
          CFLEVEL                                   = 5
          NUMBER OF DIRECTORY ENTRIES              = 1950
          NUMBER OF DATA PAGES                    = 389
DSNB772I - CUMULATIVE MEMBER DETAIL STATISTICS SINCE 17:08:41 OCT 16,
1997
DSNB773I - MEMBER DETAIL STATISTICS
          SYNCHRONOUS READS
            DUE TO BUFFER INVALIDATION
              DATA RETURNED                        = 0
              DATA NOT RETURNED                    = 0
DSNB774I - DUE TO DATA PAGE NOT IN BUFFER POOL
              DATA RETURNED                        = 0
              DATA NOT RETURNED                    = 0
DSNB775I - PREFETCH READS
              DATA NOT RETURNED                    = 0
              REGISTER PAGE LIST NOT AVAILABLE
                DATA RETURNED                      = 0
DSNB789I - REGISTER PAGE LIST                      = 0
              RETRIEVE CHANGED PAGES                = 0
              RETRIEVE CLEAN PAGES                  = 0
              FAILED READS DUE TO LACK OF STORAGE    = 0
DSNB776I - SYNCHRONOUS WRITES
              CHANGED PAGES                         = 5
              CLEAN PAGES                           = 0
DSNB777I - ASYNCHRONOUS WRITES
              CHANGED PAGES                         = 0
              CLEAN PAGES                           = 0
              FAILED WRITES DUE TO LACK OF STORAGE  = 0
```

-DISPLAY GROUPBUFFERPOOL (DB2)

```
DSNB778I - CASTOUT THRESHOLDS DETECTED
           FOR CLASSES                                = 0
           FOR GROUP BUFFER POOL                      = 0
           GBP CHECKPOINTS TRIGGERED                  = 0
           PARTICIPATION IN REBUILD                    = 1
DSNB796I - CASTOUTS
           PAGES CASTOUT                              = 0
           UNLOCK CASTOUT                            = 0
           READ CASTOUT CLASS                         = 0
           READ CASTOUT STATISTICS                    = 0
           READ DIRECTORY INFO                        = 0
DSNB779I - ENGINES NOT AVAILABLE
           FOR CASTOUT                                = 0
           FOR WRITING                                = 0
DSNB797I - OTHER INTERACTIONS
           REGISTER PAGE                              = 0
           UNREGISTER PAGE                           = 0
           DELETE NAME                                = 0
           READ STORAGE STATISTICS                    = 0
           EXPLICIT CROSS INVALIDATIONS               = 0
           ASYNCHRONOUS GBP REQUESTS                  = 0
DSNB764I - DUPLEXING STATISTICS FOR GBP29-SEC
           WRITES
           CHANGED PAGES                              = 5
           FAILED DUE TO LACK OF STORAGE              = 0
           ASYNCHRONOUS COMPLETION CHECKS             = 0
DSNB793I - DELETE NAME LIST                          = 0
           READ CASTOUT STATISTICS                    = 0
           DELETE NAME                                = 0
           OTHER ASYNCHRONOUS GBP REQUESTS            = 0
DSNB790I - DISPLAY FOR GROUP BUFFER POOL GBP29 IS COMPLETE
DSN9022I - DSNB1CMD '-DISPLAY GBPOOL' NORMAL COMPLETION
```


-DISPLAY LOCATION (DB2)

If you specify the **DETAIL** option, which is optional, each line could be followed by information regarding conversations owned by DB2 system threads that are communicating with the location.

The information returned by the **DISPLAY LOCATION** command reflects a dynamic status. By the time the information is displayed, it is possible that the status has changed.

Abbreviation: -DIS LOC

Environment

This command can be issued from an MVS console, a DSN session under TSO, a DB2I panel (DB2 COMMANDS), an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

Data sharing scope: Member


Authorization

To execute this command, the privilege set of the process must include one of the following:

- **DISPLAY** privilege
- **SYSOPR**, **SYSCTRL**, or **SYSADM** authority

DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.

Syntax



Option descriptions

(*) Displays information for all remote locations.

(location-name)

Lists one or more location names, separated by commas. If *location-name* is not specified, information for all remote locations is displayed.

Because DB2 does not receive a location name from requesters that are not DB2 for OS/390 and z/OS subsystems, you can enter the LUNAME or IP address of such a requester. Enclose the LUNAME by the less-than (<) and greater-than (>) symbols. Enter the IP address in the form *nnn.nnn.nnn.nnn*. For example, **-DISPLAY LOCATION(<LULA>)** displays information about a remote location (that is not DB2 for OS/390 and z/OS) with the LUNAME of

-DISPLAY LOCATION (DB2)

LULA. -DISPLAY LOCATION(124.63.51.17) displays information about clients at the remote TCP/IP host whose dotted decimal IP address is 124.63.51.17.

(partial-location)*

Selects all location names that begin with the string *partial-location* and can end with any string, including the empty string. For example, LOCATION(ABC*) selects all location names that begin with the string 'ABC'.

You can use an asterisk (*) when specifying a LUNAME in the same manner as described above for location names that are not DB2 for OS/390 and z/OS subsystems. For example, -DISPLAY LOCATION(<LULA*) selects all remote locations (that are not DB2 for OS/390 and z/OS) with a LUNAME that begins with the string 'LULA'.

<luname>

Requests information about the remote clients that are connected to DDF through the remote SNA LU that is specified.

(ipaddr)

Requests information about the clients that are connected to DDF through the remote TCP/IP host. *nnn.nnn.nnn.nnn* is the dotted decimal IP address.

DETAIL

Displays additional information about conversation activity for DB2 system threads, as shown in “Example 2” on page 145.

Output

The DISPLAY LOCATION command displays the following output:

LOCATION

The LOCATION of the remote system.

PRDID

The product identifier (PRDID) of the remote system. The PRDID is displayed in the form *nnnvvrrm*, where:

nnn	The database product
vv	The product version
rr	The product release
m	The product modification level

LINKNAME

The address (LU name or IP address) of the remote system.

REQUESTERS

The number of active threads from the local subsystem that are accessing the remote system.

SERVERS

The number of threads from the remote system that are accessing the local subsystem.

CONVERSATIONS

The total number of conversations or sockets related to the partner system.

Examples

Example 1: Display information about threads and conversations with specific remote locations, using the following command:

```
-DISPLAY LOCATION(SAN_JOSE,SAN_FRANCISCO)
```

```
DSNL200I - DISPLAY LOCATION REPORT FOLLOWS-
```

-DISPLAY LOCATION (DB2)

LOCATION	PRDID	LINKNAME	REQUESTERS	SERVERS	CONVS
SAN_JOSE	DSN05010	LUND1	1	0	1
SAN_FRANCISCO	DSN05010	LUND3	1	0	1

DISPLAY LOCATION REPORT COMPLETE

Example 2: Display information about threads and conversations with all remote locations. Additionally, display detail conversation information about DB2 system threads that communicate with other locations. This is an example of the output generated by the following command:

-DISPLAY LOCATION DETAIL

DSNL200I - DISPLAY LOCATION REPORT FOLLOWS-

LOCATION	PRDID	LINKNAME	REQUESTERS	SERVERS	CONVS
SAN_JOSE	DSN05010	LUND1	1	0	3
-SYSTASK	SESSID	A ST TIME			
-SYSCON-O	00D359691359EE80	S 9128009214880			
-SYSCON-I	00D359691359EE81	W R 9128009214881			
MENLO_PARK	DSN05010	LUND2	1	0	4
-SYSTASK	SESSID	A ST TIME			
-SYSCON-O	00D359691359EE82	S 9128009214882			
-SYSCON-I	00D359691359EE83	W R 9128009214883			
-RESYNC	00D359691359EE84	V R 9128009214884			
SAN_FRANCISCO	DSN05010	LUND3	1	0	6
-SYSTASK	SESSID	A ST TIME			
-SYSCON-O	0000000000000000	C 9128009214885			
-SYSCON-I	00D359691359EE86	W R 9128009214886			
-RESYNC	00D359691359EE87	W R 9128009214887			
-RESYNC	00D359691359EE88	W R 9128009214888			
-RESYNC	00D359691359EE89	W R 9128009214889			

DISPLAY LOCATION REPORT COMPLETE

Example 3: Display information for a DB2 that is connected to the following DRDA partners:

- A non-MVS server named DRDALOC via TCP/IP.
- Several TCP/IP clients from the same TCP/IP host as the DRDALOC server.
- A DB2 for MVS server named DB2SERV via SNA.

DISPLAY LOCATION(*)

DSNL200I - DISPLAY LOCATION REPORT FOLLOWS -

LOCATION	PRDID	LINKNAME	REQUESTERS	SERVERS	CONVS
DRDALOC	SQL03030	124.63.51.17	3	0	3
124.63.51.17	SQL03030	124.63.51.17	0	15	15
DB2SERV	DSN05010	LULA	1	0	1

DISPLAY LOCATION REPORT COMPLETE

Example 4: The following example assumes DB2 is connected to the following DRDA partners:

- DB2A is connected to this DB2, using TCP/IP for DRDA connections and SNA for DB2 private protocol connections.
- DB2SERV is connected to this DB2 using only SNA.

DISPLAY LOCATION(*)

DSNL200I - DISPLAY LOCATION REPORT FOLLOWS -

LOCATION	PRDID	LINKNAME	REQUESTERS	SERVERS	CONVS
DB2A	DSN05010	LUDB2A	3	4	9
DB2A	DSN05010	124.38.54.16	2	1	3
DB2SERV	DSN04010	LULA	1	1	3

DISPLAY LOCATION REPORT COMPLETE

-DISPLAY LOG (DB2)

The DB2 command DISPLAY LOG displays log information and the status of the offload task.

Abbreviation: DIS LOG

Environment

This command can be issued from an MVS console, a DSN session under TSO, a DB2I panel (DB2 COMMANDS), an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

Data sharing scope: Member

Authorization

To execute this command, the privilege set of the process must include one of the following authorities:

- DISPLAY privilege
- SYSOPR, SYSCTRL, or SYSADM authority

DB2 commands that are issued from an MVS console are not associated with any secondary authorization IDs.

Syntax

```
►►—DISPLAY LOG—◄◄
```

Usage notes

Information provided by the DISPLAY LOG command: You can use the DISPLAY LOG command to view the current LOGLOAD setting, including information about the current active log data sets and status of the offload task. You can obtain additional information about log data sets and checkpoint information by using the Print Log Map utility (DSNJU004). For more information about the Print Log Map utility, see Part 3 of *DB2 Utility Guide and Reference*.

Examples

Example 1: Display log information and status of the offload task.

```
DISPLAY LOG
```

This command produces output similar to the following output:

```
DSNJ370I - DSNJC00A LOG DISPLAY
CURRENT COPY1 LOG = DSNJC710.LOGCOPY1.DS03 IS 22% FULL
CURRENT COPY2 LOG = DSNJC710.LOGCOPY2.DS03 IS 22% FULL
H/W RBA = 0000039A9F24, LOGLOAD = 150000
FULL LOGS TO OFFLOAD = 2 OF 6, OFFLOAD TASK IS (BUSY,ALLC)
DSNJ371I - DB2 RESTARTED 14:06:23 MAY 22, 1998
RESTART RBA 0000039A8000
DSNJ9002I - DSNJC001 'DIS LOG' NORMAL COMPLETION
```

This example shows the following information:

DISPLAY LOG (DB2)

- The active log data sets are 22% full. If you are running dual logs and the percentages are different, the log data sets are of different sizes. DB2 switches both active logs when one reaches the end of the file. This can result in unused active log space if one log data set is larger than the other.
- The current LOGLOAD setting is 150000 log records between system checkpoints. You can modify this value using the SET LOG command.
- Two of the six active log data sets require archiving. The status of the offload task includes the indicator that it is busy, allocating an archive log data set. This might be an indication of an outstanding tape mount on the system console. If the status remains busy and no longer seems to be functioning, you can terminate the task, and then restart it using the ARCHIVE LOG CANCEL OFFLOAD command.
- DB2 was started at 14:06:23 on MAY 22, 1998, and began logging at RBA 0000039A8000.

-DISPLAY PROCEDURE (DB2)

-DISPLAY PROCEDURE (DB2)

The DB2 command DISPLAY PROCEDURE displays statistics about stored procedures accessed by DB2 applications. This command displays one output line for each stored procedure that has been accessed by a DB2 application. You can qualify stored procedure names with a schema name.

The information returned by the DISPLAY PROCEDURE command reflects a dynamic status. By the time the information is displayed, it is possible that the status could have changed.

Abbreviation: -DIS PROC

Environment

This command can be issued from an MVS console, a DSN session under TSO, a DB2I panel (DB2 COMMANDS), an IMS or a CICS terminal, or a program using the instrumentation facility interface (IFI).

Data sharing scope: Group or local, depending on the value of the SCOPE option.

Authorization

To execute this command, the privilege set of the process must include one of the following:


- DISPLAY privilege
- SYSOPR, SYSCTRL, or SYSADM authority
- Ownership of the stored procedure

If you specify -DISPLAY PROCEDURE *.* or schema.partial-name*, the privilege set of the process must include one of the following authorities:

- SYSOPR authority
- SYSCTRL authority
- SYSADM authority

DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.

Syntax



Option descriptions

(*.*)

Displays information for all stored procedures in all schemas that have been accessed by DB2 applications since DB2 was started.

-DISPLAY PROCEDURE (DB2)

(schema.procedure-name)

Displays the specified stored procedure in the specified schema.

(schema.partial-name)*

Displays a set of stored procedures in the specified schema that have been accessed by DB2 applications since DB2 was started. The names of all procedures in the set begin with *partial-name* and can end with any string, including the empty string. For example, PAYROLL.ABC* displays information for all stored procedure names beginning with ABC in the PAYROLL schema.

(procedure-name)

Displays one or more specific stored procedure names in the SYSPROC schema. If no procedures are named, DB2 displays information for all stored procedures that have been accessed by DB2 applications.

(partial-name)*

Displays information for a set of stored procedures in the SYSPROC schema that have been accessed by DB2 applications since DB2 was started. The names of all procedures in the set begin with *partial-name* and can end with any string, including the empty string. For example, ABC* displays information for all stored procedures in the SYSPROC schema with names that begin with ABC.

SCOPE

Specifies the scope of the command.

(LOCAL)

Specifies to display information about procedures on the local member only.

(GROUP)

Specifies to display information about procedures on all members of the data sharing group.

Output

Sample output: The DISPLAY PROCEDURE command generates the following output:

DSNX940I - DSNX9DIS DISPLAY PROCEDURE REPORT FOLLOWS -

PROCEDURE	STATUS	ACTIVE	QUEUED	MAXQUE	TIMEOUT	WLM_ENV
APPL1	STARTED	1	0	0	0	
APPL2	STARTED	1	0	0	0	
APPL2	STARTED	0	1	2	0	
APPL5	STOPREJ	0	0	0	0	
APPL6	STOPABN	0	0	0	0	
PROC1	STOPQUE	0	0	0	0	

DSNX9DIS DISPLAY PROCEDURE REPORT COMPLETE

Description of output: Each output line displays:

PROCEDURE

The name of the stored procedure.

STATUS

The status of the stored procedure of the stored procedure. The possible values are:

STARTED

Requests for the procedure can be processed.

STOPQUE

Requests are queued.

-DISPLAY PROCEDURE (DB2)

STOPREJ

Requests are rejected.

STOPABN

Requests are rejected because of abnormal termination.

ACTIVE

The number of threads that are currently running the load module.

QUEUED

The number of threads that are waiting for the procedure to be scheduled.

MAXQUE

The maximum number of threads that have waited concurrently for the procedure to be scheduled since DB2 was started. DB2 resets this value to 0 each time you execute the START PROCEDURE command.

TIMEOUT

The number of times an SQL CALL statement timed out while waiting for a request for the procedure to be scheduled. DB2 resets this value to 0 each time you execute the START PROCEDURE command.

Message DSNX943I lists a range of procedures that are stopped because a STOP PROCEDURE command included a partial name with a pattern-matching character (*) such as:

```
-STOP PROCEDURE(ABC*)
```

Message DSNX950I is returned when DISPLAY PROCEDURE is issued for a procedure name that has not been accessed by a DB2 application.

Examples

Example 1: Display information about all stored procedures that have been accessed by DB2 applications.

```
-DISPLAY PROCEDURE
```

This command produces output similar to the following output:

```
DSNX940I DSNX9DIS - DISPLAY PROCEDURE REPORT FOLLOWS-
PROCEDURE      STATUS    ACTIVE    QUEUED    MAXQUE    TIMEOUT
USERPRC1       STARTED      0         0         1         0
USERPRC2       STOPQUE      0         5         5         3
USERPRC3       STARTED      2         0         6         0
USERPRC4       STOPREJ      0         0         1         0
DSNX9DIS DISPLAY PROCEDURE REPORT COMPLETE
DSN9022I - DSNX9COM '-DISPLAY PROC' NORMAL COMPLETION
```

Example 2: Display information about specific stored procedures in the SYSPROC schema.

```
-DISPLAY PROCEDURE(SYSPROC.USERPRC2,USERPRC4)
```

This command produces output similar to the following output:

```
DSNX940I DSNX9DIS - DISPLAY PROCEDURE REPORT FOLLOWS-

----- SCHEMA=SYSPROC
PROCEDURE      STATUS    ACTIVE    QUEUED    MAXQUE    TIMEOUT    WLM_ENV
USERPRC2       STOPQUE      0         5         5         3    SANDBOX
USERPRC4       STOPREJ      0         0         1         0    SANDBOX
DSNX9DIS DISPLAY PROCEDURE REPORT COMPLETE
DSN9022I - DSNX9COM '-DISPLAY PROC' NORMAL COMPLETION
```


-DISPLAY PROCEDURE (DB2)

Example 3: Display information about stored procedures in the PAYROLL and HRPROD schemas.

```
-DISPLAY PROCEDURE(PAYROLL.*,HRPROD.*)
```

This command produces output similar to the following output:

```
DSNX940I DSNX9DIS - DISPLAY PROCEDURE REPORT FOLLOWS-
```

```
----- SCHEMA=PAYROLL
PROCEDURE      STATUS    ACTIVE    QUEUED    MAXQUE    TIMEOUT    WLM_ENV
PAYPRC1        STARTED      0         0         1         0    PAYROLL
PAYPRC2        STOPQUE      0         5         5         3    PAYROLL
PAYPRC3        STARTED      2         0         6         0    PAYROLL
USERPRC4       STOPREJ      0         0         1         0    SANDBOX

----- SCHEMA=HRPROD
PROCEDURE      STATUS    ACTIVE    QUEUED    MAXQUE    TIMEOUT    WLM_ENV
HRPRC1        STARTED      0         0         1         0    HRPROCS
HRPRC2        STOPREJ      0         0         1         0    HRPROCS
DSNX9DIS DISPLAY PROCEDURE REPORT COMPLETE
DSN9022I - DSNX9COM '-DISPLAY PROC' NORMAL COMPLETION
```

Example 4: Display information about all stored procedures in the SYSPROC schema that have been accessed by DB2 applications. Assume the -STOP PROCEDURE(SYSPROC.*) ACTION(Queue) command is in effect at the time this command is issued.

```
-DISPLAY PROCEDURE(SYSPROC.*)
```

This command produces output similar to the following output:

```
DSNX940I DSNX9DIS - DISPLAY PROCEDURE REPORT FOLLOWS-
```

```
----- SCHEMA=SYSPROC
PROCEDURE      STATUS    ACTIVE    QUEUED    MAXQUE    TIMEOUT    WLM_ENV
USERPRC2       STOPQUE      0         5         5         3    SANDBOX
USERPRC4       STOPQUE      0         0         1         0    SANDBOX
PROCEDURES USERFNC2      - USERFNC299999999999 STOP QUEUE
PROCEDURES USERFNC4      - USERFNC499999999999 STOP QUEUE
DSNX9DIS DISPLAY PROCEDURE REPORT COMPLETE
DSN9022I - DSNX9COM '-DISPLAY PROC' NORMAL COMPLETION
```

-DISPLAY RLIMIT (DB2)

-DISPLAY RLIMIT (DB2)

The DB2 command DISPLAY RLIMIT displays the current status of the resource limit facility (governor). If the facility has already been started, -DISPLAY RLIMIT also displays the ID of the resource limit specification table being used.

Abbreviation: -DIS RLIM

Environment

This command can be issued from an MVS console, a DSN session, a DB2I panel (DB2 COMMANDS), an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

Data sharing scope: Member

Authorization

To execute this command, the privilege set of the process must include the following:

- SYSOPR authority
- SYSCTRL authority
- SYSADM authority

DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.

Syntax

```
►►—DISPLAY RLIMIT—◄◄
```

Example

Display the current status of the resource limit facility.

```
-DISPLAY RLIMIT
```

If the resource limit facility (RLF) is inactive, the following output is generated:

```
DSNT701I - RESOURCE LIMIT FACILITY IS INACTIVE
DSN9022I - DSNTCDIS 'DISPLAY RLIMIT' NORMAL COMPLETION
```

If the RLF is active, the value of field RESOURCE AUTHID on panel DSNTIPP is SYSADM, and the resource limit specification table with RLST NAME SUFFIX = 03 was started, the following output is generated:

```
DSNT700I = SYSADM.DSNRLST03 IS THE ACTIVE RESOURCE LIMIT
SPECIFICATION TABLE
DSN9022I = DSNTCDIS 'DISPLAY RLIMIT' NORMAL COMPLETION
```

-DISPLAY THREAD (DB2)

The DB2 command DISPLAY THREAD displays current status information about DB2 threads. A DB2 thread is either an allied thread, a database access thread, or a parallel task thread. Threads can be active, inactive, indoubt, or postponed.

Distributed threads are those threads that have a connection with a remote location (active or inactive) or that had a connection with a remote location (indoubt). An allied thread and a parallel task thread can be distributed or nondistributed; a database access thread is always distributed.

The -DISPLAY THREAD command allows you to select the type of information you want to display by using one or more of the following criteria:

- Active threads, inactive threads, indoubt threads, postponed threads, or the set of active, indoubt, and postponed threads (see discussion under the TYPE option for more information)
- The allied threads associated with the address spaces whose connection names are specified
- Allied threads
- Distributed threads
- Distributed threads associated with a specific remote location
- Detailed information about connections with remote locations
- A specific logical unit of work ID (LUWID)

The information returned by the DISPLAY THREAD command reflects a dynamic status. When the information is displayed, it is possible that the status has changed. Moreover, the information is consistent only within one address space and is *not necessarily* consistent across all address spaces displayed.

Abbreviation: -DIS THD

Environment

This command can be issued from an MVS console, a DSN session under TSO, a DB2I panel (DB2 COMMANDS), an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

#

Data sharing scope: Group or member, depending on the value of the SCOPE option.

Authorization


To execute this command, the privilege set of the process must include one of the following:

- DISPLAY privilege
- SYSOPR, SYSCTRL, or SYSADM authority

DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.

-DISPLAY THREAD (DB2)

Syntax



Option descriptions

Only under certain conditions, as described below, are any of the following options required.

If neither (*connection-name*) nor (*) is specified, then the following rules apply:

- If the command is issued from a DSN session under TSO, a DB2I panel (DB2 COMMANDS), or an IMS or CICS terminal, then the connection name is inherited from the associated address space.
- If the command is not issued from one of the above environments, then the following rules apply:
 - If neither `LOCATION` nor `LUWID` is specified, then processing terminates with a DSNV413I message.
 - If `LOCATION` or `LUWID` is specified, then only distributed threads of the type selected by the `TYPE` option are displayed.
 - When *location-name* is explicitly specified, then only distributed threads of the type selected by the `TYPE` option that either have (active or inactive threads) or had (indoubt threads) a connection with the specified location are displayed.

(*connection-name*, ...)

Lists one or more connection names (of 1 to 8 characters each). Allied threads are selected only from the address spaces associated with those connection names. The `LOCATION` option can restrict what is displayed:

- If `LOCATION(*)` is specified, then only distributed threads of the type specified in the `TYPE` option are displayed.

-DISPLAY THREAD (DB2)

- When *location-name* is explicitly specified, then only distributed threads of the specified type that either have (active or inactive threads) or had (indoubt threads) a connection with the specified location are displayed.

(*partial-connection**, ...)

Selects the connections that begin with the string *partial-connection* and can end with any string, including the empty string. For example, DISPLAY THREAD(CICS*,IMS*) selects all connection names that begin with the string 'CICS' or 'IMS'. The LOCATION option can restrict the display exactly the same way as described above for *location-name*.

(*)

Displays all threads in all address spaces attached to DB2 and all database access threads of the types specified in the TYPE option. The LOCATION option can restrict what is displayed:

- If LOCATION(*) is specified, then only distributed threads are displayed.
- When *location-name* is explicitly specified, then only distributed threads that either have (active or inactive threads) or had (indoubt threads) a connection with the specified location are displayed.

The **default** is to display only the connections associated with the transaction manager from which the command was entered.

SCOPE

Specifies the scope of the command.

(LOCAL)

Displays only threads on the current member.

(GROUP)

Displays all threads on the data sharing group.

TYPE

Tells what type of thread to display.

Abbreviation: T

(ACTIVE)

Displays only active threads. An active allied thread is connected to DB2 via TSO, BATCH, IMS, CICS or CAF. An active database access thread is connected via VTAM to another system and is performing work on behalf of that system. If, during command processing, an active thread becomes indoubt, it can appear twice—once as active and once as indoubt.

Abbreviation: A

The information produced by ACTIVE can be useful for debugging purposes, especially messages DSNV403I and DSNV404I; the contents of those messages are described in Part 2 of *DB2 Messages and Codes*.

(INDOUBT)

Displays only indoubt threads.

An indoubt thread is a participant in a two-phase commit protocol that has completed the first phase of commit, and has then lost communication with the commit coordinator, and does not know whether to commit or roll back the updates that have been made.

The indoubt thread information displayed includes threads for which DB2 has a coordinator role, a participant role, or both coordinator and participant roles.

#

-DISPLAY THREAD (DB2)

The commit coordinator for an allied thread is either a transaction manager (for example, IMS or CICS) or OS/390 RRS for threads that use RRSF. The commit coordinator for a database access thread is a requester at a remote system.

Indoubt threads hold locks on all resources that were updated.

Abbreviation: I

(*) Displays active, indoubt, and postponed threads.

(INACTIVE)

Displays only inactive threads. An inactive thread is a database access thread that is connected via VTAM to another system and is idle, waiting for a new unit of work to begin from that system.

Abbreviation: INA

Use qualifiers such as complete location names or LUWIDs with this option. When there are large numbers of inactive database access threads, unqualified display requests could temporarily change the DB2 working set, which can temporarily affect the performance of active threads.

(POSTPONED)

Displays information about units of work whose back-out processing has been postponed.

Abbreviation: P

After you have identified postponed threads, use the RECOVER POSTPONED command on page 255 to complete backout processing for the postponed units of work.

LOCATION(*location-name*, ...)

Limits the display to distributed threads as described below.

Abbreviation: LOC

location-name

Displays only distributed threads of the specified type that either have (active or inactive threads) or had (indoubt threads) a remote connection with the specified *location-name*.

DB2 does not receive a location name from requesters that are not DB2 for OS/390 and z/OS subsystems. To display information about a requester that is not a DB2 for OS/390 and z/OS subsystem, enter its LUNAME or IP address. Enclose the LUNAME by the less-than (<) and greater-than (>) symbols. Enter the IP address in the form *nnn.nnn.nnn.nnn*. For example, the following command displays information about a remote location (that is not DB2 for OS/390 and z/OS) with the LUNAME of LULA:

```
-DISPLAY THREAD (*) LOCATION (<LULA>)
```

The following command displays information about a remote location (that is not DB2 for OS/390 and z/OS) with an IP address of 123.34.101.98:

```
-DISPLAY THREAD (*) LOCATION (123.34.101.98)
```

DB2 uses the <LUNAME> notation or IP address in messages displaying information about requesters other than DB2.

*partial-location**

Selects all location names that begin with the string *partial-location* and can

-DISPLAY THREAD (DB2)

end with any string, including the empty string. For example, LOCATION(SAN*) selects all location names that begin with the string 'SAN'.

You can use an asterisk (*) when specifying a LUNAME in the same manner as described above for other location names that are not DB2 for OS/390 and z/OS subsystems. For example, LOCATION(<LULA*) selects all remote locations (that are not DB2 for OS/390 and z/OS) with an LUNAME that begins with the string 'LULA'.

You cannot use an asterisk when you specify an IP address.

(*) Display all distributed threads of the specified type.

LUWID(*luwid*, ...)

Displays information about the distributed threads that have the specified LUWID. It is possible for more than one thread to have the same LUWID.

luwid

Consists of a fully qualified LU network name followed by a period and an LUW instance number.

The LU network name consists of a 1 to 8 character network ID, a period, and a 1 to 8 character network LU name. The LUW instance number consists of 12 hex characters that uniquely identify the unit of work.

*partial-luwid**

Selects all LUWIDs that begin with the string *partial-luwid* and can end with any string, including the empty string. For example, LUWID(NET1.*) selects all LUWIDs with a network name of 'NET1'.

token

Identifies a specific thread in an alternate way. DB2 assigns a token to each distributed thread it creates. A token is a one- to six-digit decimal number that appears after the equal sign in all DB2 messages that display a LUWID.

If there are no periods nor a '*' in the LUWID specification, DB2 assumes that you are supplying a token. The token that DB2 assigns to a specific LUWID is unique for that DB2 subsystem, but not necessarily unique across subsystems.

DETAIL

Displays additional information about conversation or socket activity when distributed information is displayed for active or inactive threads. DETAIL has no effect on the display of indoubt threads.

RRSURID(*rrs-urid*)

Specifies that only threads that match the specified RRSURID selection criteria are to be displayed.

- If RRSURID(*rrs-urid*) is specified, then any thread involved in the RRS URID which has the value *rrs-urid*, and that meets any other selection criteria that was specified, will be displayed.
- If RRSURID(*) is specified, then any thread involved in any RRS URID, and that meets any other selection criteria that was specified, will be displayed.

Usage notes

Formatted report for distributed threads: The series of messages DSNV444I through DSNV446I augment the formatted report for -DISPLAY THREAD

-DISPLAY THREAD (DB2)

TYPE(ACTIVE or INACTIVE) for distributed threads. See these messages in Part 2 of *DB2 Messages and Codes* for an explanation of the formatted report.

Threads using private protocol and DRDA access: It is possible for a database access thread that is connected to a requester to also be connected to another database server location using DB2 private protocol access or DRDA access. In this case, DB2 issues message DSNV445I for the requester, and message DSNV444I and zero or more DSNV446I messages for the remote server connections. In this case, the database access thread acts as an intermediate database server.

Participant threads waiting for the commit or abort decision: A DSNV465I message is issued for an active participant thread that has completed phase 1 of commit processing and has been waiting for the commit or abort decision from the coordinator for more than 60 seconds.

DISPLAY THREAD output limit: If a DISPLAY THREAD command is issued from the MVS console, the maximum number of lines of output for a single invocation of the command is 255 lines (at which time a DSNV421I or DSNV422I message is printed). If you do not receive the required information in the first 255 lines of output, issue the command again, specifying the TYPE option and a specific connection name, location, luwid, or a combination of these, as appropriate, to reduce the output.

Showing parallel tasks: The DB2 DISPLAY THREAD command shows parallel tasks by using a status type of PT. The parallel tasks are displayed immediately after the originating task. If the thread has a status of PT, the connection name contains blanks if the thread of the originating task is running on the same DB2. This shows that these parallel tasks are related to the originating task. If the parallel task is running on a DB2 that is different from the DB2 that runs the originating task, then the connection name is shown and the entry is followed by message DSNV443I.

Output

Table 16 shows sample -DISPLAY THREAD commands and the types of output they generate. The DETAIL keyword is not included because it affects only the amount of information displayed about a distributed thread.

If RRSURID(*) is specified, then only threads involved in any RRS URID will be displayed. If RRSURID(*rrs-urid*) is specified, then only threads involved in that specific RRS URID will be displayed.

Table 16. Sample DISPLAY THREAD commands. The following output is generated when commands are issued from different environments with different TYPE specifications. (Specifying TYPE() displays the equivalent output of both TYPE(ACTIVE) and TYPE(INDOUBT) in one report.)*

	ACTIVE	INDOUBT	INACTIVE
Command issued from a DSN session under TSO, DB2I, IMS or CICS, where the connection name is inherited			
-DIS THD	1	1	2
-DIS THD LOC(*)	3	3	2
-DIS THD LOC(<i>location-name</i>)	4	4	2
Command issued from MVS console			
-DIS THD	6	6	6

-DISPLAY THREAD (DB2)

Table 16. Sample DISPLAY THREAD commands (continued). The following output is generated when commands are issued from different environments with different TYPE specifications. (Specifying TYPE(*) displays the equivalent output of both TYPE(ACTIVE) and TYPE(INDOUBT) in one report.)

	ACTIVE	INDOUBT	INACTIVE
-DIS THD LOC(*)	9	9	8
-DIS THD LOC(<i>location-name</i>)	10	10	11
Command issued from any source			
-DIS THD(<i>connection-name</i>)	1,12	1,12,15	12
-DIS THD(<i>connection-name</i>) LOC(*)	3,12	3,12,15	12
-DIS THD(<i>connection-name</i>) LOC(<i>location-name</i>)	4,13	4,13,15	13
-DIS THD(*)	7	7,15	8
-DIS THD(*) LOC(*)	9	9,15	8
-DIS THD(*) LOC(<i>location-name</i>)	10	10,15	11
-DIS THD(*) LUWID(<i>luwid</i> or <i>token</i>)	5	5,15	5
-DIS THD(<i>connection-name</i>) LUWID(<i>luwid</i> or <i>token</i>)	14	14,15	14
-DIS THD LUWID(<i>luwid</i> or <i>token</i>)	5	5,15	5

Description of display generated:

1. Allied threads of the specified TYPE with the connection name.
2. No threads (inactive threads are database access threads and have no inherited connection name).
3. Distributed allied threads of the specified TYPE with the connection name.
4. Distributed allied threads of the specified TYPE with the connection name and a distributed connection = *location-name*.
5. The threads of the specified TYPE that have LUWID = *luwid* or *token*.
6. Message DSNV413I is displayed to indicate an error.
7. All threads (both allied and database access) of the specified TYPE.
8. All inactive database access threads.
9. All distributed threads (both allied and database access) of the specified TYPE.
10. All distributed threads (both allied and database access threads) of the specified TYPE with a distributed connection = *location-name*.
11. All inactive database access threads with a distributed connection = *location-name*.
12. Database access threads of the specified TYPE with the connection name.
13. Database access threads of the specified TYPE with the connection name and a distributed connection = *location-name*.
14. A thread of the specified TYPE with the connection name and LUWID = *luwid* or *token*.
15. Messages DSNV407 and DSNV408 also display coordinator's TCP/IP resync port number; message DSNV446 also displays the participant's TCP/IP resync port number.

If the DETAIL option is specified, then the following additional information is displayed:

LOCATION

The location name of the remote system.

SESSID

For a VTAM connection, the VTAM defined session instance identifier of the session on which the conversation is executing.

For a TCP/IP connection, the local and remote TCP/IP port numbers, in the form *local:remote*. *local* is the port number for the local DB2 subsystem. *remote* is the port number for the remote partner.

-DISPLAY THREAD (DB2)

- A** If VTAM or TCP/IP has control of the conversation (if DB2 transferred control of the thread to VTAM or TCP/IP for that conversation), there is a V in the A (Active) column. A W indicates that DB2 has suspended processing on this conversation until VTAM notifies DB2 that the VTAM event is complete. The column is otherwise blank.

STATUS

This 2 byte column indicates the status of the conversation or socket. The possible values for STATUS are:

Value	Status
Sx	Send
Rx	Receive
Ax	Allocation
Dx	Deallocation
Cx	Change number of sessions (CNOS) processing
Xx	Exchange Log name processing
blank	Not in one of the above mentioned states

x can be one of the following values:

- 1 = private protocol conversation with single-phase commit
- 2 = DRDA conversation with single-phase commit
- 3 = private protocol conversation with two-phase commit
- 4 = DRDA conversation with two-phase commit.

Examples

Example 1: The output of the command DISPLAY THREAD shows a token for every thread, distributed or not. This example shows the token for an allied thread that is not distributed. The token is 123. You can use the thread's token as the parameter in the command CANCEL THREAD.

```
-DIS THD(*) DETAIL
```

This command produces output similar to the following output:

```
DSNV401I - DISPLAY THREAD REPORT FOLLOWS -
DSNV402I - ACTIVE THREADS -
NAME      ST A   REQ ID          AUTHID   PLAN      ASID  TOKEN
BATCH    T  *    5 BKH2C          SYSADM   BKH2      000D   123
DISPLAY ACTIVE REPORT COMPLETE
DSN9022I - DSNVDT '-DIS THD' NORMAL COMPLETION
```

Example 2: This example shows information about conversation activity when distribution information is displayed for active threads. DB2 returns the following message, indicating that the local site application is waiting for a conversation to be allocated in DB2, and a DB2 server that is accessed by a DRDA client using TCP/IP.

```
-DIS THD(*) LOCATION(*) DETAIL
```

This command produces output similar to the following output:

```
-DIS THD(*) LOC(*) DET
DSNV401I - DISPLAY THREAD REPORT FOLLOWS -
DSNV402I - ACTIVE THREADS -
NAME      ST A   REQ ID          AUTHID   PLAN      ASID  TOKEN
TSO       TR  *    3 SYSADM          SYSADM   DSNESPRR 002E   2
V436-PGM=DSNESPRR.DSNESM68, SEC=1, STMT=116
V444-DB2NET.LUND0.A238216C2FAE=2 ACCESSING DATA AT
V446-USIBMSTODB22:LUND1
V447--LOCATION          SESSID          A ST      TIME
```

-DISPLAY THREAD (DB2)

```
V448--USIBMSTODB22      0000000000000000 V A1 9015816504776
TSO      RA *    11 SYSADM      SYSADM  DSNESPRR 001A      15
V445--STLDRIV.SSLU.A23555366A29=15 ACCESSING DATA FOR 123.34.101.98
V447--LOCATION      SESSID      A ST    TIME
V448--123.34.101.98  446:3171      S2    9015611253108
DISPLAY ACTIVE REPORT COMPLETE
DSN9022I - DSNVDT '-DIS THD' NORMAL COMPLETION
```

Example 3: In this example, a system at STL has a TSO application and an IMS application. The system at STL fails after DB2 commits the TSO application, but before the commit decision has been communicated to the participant subsystems at SJ and LA. The failure occurs before IMS has communicated the commit or rollback decision to STL's DB2. The DISPLAY THREAD commands that are issued after the STL DB2 restarts but before reconnect with IMS. DISPLAY THREAD commands that are issued at each location show output similar to the following output:

At STL:

```
-DIS THD(*) TYPE(INDOUBT)
```

This command produces output similar to the following output:

```
DSNV401I - DISPLAY THREAD REPORT FOLLOWS -
DSNV406I - INDOUBT THREADS -
COORDINATOR      STATUS      RESET URID      AUTHID
STLIMS01          INDOUBT      0F201050A010 SM09H
V467-HAS LUWID IBM.STLDB21.15A86A876789.0010=1
V449-HAS NID=A5 AND ID=STLIMS01
V450-HAS PARTICIPANT INDOUBT AT
V446--IBMSJ0DB20001:STLDB22
IBMSTLDB20001      COMMITTED      0F20105B0000 J078S
V467-HAS LUWID IBM.STLDB21.16B57B954427.0003=2
V450-HAS PARTICIPANT INDOUBT AT
V446--IBMSJ0DB20001:STLDB22 IBMLA0DB20001:STLDB23
DISPLAY INDOUBT REPORT COMPLETE -
DSN9022I - DSNVDT '-DIS THD' NORMAL COMPLETION
```

At San Jose:

```
-DIS THD(*) TYPE(INDOUBT)
```

This command produces output similar to the following output:

```
DSNV401I - DISPLAY THREAD REPORT FOLLOWS -
DSNV406I - INDOUBT THREADS -
COORDINATOR      STATUS      RESET URID      AUTHID
IBMSTLDB20001:STLDB21 INDOUBT      03201050A010 HEU4443
V467-HAS LUWID IBM.STLDB21.15A86A876789.0010=8
V466-THREAD HAS BEEN INDOUBT FOR 00:05:20
IBMSTLDB20001:STDB21 INDOUBT      03201050B000 PP433MM
V467-HAS LUWID IBM.STLDB21.16B57B954427.0003=6
DISPLAY INDOUBT REPORT COMPLETE
DSN9022I - DSNVDT '-DIS THD' NORMAL COMPLETION
```

At Los Angeles (both ACTIVE and INDOUBT threads are displayed):

```
-DIS THD(*) TYPE(*) DETAIL
```

This command produces output similar to the following output:

```
DSNV401I - DISPLAY THREAD REPORT FOLLOWS -
DSNV402I - ACTIVE THREADS -
NAME      ST A   REQ ID      AUTHID  PLAN      ASID TOKEN
```

-DISPLAY THREAD (DB2)

```
SERVER RA *      0 RUW2STAT      JONES      DISTSERV 0005      4
V465-THREAD HAS BEEN PREPARED FOR 00:05:20
V445-IBM.STLDB21.15A86A876789=4 ACCESSING DATA FOR
      IBMSJ0DB20001:STLDB21
V447--LOCATION      SESSID      A ST TIME
V448--IBMSJ0DB20001      0000000400000004 W R4 9034817015032
DISPLAY ACTIVE REPORT COMPLETE
DSNV406I - INDOUBT THREADS -
COORDINATOR      STATUS      RESET URID      AUTHID
IBMSTLDB20001:STLDB21      INDOUBT      03201050B000 SM43YY33
V467-HAS LUWID IBM.STLDB21.16B57B954427.0003=5
V466-THREAD HAS BEEN INDOUBT FOR 00:05:20
DISPLAY INDOUBT REPORT COMPLETE
DSN9022I - DSNVDT '-DIS THD' NORMAL COMPLETION
```

Example 4: This example shows a thread executing within a stored procedure and a thread waiting for a stored procedure to be scheduled. Assume that an application makes a call to stored procedure PROC1 and then to stored procedure PROC2. PROC2 is in a STOP QUEUE state.

The output for PROC1 while it is executing shows a status of SP in the ST column, which indicates that a thread is executing within a stored procedure:

-DIS THD(*)

This command produces output similar to the following output:

```
DSNV401I - DISPLAY THREAD REPORT FOLLOWS -
DSNV402I - ACTIVE THREADS - 176
NAME      ST A  REQ ID      AUTHID  PLAN      ASID TOKEN
BATCH     SP   3 RUNAPPL      SYSADM  PL01AP01 001D  43
V429 CALLING STORED PROCEDURE PROC1, LOAD MODULE LMPROC1
DISPLAY ACTIVE REPORT COMPLETE
DSN9022I - DSNVDT '-DISPLAY THREAD' NORMAL COMPLETION
```

The output for PROC2, while it is queued, shows a status of SW in the ST column, which indicates that a thread is waiting for a stored procedure to be scheduled:

-DIS THD(*)

This command produces output similar to the following output:

```
DSNV401I - DISPLAY THREAD REPORT FOLLOWS -
DSNV402I - ACTIVE THREADS - 198
NAME      ST A  REQ ID      AUTHID  PLAN      ASID TOKEN
BATCH     SW *  13 RUNAPPL      SYSADM  PL01AP01 001D  43
V429 CALLING STORED PROCEDURE PROC2, LOAD MODULE
DISPLAY ACTIVE REPORT COMPLETE
DSN9022I - DSNVDT '-DISPLAY THREAD' NORMAL COMPLETION
```

Example 5: This example shows an allied, nondistributed originating thread (TOKEN=30) that is established (allocated according to plan) in addition to all of its parallel tasks (PT) which are running on the same DB2. All parallel tasks are displayed immediately following their corresponding originating thread.

```
16.32.57      DB1G DISPLAY THREAD(*)
16.32.57 STC00090 DSNV401I DB1G DISPLAY THREAD REPORT FOLLOWS -
16.32.57 STC00090 DSNV402I DB1G ACTIVE THREADS -
NAME      ST A  REQ ID      AUTHID  PLAN      ASID TOKEN
BATCH     T *   1 PUPPYDML      USER001  DSNTEP3  0025  30
          PT *  641 PUPPYDML      USER001  DSNTEP3  002A  40
          PT *  72 PUPPYDML      USER001  DSNTEP3  002A  39
          PT *  549 PUPPYDML      USER001  DSNTEP3  002A  38
          PT *  892 PUPPYDML      USER001  DSNTEP3  002A  37
```

-DISPLAY THREAD (DB2)

```
PT *    47 PUPPYDML    USER001 DSNTEP3 002A 36
PT *    612 PUPPYDML    USER001 DSNTEP3 002A 35
PT *    545 PUPPYDML    USER001 DSNTEP3 002A 34
PT *    432 PUPPYDML    USER001 DSNTEP3 002A 33
PT *    443 PUPPYDML    USER001 DSNTEP3 002A 32
PT *    252 PUPPYDML    USER001 DSNTEP3 002A 31
DISPLAY ACTIVE REPORT COMPLETE
16.32.58 STC00090 DSN9022I DB1G DSNVDT '-DISPLAY THREAD' NORMAL
COMPLETION
```

Example 6: This example shows the detail report for a DB2 client that uses TCP/IP to access a remote DRDA server.

DISPLAY THREAD(*) LOCATION(*)

This command produces output similar to the following output:

```
DSNV401I - DISPLAY THREAD REPORT FOLLOWS -
DSNV402I - ACTIVE THREADS -
NAME      ST A  REQ ID          AUTHID PLAN      ASID  TOKEN
BATCH    TR *    6 BKH2C          SYSADM YW1019C  0009    2
V444-STLDRIV.SSLU.A23555366A29=2 ACCESSING DATA AT
V446-USIBMSTODB22:123.34.101.98:446
V447--LOCATION          SESSID          A ST TIME
V448--USIBMSTODB22    4019:446          V R2 9015611253116
DISPLAY ACTIVE REPORT COMPLETE
DSN9022I - DSNVDT '-DIS THD' NORMAL COMPLETION
```

Example 7: This example shows the detail report for a DB2 server that is accessed by a DRDA client using TCP/IP.

DISPLAY THREAD(*) LOCATION(*)

This command produces output similar to the following output:

```
DSNV401I - DISPLAY THREAD REPORT FOLLOWS -
DSNV402I - ACTIVE THREADS -
NAME      ST A  REQ ID          AUTHID PLAN      ASID  TOKEN
BATCH    RA *    5 BKH2C          SYSADM DISTSERV 0008    2
V445-STLDRIV.SSLU.A23555366A29=2 ACCESSING DATA FOR 123.34.101.98
V447--LOCATION          SESSID          A ST TIME
V448--123.34.101.98    446:3171          S2 9015611253108
DISPLAY ACTIVE REPORT COMPLETE
DSN9022I - DSNVDT '-DIS THD' NORMAL COMPLETION
```

Example 8: This example shows information about units of work whose back-out processing has been postponed.

-DISPLAY THREAD (*) TYPE (POSTPONED)

This command produces output similar to the following output:

```
DSNV401I - DISPLAY THREAD REPORT FOLLOWS -
DSNV431I - POSTPONED ABORT THREADS -
COORDINATOR          STATUS      RESET URID          AUTHID
BATCH                ABORT-P          000002FF98EA ADMF001
BATCH                ABORT-P          000002FF9000 ADMF001
DISPLAY POSTPONED ABORT REPORT COMPLETE
DSN9022I - DSNVDT '-DISPLAY THREAD' NORMAL COMPLETION
```

Example 9: This example shows the token for a thread that is executing a user-defined function. The token is 18.

-DISPLAY THREAD(*) DETAIL

-DISPLAY THREAD (DB2)

This command produces output similar to the following output:

```
DSNV401I - DISPLAY THREAD REPORT FOLLOWS -
DSNV402I - ACTIVE THREADS -
NAME      ST A  REQ ID      AUTHID  PLAN      ASID  TOKEN
BATCH     T  *   231 DISTHD    ADMF001          0021   95
BATCH     SW *    38 INSERT    ADMF001  DSNTEP3  0025   18
V436-PGM=CLIP74C1.UFIP74C1, SEC=0, STMNT=0
V429 CALLING FUNCTION =SCIP7401.SP_UFIP74C1
      PROC=V61AWLM3, ASID=0030, WLM_ENV=WLMENV3
DISPLAY ACTIVE REPORT COMPLETE
DSN9022I - DSNVDT '-DISPLAY THREAD' NORMAL COMPLETION
```

Example 10: This example shows information about a thread that is involved in an RRS Unit of Recovery.

-DIS THD(*) RRSURID(*)

This command produces output similar to the following.

```
- 08.23.58 STC00149 DSNV401I ( DISPLAY THREAD REPORT FOLLOWS -
- 08.23.58 STC00149 DSNV402I ( ACTIVE THREADS -
- NAME      ST A  REQ ID      AUTHID  PLAN      ASID  TOKEN
- RRSAF     T    8  TGXID-111    ADMF001  TGXIDR  0023   35
- V481-DB2 IS PARTICIPANT FOR RRS URID B4D0FC267EB020000000001101010000
- V437-WORKSTATION=
- APPLICATION NAME=
- DISPLAY ACTIVE REPORT COMPLETE
- 08.23.58 STC00149 DSN9022I ( DSNVDT '-DIS THD' NORMAL COMPLETION
```

Example 11: This example shows information about a thread where DB2 is the coordinator for an indoubt RRS Unit of Recovery. DB2 has committed the thread but has not been able to resolve the RRS UR with RRS.

-DIS THD(*) TYPE(I) RRSURID(*)

This command produces output similar to the following.

```
- 09.27.21 STC00185 DSNV406I ( INDOUBT THREADS -
- COORDINATOR      STATUS      RESET URID      AUTHID
- UNKNOWN          COMMITTED      123456789ABC UNKNOWN
- V480-DB2 IS COORDINATOR FOR RRS URID C4D4FA267EB040000000001201020000
00- DISPLAY INDOUBT REPORT COMPLETE
- 09.27.21 STC00185 DSNV434I ( DSNVDT NO POSTPONED ABORT THREADS FOUND
- 09.27.21 STC00185 DSN9022I ( DSNVDT '-DIS THD' NORMAL COMPLETION
```

-DISPLAY TRACE (DB2)

The DB2 command DISPLAY TRACE displays a list of active traces. For more information about this trace facility, see Part 4 (Volume 1) of *DB2 Administration Guide*.

There is an additional option to this command and values for a few options that are not described here. They are intended for service and use under the direction of IBM support personnel. For details, see *DB2 Diagnosis Guide and Reference*.

Abbreviation: -DIS TRACE

Environment

This command can be issued from an MVS console, a DSN session, a DB2I panel (DB2 COMMANDS), an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

#

Data sharing scope: Group or local, depending on the value of the SCOPE option.

Authorization


To execute this command, the privilege set of the process must include one of the following:

- DISPLAY privilege
- SYSOPR, SYSCTRL, or SYSADM authority

DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.

-DISPLAY TRACE (DB2)

Syntax



Option descriptions

None of the options are required. The command `DISPLAY TRACE` lists all active traces. Each option that is used, except `TNO`, limits the effect of the command to active traces that were started using the same option, either explicitly or by default, with exactly the same parameter values. For example, the command

```
-DISPLAY TRACE (PERFM) CLASS (1,2)
```

lists only the active traces that were started using the options `PERFM` and `CLASS (1,2)`; it does *not* list, for example, any trace started using `CLASS(1)`.

(*) Does not limit the list of traces. The **default** is (*).

The `CLASS` option cannot be used with `-DISPLAY TRACE (*)`.

Each of the following keywords limits the list to traces of the corresponding type. For further descriptions of each type, see “-START TRACE (DB2)” on page 299.

Type (Abbrev)	Description
PERFM (P)	Performance records of specific events
ACCTG (A)	Accounting records for each transaction
STAT (S)	Statistical data
AUDIT (AU)	Audit data
MONITOR (MON)	Monitor data

SCOPE

Specifies the scope of the command.

(LOCAL)

Displays the trace for the local member only.

(GROUP)

Displays the trace for all members in the data sharing group.

DETAIL(output-type)

Limits the information that a trace displays based on the output type specified within parentheses.

The possible values for *output-type* are:

- | | |
|------------|---|
| 1 | Display summary trace information: TRACE NUMBER, TYPE, CLASS, DEST |
| 2 | Display qualification trace information: TRACE NUMBER, AUTHID, PLAN, LOCATION |
| 1,2 | Display both summary and qualification information |
| * | Display both summary and qualification information |

If no parameter follows DETAIL, type 1 trace information is displayed.

An additional column, QUAL, is also displayed, indicating whether the trace is qualified. Part of the summary trace information, the QUAL column can be used to determine if further qualification information for the trace is available. This information can be obtained by specifying DETAIL (2) or DETAIL (*). A QUAL column value of YES indicates that additional information for this particular trace exists in the qualification trace information; a value of NO indicates that no additional information for this trace exists.

COMMENT(string)

Specifies that comment *string* appears in the trace output, except for the output in the resident trace tables.

string is any character string; it must be enclosed between apostrophes if it includes a blank, comma, or special character. The comment does not appear in the display; it can be recorded in trace output, but only if commands are being traced.

DEST

Limits the list to traces started for particular destinations. More than one value can be specified, but do not use the same value twice. If you do not specify a value for DEST, DB2 does not use the destination of where trace output is recorded to limit the list of traces displayed.

-DISPLAY TRACE (DB2)

Abbreviation: D

Possible values and their meanings are:

Value	Trace destination
GTF	The generalized trace facility
SMF	The system management facility
SRV	An exit to a user-written routine
OP <i>n</i>	A specific destination. <i>n</i> can be a value from 1 to 8.

See “-START TRACE (DB2)” on page 299 for a list of allowable destinations for each trace type.

PLAN(*plan-name*, ...)

Limits the list to traces started for particular application plans. Up to eight plan names can be used. If more than one name is used, only one value can be used for AUTHID, TNO, and LOCATION. Do not use this option with STAT.

The **default** is **PLAN**(*), which does not limit the list.

AUTHID(*authorization-id*, ...)

Limits the list to traces started for particular authorization identifiers. Up to eight identifiers can be used. If more than one identifier is used, only one value can be used for PLAN, TNO, and LOCATION. Do not use this option with STAT.

The **default** is **AUTHID**(*), which does not limit the list.

CLASS(*integer*, ...)

Limits the list to traces started for particular classes. For descriptions of the allowable classes, see “-START TRACE (DB2)” on page 299.

The **default** is **CLASS**(*), which does not limit the list.

TNO(*integer*, ...)

Limits the list to particular traces, identified by their trace numbers (1 to 32, 01 to 09). Up to eight trace numbers can be used. If more than one number is used, only one value each for PLAN, AUTHID, and LOCATION can be used.

The **default** is **TNO**(*), which does not limit the list.

LOCATION(*location-name*, ...)

Limits the list to traces started for threads that have a distributed relationship with the specified location.

(*location-name*)

The location names that you supply are the 1 to 16 character identifiers assigned to the DB2 subsystem whose traces you want to display. Supplying an * as the location name indicates that the trace display must include all traces started with any location name qualifier.

You can specify up to eight location names. If you specify more than one location name, you can only specify one value each for PLAN, AUTHID, and TNO.

LOCATION cannot be specified when you choose a statistics trace.

Requesters other than DB2 for OS/390 and z/OS: DB2 does not receive a location name from requesters that are not DB2. To display information about a requester that is not a DB2 for OS/390 and z/OS subsystem, enter its LUNAME, enclosed by the less-than (<) and greater-than (>) symbols. For example, the following command displays information about a remote location with the LUNAME of LULA:

```
-DISPLAY TRACE (*) LOCATION (<LULA>)
```

-DISPLAY TRACE (DB2)

DB2 uses the < LUNAME> notation in messages displaying information about requesters that are not DB2 for OS/390 and z/OS.

The **default** is **LOCATION(*)**, which does not limit the list.

<luname>

Activates the DB2 trace for the remote clients that are connected to DDF through the remote SNA LU that you specified in *luname*.

nnn.nnn.nnn.nnn

Activates the DB2 trace for the remote clients that are connected to DDF through the remote TCP/IP host whose IP address is specified by *nnn.nnn.nnn.nnn*.

Examples

Example 1: List all traces that have the generalized trace facility as their only destination.

```
-DISPLAY TRACE (*) DEST (GTF)
```

Example 2: List the trace started for Example 2 of -START TRACE.

```
-DISPLAY TRACE (ACCTG) PLAN (DSN8BC71)
COMMENT ('ACCTG TRACE FOR DSN8BC71')
```

Example 3: List all active performance traces.

```
-DISPLAY TRACE=P
```

Example 4: List all active audit traces for threads that are connected to the DB2 subsystem with location name USIBMSTODB23.

```
-DISPLAY TRACE (AUDIT) LOCATION (USIBMSTODB23)
```

Example 5: Output from -DISPLAY TRACE is a set of messages that look like this:

```
- 10.26.34          -DISPLAY TRACE
- 10.26.34 STC    21 DSNW127I - CURRENT TRACE ACTIVITY IS -
- TNO TYPE    CLASS          DEST QUAL
- 01 STAT     01             SMF  NO
- 02 ACCTG     01             SMF  YES
- 03 PERFM     01,02,03       GTF  YES
- 04 AUDIT     01,02,03,04,   SMF  YES
- 04           06,07
- 05 MON       01,02,03       OP1  NO
- *****END OF DISPLAY TRACE SUMMARY DATA*****
- 10.26.34 STC    21 DSN9022I - DSNWVCM1 '-DISPLAY TRACE' NORMAL COMPLETION

- 10.28.47          -DISPLAY TRACE DETAIL(*)
- 10.28.47 STC    21 DSNW127I - CURRENT TRACE ACTIVITY IS -
- TNO TYPE    CLASS          DEST QUAL
- 01 STAT     01             SMF  NO
- 02 ACCTG     01             SMF  YES
- 03 PERFM     01,02,03       GTF  YES
- 04 AUDIT     01,02,03,04,   SMF  YES
- 04           06,07
- 05 MON       01,02,03       OP1  NO
- *****END OF DISPLAY TRACE SUMMARY DATA*****
- 10.28.47 STC    21 DSNW143I - CURRENT TRACE QUALIFICATIONS ARE -
- TNO AUTHID   PLAN          RMID          LOCATION
- 01 *         *            *            *
- 02 *         *            *            *
- 03 USER01    *            *            *
- 04 *         *            14,16,18,26  DENVER
- 05 *         PROG1        *            *
```

-DISPLAY TRACE (DB2)

```
- 06 *           *           *  
- *****END OF DISPLAY TRACE QUALIFICATION DATA*****  
- 10.28.47 STC   21   DSN9022I - DSNWVCM1 '-DISPLAY TRACE' NORMAL COMPLETION
```

-DISPLAY UTILITY (DB2)

The DB2 command DISPLAY UTILITY displays the status of utility jobs, including utility jobs in a data sharing group.

The output from the command consists of informational messages only. One set of messages is returned for each job identified by the command. For utility jobs in a data sharing group, the output shows the member name of the system on which each utility job is running.

The status from the display represents the current status, except in a data sharing group when the utility is running on a member other than the one from which the command is issued. In that case, the status is current as of the last checkpoint.

Abbreviation: -DIS UTIL

Environment


This command can be issued from an MVS console, a DSN session, a DB2I panel (DB2 COMMANDS), an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

Data sharing scope: Group or member, depending on which option you choose

Authorization

None is required.

Syntax



Option descriptions

Use at least one of the following options but do not use the same one more than once.

(utility-id)

Identifies a single job by its utility identifier, the value given for the UID parameter when the job was created.

If *utility-id* was created by the DSNU CLIST by default, it has the form of *tso-userid.control-file-name*. For a list of values for *control-file-name*, see the description of the UID parameter for the DSNU command procedure (CLIST) in *DB2 Utility Guide and Reference*.

If *utility-id* was omitted, *utility-id* has the form *userid.jobname*.

(partial-utility-id*)

Identifies a set of utility jobs. A status message is shown for each utility identifier that begins with the characters of *partial-utility-id*.

-DISPLAY UTILITY (DB2)

For example, -DISPLAY UTILITY(ABCD*) shows the status of every utility job known to DB2 whose identifier begins with the characters ABCD.

- (*) Shows the status of all utility jobs known to DB2, including jobs currently running in a data sharing group.

MEMBER (*member-name, ...*)

Restricts the display for the identified utility jobs to specific members of the data sharing group. The default is to display utility jobs running on any member. In a non-data-sharing environment, the option is ignored.

One set of messages is returned for each job identified by the command.

Usage notes

DISPLAY status: The status displayed in the returned message is the status at the time the DB2 utility function received the command. Execution has proceeded, therefore the current state of the utility can be different from the state reported. For instance, the DISPLAY UTILITY command can indicate a particular utility identifier is active, but, when the message is received by the requester, the utility job step could have terminated so that the utility identifier is no longer known to DB2.

Command response: In a data sharing environment, messages DSNU100I, DSNU105I, DSNU106I show the name of the member on which the utility job is running. If you specify a single member name in the MEMBER option and that member does not belong to the group, or if you specify a list of member names in the MEMBER option and none of those members belong to the group, the command fails and a message is issued.

Output

The output from -DISPLAY UTILITY consists of informational messages only.

Output during any phase of REORG with SHRLEVEL CHANGE or SHRLEVEL REFERENCE: During *any* phase of REORG with SHRLEVEL CHANGE or SHRLEVEL REFERENCE, the output of -DISPLAY UTILITY includes the information in DSNU347I. During *any* phase of REORG with SHRLEVEL CHANGE, the output of DISPLAY UTILITY includes information in DSNU384I as follows as shown in “Example 4” on page 174

DEADLINE

Indicates a timestamp according to the most recently specified value of DEADLINE.

MAXRO

Indicates the number of seconds, according to the most recently specified value of MAXRO.

LONGLOG

Indicates either CONTINUE, TERM, or DRAIN according to the most recently specified value of LONGLOG.

DELAY

Indicates the number of seconds according to the most recently specified value of DELAY.

Output during LOG phase of REORG with SHRLEVEL CHANGE: During the LOG phase of REORG with SHRLEVEL CHANGE, the output of -DISPLAY UTILITY now includes the additional information found in message DSNU383I as shown in “Example 4” on page 174 as follows:

CURRENT ITERATION NUMBER

Indicates the current iteration number.

WRITE ACCESS ALLOWED IN CURRENT ITERATION

Indicates “YES” or “NO” according to whether write access is allowed in the current iteration of log processing.

ITERATION BEFORE PREVIOUS ITERATION

Indicates the ELAPSED TIME so far, and the NUMBER OF LOG RECORDS PROCESSED in the iteration. Their values are 0 if the current iteration number is 1 or 2.

PREVIOUS ITERATION

Indicates the ELAPSED TIME and the NUMBER OF LOG RECORDS PROCESSED for the previous iteration. Their values are 0 if the current iteration number is 1.

CURRENT ITERATION:

Indicates the ESTIMATED ELAPSED TIME, the ACTUAL ELAPSED TIME SO FAR and the ACTUAL NUMBER OF LOG RECORDS BEING PROCESSED.

CURRENT ESTIMATE FOR NEXT ITERATION

For the next iteration, indicates the currently ELAPSED TIME and the currently estimated NUMBER OF LOG RECORDS TO BE PROCESSED.

Progress of utility processing: The DISPLAY UTILITY command provides the user an estimate of how much processing the utility has completed. The output displays information from message DSNU105I as seen in “Example 2” and includes:

COUNT

COUNT *n* is the number of pages or records processed in a utility phase. COUNT has different meanings for different utilities. For utilities not mentioned below, ignore this field.

- For LOAD, COUNT represents the total number of records that have been loaded into all partitions when the command was issued. The count is zero from the time the RELOAD phase starts until the first LOAD subtask begins loading records into the first partition assigned to that subtask.
- For CHECK INDEX, RECOVER INDEX, and REORG, COUNT represents the number of records processed.
- For COPY, MERGE COPY, RECOVER (restore phase), and RUNSTATS, COUNT represents the number of pages processed.
- For STOSPACE, COUNT represents the number of table spaces or indexes processed.

For more information, see *DB2 Utility Guide and Reference*.

Examples

Example 1: Display status information for all utility jobs currently known to DB2.

-DISPLAY UTILITY (*)

Example 2: Display the status of utilities on all members of the data sharing group.

-DB1G DISPLAY UTILITY (*)

The following output, which shows utility jobs on members DB1G and DB2G, is generated:

-DISPLAY UTILITY (DB2)

```
DSNU100I -DB1G DSNUGDIS USER = SAMPID
          MEMBER = DB1G
          UTILID = RUNTS
          PROCESSING UTILITY STATEMENT 1
          UTILITY = RUNSTATS
          PHASE = RUNSTATS COUNT = 0
          STATUS = STOPPED
DSNU100I -DB1G DSNUGDIS USER = SAMPID
          MEMBER = DB2G
          UTILID = CHKIX1
          PROCESSING UTILITY STATEMENT 8
          UTILITY = CHECK
          PHASE = UNLOAD COUNT = 0
          STATUS = STOPPED
DSN9022I -DB1G DSNUGCC '-DB1G DISPLAY UTILITY' NORMAL COMPLETION
```

Example 3: In a data sharing environment, display the status of utilities on member DB1G.

```
-DB1G DISPLAY UTILITY (*) MEMBER (DB1G)
```

Example 4: This shows output from the command DISPLAY UTILITY:

```
-DB1G DISPLAY UTILITY(*)
DSNU105I -DB1G DSNUGDIS - USERID = SYSADM 973
          MEMBER =
          UTILID = REORGCP
          PROCESSING UTILITY STATEMENT 1
          UTILITY = REORG
          PHASE = LOG COUNT = 0
          STATUS = ACTIVE
DSNU347I -DB1G DSNUGDIS - 974
          DEADLINE = NONE
DSNU384I -DB1G DSNUGDIS - 975
          MAXRO = DEFER
          LONGLOG = CONTINUE
          DELAY = 1200 SECONDS
DSNU383I -DB1G DSNUGDIS - CURRENT ITERATION NUMBER = 4 976
WRITE ACCESS ALLOWED IN THIS ITERATION = YES
ITERATION BEFORE PREVIOUS ITERATION:
  ELAPSED TIME = 00:00:00
  NUMBER OF LOG RECORDS PROCESSED = 0
PREVIOUS ITERATION:
  ELAPSED TIME = 00:00:00
  NUMBER OF LOG RECORDS PROCESSED = 0
CURRENT ITERATION:
  ESTIMATED ELAPSED TIME = 00:00:00
  ACTUAL ELAPSED TIME SO FAR = 00:00:00
  ACTUAL NUMBER OF LOG RECORDS BEING PROCESSED = 0
CURRENT ESTIMATE FOR NEXT ITERATION:
  ELAPSED TIME = 00:00:00
  NUMBER OF LOG RECORDS TO BE PROCESSED = 0
DSN9022I -DB1G DSNUGCCC '-DIS UTIL' NORMAL COMPLETION
```


DSN (TSO)

The TSO command DSN enables you to issue DSN subcommands, namely:

ABEND	BIND	DCLGEN	END
FREE	REBIND	RUN	SPUFI

During a DSN session, you can enter DB2 commands or comments. DB2 commands must start with a hyphen (-). Comments must start with an asterisk (*).

During a DSN session, you can also issue TSO commands, except for FREE, RUN, TEST, and TIME. To use TSO TEST to debug an application program, execute it with the DSN command; for example:

```
TEST 'prefix.SDSNLOAD(DSN)' CP
```

The ABEND subcommand listed above is used for diagnostic purposes only, and is intended to be used only under the direction of your IBM Support Center. Use it only when diagnosing a problem with DSN or DB2. Percent commands are not recognized during a DSN session, they are only supported by the TSO command processor.

Environment

A DSN session runs under TSO in either foreground or background mode. When you run it in background mode, you are not prompted for corrections or additional required information.


You can also start a DSN session from a CLIST running in either foreground or background mode.

Data sharing scope: Member

Authorization

None is required for the DSN command, but authorization is required for most subcommands.

Syntax



Option descriptions

None of the following options are required.

SYSTEM

DSN (TSO)

(*subsystem-name*)

Specifies the name of the DB2 subsystem.

(*group-attachment-name*)

Specifies the group attachment name of the data sharing group.

The **default** is **SYSTEM(DSN)**. This value can be modified during DB2 installation.

RETRY(*integer*)

Specifies the number (*integer*) of additional times connection to the DB2 subsystem should be attempted if DB2 is not up or the maximum number of batch connections has been reached when DSN is issued. Retries occur at 30-second intervals.

The **default** is **RETRY(0)**. The maximum number of retries is 120.

TEST(*integer*)

Specifies the last two digits (*integer*) of the module name in order to trace a single DSN module. Specify a number greater than 100 to trace all DSN modules. DSN trace information messages are written to the TSO SYSTSPRT DD statement, and optionally, to the DSNTRACE DD statement.

GROUP

(**YES**) Specifies to consider group attach processing when the specified system is not active.

(**NO**) Specifies that group attach processing is not considered.

Usage notes

Beginning a DSN session: Issue the DSN command to begin a DSN session, which allows you to enter DSN subcommands. These rules govern the session:

- In foreground operation, you are prompted for input by the prompt string DSN at the terminal. In background mode, your input is read from the SYSTSIN data set.
- Except for delimited table names in the DCLGEN command, input in lowercase letters is changed to uppercase.
- If duplicate keywords of any subcommand are specified, only the last of these keywords is processed. For example, if both MEMBER(*dbrm-member-name1*) and MEMBER(*dbrm-member-name2*) are specified with BIND PLAN, DB2 receives only the latter, MEMBER(*dbrm-member-name2*).
- If ATTENTION (PA1) is pressed during a DSN session, and PROMPT is specified in the TSO user profile, message DSNE005 appears: EXECUTION IS INTERRUPTED, ENTER C TO CANCEL, OR ANY OTHER REPLY TO RESUME THE *subcommand* SUBCOMMAND.

If you enter C, the current subcommand is canceled and the current DB2 connection terminates; a new one is established, and another DSN prompt appears. Any other reply, except ATTENTION, causes the current subcommand to continue from the point at which it was interrupted.

If a DSN session is started from a CLIST, or a CLIST is executed under DSN, CONTROL PROMPT must be specified in the CLIST in order to receive message DSNE005.

- After a command is processed during a DSN session, you are prompted for input. That cycle continues until you end the session.
- You can end the session by doing one of the following:
 - Issue the END subcommand. Control is passed to TSO.

- Press ATTENTION and respond to the message by pressing ATTENTION again.
- Issue another DSN command. The old session ends and a new one begins.

DSN return code processing: At the end of a DSN session, register 15 contains the highest value placed there by any DSN subcommand used in the session or by any program run by the RUN subcommand. Your run-time environment might format that value as a return code. The value does not, however, originate in DSN.

Examples

Example 1: Start a DSN session. If the attempt to connect to DB2 fails, five retries (at 30 second intervals) are to be made.

```
DSN SYSTEM (DB2) RETRY (5)
```

Example 2: Start a DSN session, run a program, and then end the session and return to TSO.

```
TSO prompt : READY
USER enters: DSN SYS (SSTR)
DSN prompt : DSN
USER enters: RUN PROGRAM (MYPROG)
DSN prompt : DSN
USER enters: END
TSO prompt : READY
```

DSNC (CICS attachment facility)

The CICS attachment facility DSNC command allows you to enter DB2 commands from CICS.

Environment

This command can be issued only from a CICS terminal.


Data sharing scope: Member

Authorization

This command requires the appropriate level of CICS authority, as described in the appropriate *CICS for MVS/ESA CICS-RACF Security Guide* or *CICS for MVS/ESA Operations and Utilities Guide*.

Entering the DSNC command requires no privileges from DB2 security. For a description of the privileges required to issue a DB2 command using the DSNC command, see the command's description.

Syntax



Option descriptions

destination

Identifies another terminal to receive display information. It must be a valid terminal that is defined to CICS and supported by CICS basic mapping support (BMS).

db2-command

Specifies the exact DB2 command that you want to enter from a CICS terminal. It must be preceded by a hyphen.

Usage note

Screen scrolling: The CICS SIT table keyword SKRxxxx can be used to support the scrolling of DSNC DB2 commands from your terminal. For further information regarding the SIT keywords and parameters, see *CICS for MVS/ESA System Definition Guide*.

Example

Example: Issue the DB2 command -DISPLAY THREAD from a CICS terminal.

```
DSNC -DISPLAY THREAD
```

DSNC DISCONNECT (CICS attachment facility)

The CICS attachment facility command DSNC DISCONNECT disconnects threads.

The command provides manual control to release resources being shared by normal transactions so that special purpose processes, such as utilities, can have exclusive access to the resources.

Abbreviation: DSNC DISC

Environment

This command can be issued only from a CICS terminal.

Data sharing scope: Member

Authorization

This command requires an appropriate level of CICS authority, as described in the appropriate *CICS for MVS/ESA CICS-RACF Security Guide*.

Syntax

```
►►—DSNC DISCONNECT—plan-name—►►
```

Option description

plan-name

Specifies a valid application plan.

Usage notes

Preventing creation of threads: The command DSNC DISCONNECT does not prevent threads from being created on behalf of transactions. The command only causes currently connected threads to be terminated as soon as they are not being used by a transaction. To interrupt a transaction and cancel a thread faster, you can use the command CANCEL THREAD. For details, see “-CANCEL THREAD (DB2)” on page 77.

You can stop the transactions associated with a particular plan ID in CICS with the MAXIMUM setting for TCLASS or MAXACTIVE setting for TRANCLASS. This prevents new instances of the transaction from causing a re-creation of a thread.

Alternative for protected threads: You may want to deallocate a plan for rebinding or for running a utility against the database. If you are using a protected thread, use DSNC MODIFY rather than DSNC DISCONNECT. Modify the THRDA value of the plan to zero to send all the threads to the pool. The protected thread will terminate on its own within 60 seconds and DISCONNECT is unnecessary.

Example

Disconnect active threads for PLAN1.

```
DSNC DISC PLAN1
```

DSNC DISPLAY (CICS attachment facility)

The CICS attachment facility command DSNC DISPLAY displays information on CICS transactions accessing DB2 data, or statistical information associated with entries in the resource control table (RCT).

Abbreviation: DSNC DISP

Environment


This command can be issued only from a CICS terminal.

Data sharing scope: Member

Authorization

This command requires an appropriate level of CICS authority, as described in the *CICS for MVS/ESA CICS-RACF Security Guide* or *CICS for MVS/ESA Operations and Utilities Guide*.

Syntax



Option descriptions

PLAN *plan-name*

Displays information about transactions by plan name.

plan-name is a valid plan name for which information is displayed.

Default: If you do not specify *plan-name* (or if you specify an asterisk, *), information is displayed for all active plan names listed in the resource control table.

TRANSACTION *transaction-id*

Displays information about transactions by transaction ID.

Abbreviation: TRAN

transaction-id is a valid transaction ID for which information is displayed. For a group transaction entry in the resource control table, you can enter an identifier for any transaction associated with the group.

Default: If you do not specify a transaction ID, information is displayed for all active transactions listed in the resource control table.

STATISTICS

Displays the statistical counters associated with each entry in the resource control table. The counters concern the usage of the available connections of the CICS attachment facility to DB2.

Abbreviation: STAT

DSNC DISPLAY (CICS)

If you issue this command from CICS while the CICS attachment facility is active but the DB2 subsystem is not, a statistics display is produced with no obvious indication that the subsystem is not operational. Message DSNCO37A appears in the CICS message log to indicate that the attachment facility is waiting for DB2 to start.

For a description of the output produced by this parameter, see Part 4 (Volume 1) of *DB2 Administration Guide*.

destination

Is the identifier of another terminal to receive the requested display information. It must be a valid terminal that is defined to CICS and supported by CICS basic mapping support (BMS).

Usage notes

Entering parameters: Because the optional destination is sometimes preceded by an optional plan name or transaction ID in the command, each parameter must be unique and separately identifiable as either a name or a terminal identifier. If only one parameter is entered, it is first checked to see whether it is a plan name or a transaction ID, and it is then checked as a destination. To use a character string that is both a plan name or transaction ID and also a valid terminal identifier, you must use both the name and destination parameters to display the desired information at the desired terminal.

Acknowledging display information sent to an alternate destination: When an alternate destination is specified to receive the requested display information, the following message is sent to the requesting terminal:

```
DSNC020I THE DISPLAY COMMAND IS COMPLETE
```

Output

The following is an example of the output for the DSNC DISPLAY (PLAN or TRANSACTION) command. For each created thread, the output shows the plan or transaction name. An 'A' in field A/I indicates that the thread is within a unit of work. An 'I' indicates that the thread is waiting for a unit of work authorization ID for the plan being used.

```
DSNC013I DISPLAY REPORT FOLLOWS
NAME    A/I    AUTH-ID
XP05    A      SYSADM
DSNC020I THE DISPLAY COMMAND IS COMPLETE
```

For each entry in the RCT, the output of a DSNC DISPLAY STATISTICS command as seen in “Example 4” on page 183 displays the following information:

TRAN Transaction name. For group entries, this is the name of the first transaction defined in the group. DSNC shows the statistics for the TYPE=COMD RCT entry. POOL shows statistics for the TYPE=POOL entry, unless the TYPE=POOL entry contains the parameter TXID=x.

PLAN The plan name associated with this entry. Eight asterisks in this field indicates that this transaction is using dynamic plan allocation. The command processor transaction DSNC does not have a plan associated with it because it uses a command processor.

CALLS

The total number of SQL statements issued by transactions associated with this entry.

DSNC DISPLAY (CICS)

AUTHS

The total number of sign-on invocations for transactions associated with this entry. A sign-on does not indicate whether a new thread is created or an existing thread is reused. If the thread is reused, a sign-on occurs only if the authorization ID or transaction ID has changed.

W/P

The number of times that all available threads for this entry were busy. This value depends on the value of TWAIT for the entry.

If TWAIT was set to POOL in the RCT, W/P indicates the number of times the transaction overflowed to the pool. An overflow to the pool shows up in the transaction statistics only and is not reflected in the pool statistics.

If TWAIT was set to YES, this reflects the number of times that the thread both had to wait, and could not attach a new subtask (number of started tasks has reached THRDA).

The only time W/P is updated for the pool is when a transaction had to wait for a pool thread and a new subtask could not be attached for the pool. The W/P statistic is useful for determining if there are enough threads defined for the entry.

HIGH

The maximum number of threads required by transactions associated with this entry at any time since the connection was started. This number includes the transactions that were forced to wait or diverted to the pool. It provides a basis for setting the maximum number of threads for the entry.

ABORTS

The total number of units of recovery which were rolled back. It includes both abends and SYNCPOINT ROLLBACKS, including SYNCPOINT ROLLBACKS generated by -911 SQL codes.

COMMITTS

One of the following two fields is incremented each time a DB2 transaction associated with this entry has a real or implied (such as EOT) syncpoint. Units of recovery that do not process SQL calls are not reflected here.

1-PHASE

The total number of single phase commits for transactions associated with this entry. This total does not include any two-phase commits (see the explanation for 2-PHASE below). This total does include read-only commits as well as single phase commits for units of recovery which have performed updates. A two-phase commit is needed only when CICS is the recovery coordinator for more than one resource manager.

2-PHASE

The total number of two-phase commits for transactions associated with this entry. This number does not include one-phase commit transactions.

Examples

Example 1: Display information on all active plan IDs listed in the resource control table. The display information is to be sent to another terminal designated as MTO2.

```
DSNC DISP PLAN * MTO2
```

Example 2: Display information about all active transactions listed in the resource control table.

```
DSNC DISP TRANSACTION
```


DSNC DISPLAY (CICS)

Example 3: Display statistical counters associated with each entry in the resource control table.

DSNC DISP STAT

Example 4: This is an example of the output for the DSNC DISPLAY STATISTICS command:

DSNC014I STATISTICS REPORT FOR 'DSNCRCTC' FOLLOWS

								-----COMMITES-----	
TRAN	PLAN	CALLS	AUTHS	W/P	HIGH	ABORTS	1-PHASE	2-PHASE	
DSNC		1	1	1	1	0	0	0	
POOL	POOL	0	0	0	0	0	0	0	
XC01	DSNXC01	22	1	11	2	0	7	5	
XC02	DSNXC02	0	0	0	0	0	0	0	
XA81	DSNA81	0	0	0	0	0	0	0	
XCD4	DSNCED4	0	0	0	0	0	0	0	
XP03	DSNTP03	1	1	0	1	0	1	0	
XA20	DSNTA20	1	1	0	1	0	0	1	
XA88	*****	0	0	0	0	0	0	0	

DSNC020I THE DISPLAY COMMAND IS COMPLETE

DSNC MODIFY (CICS attachment facility)

The CICS attachment facility command DSNC MODIFY modifies the ERRDEST entry in the resource control table (RCT), or the maximum active thread value associated with a given transaction or group name.

Abbreviation: DSNC MODI

Environment


This command can be issued only from a CICS terminal.

Data sharing scope: Member

Authorization

This command requires an appropriate level of CICS authority, as described in the appropriate *CICS for MVS/ESA CICS-RACF Security Guide* or *CICS for MVS/ESA Operations and Utilities Guide*.

Syntax



Option descriptions

DESTINATION

Specifies that the ERRDEST parameter of the resource control table is to be changed, replacing the “old” destination ID with the “new” destination ID.

Abbreviation: DEST

old

Is any destination ID currently active in the ERRDEST of the resource control table.

new

Is a new destination identifier. The new destination is verified to ensure that it is an existing transient data entry in the destination control table.

TRANSACTION

Specifies that the maximum active thread value associated with the given transaction or group is to be modified.

Abbreviation: TRAN

transaction-id

Is a valid transaction identifier. If the change is for a group transaction entry in the RCT, any transaction ID associated with the group can be entered to identify the entry.

integer

Is a new maximum value.

Usage notes

Protected threads: If you increase the active thread value using the command DSNC MODIFY TRANSACTION, the attributes of the TYPE=ENTRY macro are used. If the TYPE=ENTRY definition does not include a setting for an attribute, then the TYPE=INIT value is used.

Issuing DSNC MODIFY TRANSACTION to increase the total threads permitted allows creation of unprotected threads. For example, assume THRDS=2, THRDA=2 and THRDM=6. If the total number of threads permitted is increased, the additional threads are unprotected.

The command DSNC MODIFY TRANSACTION can also allow creation of protected threads. If THRDS=2, THRDA=2 and THRDM=6 and the value of THRDA is modified to 1, one of the protected threads is eliminated. If the value of THRDA is then modified back to 2, the thread that is re-created is protected.

TRANSACTION thread limit: The *integer* specified in the command DSNC MODIFY TRANSACTION cannot be larger than the value specified for the THRDM parameter of the DSNCRCT TYPE=ENTRY macro. The lowest possible value is zero. The value specified for the THRDM parameter is an upper limit (provided during initialization) on the number of threads to be connected for a transaction group. For more information about defining the thread limit, see Part 2 of *DB2 Installation Guide*.

Example

Change the specification of the ERRDEST parameter in the resource control table from MTO1 to MTO2.

```
DSNC MODI DEST MT01 MT02
```

DSNC STOP (CICS)

DSNC STOP (CICS attachment facility)

The CICS attachment facility command DSNC STOP stops the attachment facility.

Environment


This command can be issued only from a CICS terminal.

Data sharing scope: Member

Authorization

This command requires an appropriate level of CICS authority, as described in the appropriate *CICS for MVS/ESA CICS-RACF Security Guide* or *CICS for MVS/ESA Operations and Utilities Guide*.

Syntax



Option descriptions

QUIESCE

Specifies that the CICS attachment facility is to be stopped after CICS transactions currently running terminate.

Abbreviation: Q

FORCE

Specifies that the CICS attachment facility is to be stopped immediately by forcing disconnection with DB2, regardless of any transactions that are running.

Usage notes

Requirements for restarting: Using FORCE can leave threads in an indoubt situation. Restarting requires reconnection of CICS and DB2 to resolve any indoubt situations. In a data sharing environment, resolution of indoubt situations requires that the CICS be reconnected to the same DB2 member.

Output destinations: Output from the command DSNC STOP is sent to both the requesting terminal, and to the transient data queue for error messages defined in the DSNCRCT TYPE=INITIAL macro.

Example

Stop the CICS attachment facility.
DSNC STOP FORCE

DSNC STRT (CICS attachment facility)

The DSNC STRT command starts the CICS attachment facility, which allows CICS application programs to access DB2 databases.

Environment


This command can be issued only from a CICS terminal.

Data sharing scope: Member

Authorization

This command requires an appropriate level of CICS authority, as described in the appropriate *CICS for MVS/ESA CICS-RACF Security Guide* or *CICS for MVS/ESA Operations and Utilities Guide*.

Syntax



Option descriptions

rct-suffix

Specifies the resource control table to be loaded when the CICS attachment facility starts. The *rct-suffix*, which can be one or two bytes, is appended to DSN2CT to create the name of the resource control table. (For example, if you specify 33 as the *rct-suffix*, module DSN2CT33 is loaded.)

The **default** is the suffix specified in the CICS INITPARM parameter, a feature of the new CICS attachment facility. If a suffix was not specified in INITPARM, the default is 00, and module DSN2CT00 is loaded.

ssid

Specifies the subsystem ID (SSID) field of the resource control table, which allows the attachment facility to connect to any DB2 subsystem using just one resource control table. No blanks are allowed between the suffix and the SSID.

The **default** is the SSID specified in the CICS INITPARM parameter. If an SSID was not specified in INITPARM, the default is the SSID specified in the resource control table.

Usage note

Output destinations: Output from the DSNC START command is sent to both the requesting terminal, and to the transient data queue for error messages defined in the DSNCRCT TYPE=INIT macro.

Examples

Example 1: Start the CICS Version 4 Release 1 attachment facility. Use DSN2CT33 to connect to SSID DB2P.

```
DSNC STRT 33,DB2P
```

DSNC STRT (CICS)

Example 2: Start the CICS Version 4 Release 1 attachment facility. Use the default resource control table with SSID DBA1.

```
DSNC STRT ,DBA1
```

Example 3: Start the CICS Version 4 Release 1 attachment facility. Use DSN2CTA to connect to the SSID that is specified in DSN2CTA.

```
DSNC STRT A
```

DSNH (TSO CLIST)

The DSNH command procedure (a TSO CLIST) is a powerful yet easy method of preparing an application program for execution. By issuing a single command, you can select numerous options required for the preparation of an application and execute it under TSO.

DSNH processing is a sequential process that can include any of the following actions referred to by the two-letter step name:

For invoking the...	Use step name
PL/I macro processor	MP
DB2 precompiler	PC
CICS command language translator	TR
DSN BIND PLAN subcommand for binding a plan	BI
DSN BIND PACKAGE subcommand for binding a package	BP
Compiler or assembler for your program	CO
A C compiler prelink utility for including compile-time parameters	PL
Link-editor to produce an executable load module	LE
DSN RUN subcommand to execute the program	RU

Note: The step names are used in the heading of Table 18 on page 190.

Individual steps or a sequence of steps can be performed, and you can end the process at any point you choose. Any steps in the process that are skipped must have been previously completed successfully by DSNH. For guidance in preparing an application program for execution, see *DB2 Application Programming and SQL Guide*. See Table 1 on page 7 for a description of the DSN BIND subcommands.

Environment

The DSNH CLIST can run in TSO foreground or in batch under the TSO terminal monitor program. DB2I uses the DSNH CLIST on the precompiler panel to control program preparation. You can pass DSNH parameters from DB2I panels on the "Other options" lines.

Data sharing scope: Member

Authorization


See "BIND PACKAGE (DSN)" on page 32 for a description of the privileges necessary to bind a package.

See "BIND PLAN (DSN)" on page 38 for a description of the privileges necessary to bind a plan.

See "RUN (DSN)" on page 262 for a description of the privileges necessary to run a plan.

DSNH (TSO CLIST)

Syntax



Summary of DSNH CLIST parameters

The CLIST parameters provide the processing options for each step; specify them when you execute DSNH. Some parameters are used for more than one step, as indicated in Table 18. The figure shows where each parameter is used, using the following notation:

- Y in any cell shows that the option listed at the beginning of the row is used in the step whose name appears at the top of the column.
- * in any cell indicates that the option listed at the beginning of the row is used in *another* step which affects the step whose name appears at the top of the column.

Notation of CLIST parameters for the BIND PLAN and BIND PACKAGE steps: Many parameters of BIND PLAN and of BIND PACKAGE provide the same function and are spelled alike. CLIST parameters for BIND PLAN and BIND PACKAGE are differentiated from general parameters and from each other by prefixes. A parameter name prefixed by the letter B applies to the BIND PLAN subcommand; a parameter name prefixed by the letter P applies to BIND PACKAGE.

In Table 18, a prefix is separated from the DB2 parameter name by a slash (/). Table 17 shows the variations possible for a single parameter name.

Table 17. DSNH CLIST prefixing rules

Parameter value	Function or subcommand	Example
<i>parameter</i>	If no prefix is specified, the parameter applies to a single function or subcommand.	DBRMLIB
<i>B/parameter</i>	The prefix B is used to indicate that this variation of the parameter applies only to the BIND PLAN step.	BDBRMLIB
<i>P/parameter</i>	The prefix P is used to indicate that this variation of the parameter applies only to the BIND PACKAGE step.	PDBRMLIB

Table 18. Summary of DSNH CLIST parameters

OPTIONS	MP	PC	TR	BI	BP	CO	PL	LE	RU
ACQUIRE	-	-	-	Y	-	-	-	-	*
P/ACTION	-	-	-	Y	Y	-	-	-	-
ASMLIB	-	-	-	-	-	Y	-	-	-
ASMLOAD	-	-	-	-	-	Y	-	-	-
P/BDMEM	-	-	-	Y	Y	-	-	-	-
P/BIND	-	-	-	Y	Y	-	-	-	-
P/BLIB	-	-	-	Y	-	-	-	-	-
P/BnLIB	-	-	-	Y	-	-	-	-	-
P/BMEM	-	-	-	Y	Y	-	-	-	-
CACHESIZE	-	-	-	Y	-	-	-	-	-

Table 18. Summary of DSNH CLIST parameters (continued)

OPTIONS	MP	PC	TR	BI	BP	CO	PL	LE	RU
CCLINK	-	-	-	-	-	-	Y	-	-
CCLLIB	-	-	-	-	-	-	-	Y	-
CCLOAD	-	-	-	-	-	Y	-	-	-
CCMSGSGS	-	-	-	-	-	Y	Y	-	-
CCOLIB	-	-	-	-	-	-	Y	-	-
CCPLIB	-	-	-	-	-	-	-	Y	-
CCPMSGSGS	-	-	-	-	-	-	Y	-	-
CCSLIB	-	-	-	-	-	Y	-	-	-
P/CICS	-	-	-	Y	Y	-	-	-	-
CICSCOB	-	-	Y	-	-	-	-	Y	-
CICSLLIB	-	-	Y	-	-	-	-	Y	-
CICSOPT	-	-	Y	-	-	-	-	-	-
CICSPRE	-	-	Y	-	-	-	-	Y	-
CICSPLIB	-	-	Y	-	-	-	-	Y	-
CICSVER	-	-	Y	-	-	-	-	Y	-
CICSXLAT	-	-	Y	-	-	-	-	-	-
CLIB	Y	-	-	-	-	Y	-	-	-
CnLIB	Y	-	-	-	-	Y	-	-	-
COBICOMP	-	-	-	-	-	-	-	Y	-
COBILINK	-	-	-	-	-	-	-	Y	-
COBIPLNK	-	-	-	-	-	-	Y	-	-
COBIPMSG	-	-	-	-	-	-	Y	-	-
COBLIB	-	-	-	-	-	-	-	Y	-
COBLOAD	-	-	-	-	-	Y	-	-	-
COBSOM	-	-	-	-	-	-	Y	-	-
COB2CICS	-	-	-	-	-	-	-	Y	-
COB2LIB	-	-	-	-	-	-	-	Y	-
COB2LOAD	-	-	-	-	-	Y	-	-	-
COMPILE	-	-	-	-	-	Y	-	-	-
CONNECT	-	Y	-	-	-	-	-	-	-
CONTROL	Y	-	Y	*	-	Y	-	Y	Y
COPTION	Y	-	-	-	-	Y	-	-	-
COPY	-	-	-	-	Y	-	-	-	-
COPYVER	-	-	-	-	Y	-	-	-	-
CPPCLASS	-	-	-	-	-	-	Y	-	-
CPPCLINK	-	-	-	-	-	-	Y	-	-
CPPCLLIB	-	-	-	-	-	-	-	Y	-
CPPCSLIB	-	-	-	-	-	Y	-	-	-
CPPLLIB	-	-	-	-	-	-	Y	-	-
CPPPMMSGSGS	-	-	-	-	-	-	Y	-	-
CPPSLIB	-	-	-	-	-	Y	-	-	-
CPPUTIL	-	-	-	-	-	Y	-	-	-
CURRENTDATA	-	-	-	Y	Y	-	-	-	-
CURRENTSERVER	-	-	-	Y	-	-	-	-	-
DATE	-	Y	-	-	-	-	-	-	-
P/DBPROTOCOL	-	-	-	Y	Y	-	-	-	-
P/B/DBRMLIB	-	Y	-	Y	Y	-	-	-	-
DECARTH	-	Y	-	-	-	-	-	-	-
DECIMAL	-	Y	-	-	-	*	-	-	-
P/DEFER	-	-	-	Y	Y	-	-	-	-
P/DEGREE	-	-	-	Y	Y	-	-	-	-
DELIMIT	-	Y	Y	-	-	Y	-	-	-
P/DISABLE	-	-	-	Y	Y	-	-	-	-
DISCONNECT	-	-	-	Y	-	-	-	-	-

DSNH (TSO CLIST)

Table 18. Summary of DSNH CLIST parameters (continued)

OPTIONS	MP	PC	TR	BI	BP	CO	PL	LE	RU
P/DLIBATCH	-	-	-	Y	Y	-	-	-	-
P/DYNAMICRULES	-	-	-	Y	Y	-	-	-	-
P/ENABLE	-	-	-	Y	Y	-	-	-	-
ENTRY	-	-	-	-	-	-	-	Y	-
EXPLAIN	-	-	-	Y	Y	-	-	-	-
P/FLAG	Y	Y	Y	Y	Y	Y	-	-	-
FORTLIB	-	-	-	-	-	-	-	Y	-
FORTLOAD	-	-	-	-	-	Y	-	-	-
GRAPHIC	-	Y	-	-	-	-	-	-	-
HOST	Y	Y	Y	*	-	Y	-	Y	Y
P/IMSBMP	-	-	-	Y	Y	-	-	-	-
P/IMSMPP	-	-	-	Y	Y	-	-	-	-
IMSPRE	-	-	-	-	-	-	-	Y	-
INPUT	Y	Y	*	*	-	Y	-	Y	Y
P/ISOLATION	-	-	-	Y	Y	-	-	-	-
P/KEEPDYNAMIC	-	-	-	Y	Y	-	-	-	-
LINECOUNT	Y	Y	Y	-	-	Y	-	-	-
LINK	-	-	-	-	-	-	-	Y	-
LLIB	-	-	-	-	-	-	-	Y	-
LnLIB	-	-	-	-	-	-	-	Y	-
LOAD	-	-	-	-	-	-	-	Y	Y
LOPTION	-	-	-	-	-	-	-	Y	-
MACRO	Y	-	Y	-	-	-	-	-	-
NOFOR	Y	-	-	-	-	-	-	-	-
P/NODEFER	-	-	-	Y	Y	-	-	-	-
P/OPTHINT	-	-	-	Y	Y	-	-	-	-
OPTIONS	-	Y	Y	-	-	-	-	Y	Y
OUTNAME	Y	Y	-	-	-	Y	-	Y	Y
P/OWNER	-	-	-	Y	Y	-	-	-	-
PACKAGE	-	-	-	-	Y	-	-	-	-
PARMS	-	-	-	-	-	-	-	-	Y
PASS	-	Y	-	-	-	-	-	-	-
P/PATH	-	-	-	Y	Y	-	-	-	-
PCLOAD	-	Y	-	-	-	-	-	-	-
PKLIST	-	-	-	Y	-	-	-	-	-
PLAN	-	-	-	Y	-	-	-	-	Y
PLIB	-	Y	-	-	-	-	-	-	-
PnLIB	-	Y	-	-	-	-	-	-	-
PLI2LIB	-	-	-	-	-	-	-	Y	-
PLILIB	-	-	-	-	-	-	-	Y	-
PLILOAD	Y	-	-	-	-	Y	-	-	-
POPTION	-	-	-	-	-	-	Y	-	-
PRECOMP	-	Y	-	-	-	-	-	-	-
PRELINK	-	-	-	-	-	-	Y	-	-
PRINT	Y	Y	Y	-	-	Y	-	Y	-
PSECSPAC	Y	Y	Y	-	-	Y	-	-	Y
PSPACE	Y	Y	Y	-	-	Y	-	-	Y
P/QUALIFIER	-	-	-	Y	Y	-	-	-	-
RCTERM	Y	Y	Y	Y	Y	Y	Y	-	Y
P/RELEASE	-	-	-	Y	Y	-	-	-	-
REMOTE	-	-	-	-	Y	-	-	-	-
P/REOPT	-	-	-	Y	Y	-	-	-	-
REPLVER	-	-	-	-	Y	-	-	-	-
RETAIN	-	-	-	Y	-	-	-	-	-

Table 18. Summary of DSNH CLIST parameters (continued)

OPTIONS	MP	PC	TR	BI	BP	CO	PL	LE	RU
RUN	-	Y	Y	-	-	-	-	Y	Y
RUNIN	-	-	-	-	-	-	-	-	Y
RUNOUT	-	-	-	-	-	-	-	-	Y
SOMDLLI	-	-	-	-	-	Y	Y	-	-
SOURCE	Y	Y	Y	-	-	Y	-	-	-
SPACEUN	Y	Y	Y	-	-	Y	-	-	Y
SQL	-	Y	-	-	-	-	-	-	-
SQLDELIM	-	Y	-	-	-	-	-	-	-
SQLERROR	-	-	-	-	Y	-	-	-	-
SQLFLAG	-	Y	-	-	-	-	-	-	-
SQLRULES	-	-	-	Y	-	-	-	-	-
STDSQL	-	Y	-	-	-	-	-	-	-
SUFFIX	Y	Y	-	-	-	-	-	-	-
SYSTEM	-	-	-	*	*	-	-	-	Y
TERM	Y	Y	-	-	-	Y	-	Y	-
TIME	-	Y	-	-	-	-	-	-	-
P/VALIDATE	-	-	-	Y	Y	-	-	-	-
VERSION	-	Y	-	-	-	-	-	-	-
WORKUNIT	Y	Y	Y	-	-	Y	-	-	-
WSECSPAC	Y	Y	Y	-	-	Y	-	-	-
WSPACE	Y	Y	Y	-	-	Y	-	-	-
XLIB	-	-	-	-	-	-	-	Y	-
XREF	Y	Y	-	-	-	Y	-	Y	-

General parameter descriptions

Due to similarities in name and function, the CLIST parameters for BIND PLAN and BIND PACKAGE are described separately from the parameters in Table 19. For a summary of:

- BIND PLAN parameters, see Table 20 on page 207
- BIND PACKAGE parameters, see Table 21 on page 210.

Also see “DSNH/DSN subcommand summary” on page 207 for a description of conventions used in those tables.

The only parameter required on the DSNH statement is INPUT; the others are optional. In the table of general parameters that follow:

- Parameter values must be enclosed between parentheses.
- Parameter values need not be enclosed between apostrophes. However,
 - If the value is a list of tokens with separators, it must be enclosed between apostrophes.
 - If the value is a data set name, your user identifier is prefixed to it. To avoid the prefix, enclose the name between sets of three apostrophes.
- Most parameter values that are data set names (*dsname*) cannot include member names. Exceptions are noted in the parameter descriptions.
- Underlined values are defaults. Default names can be changed to names specific to your site when DB2 is installed.

DSNH (TSO CLIST)

Table 19. General DSNH CLIST parameters

DSNH CLIST		
Parameter	Value	Comments
ASMLIB	<i>dsname</i>	Specifies a data set to be used as the standard MACLIB for High Level Assembler/MVS. The default is “SYS1.MACLIB”.
ASMLOAD	<i>dsname</i>	Specifies a data set that contains the High Level Assembler/MVS load module. <i>dsname</i> can include a member name. The default is “SYS1.LINKLIB(ASMA90)”.
CCLINK	<i>dsname</i>	Specifies a data set that contains the C compiler prelink utility invocation load module. <i>dsname</i> can include a member name. The default for HOST(C) is “CEE.V1R3M0.SCEERUN(EDCPRLK)”. The default for HOST(CPP) is “CEE.V1R4M0.SCEERUN(EDCPRLK)”.
CCLLIB	<i>dsname</i>	Specifies the data set that contains the linkage editor include modules for the C compiler routines. The default for HOST(C) is “CEE.V1R3M0.SCEELKED”. The default for HOST(CPP) is “CEE.V1R4M0.SCEELKED”.
CCLOAD	<i>dsname</i>	Specifies a data set that contains the C compiler invocation load module. <i>dsname</i> can include a member name. The default for HOST(C) is “EDC.V1R2M0.SEDCDCMP(EDCDC120)”. The default for HOST(CPP) is “CBC.V3R1M0.SCBC3CMP(CBC310)”.
CCMSGs	<i>dsname</i>	Specifies a data set that contains the C compiler messages. <i>dsname</i> can include a member name. The default for HOST(C) is “EDC.V1R2M0.SEDCDMSG(EDCMSGE)”. The default for HOST(CPP) is “CBC.V3R1M0.SCBC3MSG(EDCMSGE)”.
CCOLIB	<u>NONE</u> <i>dsname</i>	Specifies the data set that contains C object modules to be included during the execution of the prelink utility step.
CCPLIB	<u>NONE</u> <i>dsname</i>	Specifies the data set containing include modules for PLI routines. This parameter is used only for IBM C/370 Version 2 or earlier.
CCPMSGs	<i>dsname</i>	Specifies the data set containing prelink utility error messages. The default for HOST(C) is “CEE.V1R3M0.SCEEMSGP(EDCPMSGGE)”. The default for HOST(CPP) is “CEE.V1R4M0.SCEEMSGP(EDCPMSGGE)”.
CCSLIB	<i>dsname</i>	Specifies the data set that contains the C compiler headers. The default for HOST(C) is “EDC.V1R2M0.SEDCDHDR”. The default for HOST(CPP) is “CBC.V1R4M0.SCEEH.H”.

Table 19. General DSNH CLIST parameters (continued)

DSNH CLIST												
Parameter	Value	Comments										
CICSOPT	<u>NONE</u> <i>option-list</i>	Gives a list of additional CICS translator options. See the appropriate CICS application programming reference for information about translator options. NONE gives no additional options.										
CICSPRE	<i>prefix</i>	Gives the prefix for the CICS libraries. The library names are: <i>prefix</i> .LOADLIB for translators <i>prefix</i> .PL1LIBn for PL/I include <i>prefix</i> .COBLIB for COBOL include Leave this parameter blank to use CICSLLIB, CICSPLIB, CICSCOB. The default is blank.										
CICSLLIB	<i>dsname</i>	Specifies the CICS load library. To use this library, leave the CICSPRE parameter blank. The default is set on install panel DSNTIP3.										
CICSPLIB	<i>dsname</i>	Specifies the CICS PL/I library. To use this library, leave the CICSPRE parameter blank. The default is set on install panel DSNTIP3.										
CICSCOB	<i>dsname</i>	Specifies the CICS COBOL library. To use this library, leave the CICSPRE parameter blank. The default is set on install panel DSNTIP3.										
CICSVER	21 31 <u>33</u> 41	Specifies the CICS release, as follows: <table><tr><th>Value</th><th>CICS Release</th></tr><tr><td>21</td><td>Using CICS/MVS 2.1.2.</td></tr><tr><td>31</td><td>Using CICS/ESA 3.1.1.</td></tr><tr><td>33</td><td>Using CICS/ESA 3.2.1 or 3.3.0.</td></tr><tr><td>41</td><td>Using CICS/ESA Version 4</td></tr></table> The default is 33.	Value	CICS Release	21	Using CICS/MVS 2.1.2.	31	Using CICS/ESA 3.1.1.	33	Using CICS/ESA 3.2.1 or 3.3.0.	41	Using CICS/ESA Version 4
Value	CICS Release											
21	Using CICS/MVS 2.1.2.											
31	Using CICS/ESA 3.1.1.											
33	Using CICS/ESA 3.2.1 or 3.3.0.											
41	Using CICS/ESA Version 4											
CICSXLAT	NO YES	Tells whether to execute the CICS command translator. The option is effective only if you use RUN(CICS). You cannot use the option with the MARGINS option of the translator. The default is YES. The DB2I panel default is NO.										
CLIB <i>CnLIB</i>	<u>NONE</u> <i>dsname</i>	Specifies a data set that contains host language source statements to be included by the compiler or assembler. The parameters <i>CnLIB</i> (where <i>n</i> can be 2, 3, or 4) are extensions of CLIB, used to simplify passing a list of data set names. Use NONE to specify no data set.										
COBICOMP	<i>dsname</i>	Specifies the IBM COBOL data set required for compilation. The default is “‘IGY.V1R2M0.SIGYCOMP’”.										
COBILINK	<i>dsname</i>	Specifies the IBM COBOL data set required for link edit. The default is “‘CEE.V1R5M0.SCEELKED’”.										
COBIPLNK	<i>dsname</i>	Specifies the IBM COBOL data set required for prelink routines. The default is “‘CEE.V1R5M0.SCEERUN’”.										

DSNH (TSO CLIST)

Table 19. General DSNH CLIST parameters (continued)

DSNH CLIST		
Parameter	Value	Comments
COBIPMSG	<i>dsname</i>	Specifies the IBM COBOL data set required for prelink messages. The default is “CEE.V1R5M0.SCEEMSGP(EDCPMSGGE)”.
COBLIB	<i>dsname</i>	Specifies the linkage editor include library to be used for OS/VS COBOL routines. The default is “SYS1.COBLIB”.
COBLOAD	<i>dsname</i>	Specifies a data set that contains the OS/VS COBOL compiler load module. <i>dsname</i> can include a member name. The default is “SYS1.LINKLIB(IKFCBL00)”.
COBSOM	<i>dsname</i>	Specifies the IBM System Object Model (SOM) data set required for access to SOM objects. The default is “SOMMVS.V1R1M0.SGOSPLKD”.
COB2CICS	<i>dsname</i>	Specifies the linkage editor include library to be used for VS COBOL II CICS routines. The default is “SYS1.COB2CICS”.
COB2LIB	<i>dsname</i>	Specifies the linkage editor include library to be used for the VS COBOL II or COBOL/370 routines. The default is “SYS1.V1R3.COB2LIB”.
COB2LOAD	<i>dsname</i>	Specifies a data set that contains the VS COBOL II or COBOL/370 compiler load module. <i>dsname</i> can include a member name. The default is “SYS1.V1R3.COB2COMP(IGYCRCTL)”.
COMPILE	YES NO	Tells whether to execute the compiler or assembler if the precompile step is successful.
CONNECT	(1) (2)	Specifies whether a CONNECT SQL statement should be processed as a type 1 CONNECT or a type 2 CONNECT statement. The DSNH(TSO CLIST) command does not accept the CT(1) and CT(2) abbreviations for this precompiler option. The default is CONNECT(2).
CONTROL	NONE CONLIST LIST SYMLIST	CONTROL helps you trace the allocation of non-existent data sets. Use CONTROL if you have a problem without an obvious cause. CONLIST displays CLIST commands after substitution for symbols and before command execution. LIST displays TSO commands after substitution for symbols and before command execution. SYMLIST displays all executable statements (TSO commands and CLIST statements) before substitution for symbols.

Table 19. General DSNH CLIST parameters (continued)

DSNH CLIST		
Parameter	Value	Comments
COPTION	<u>NONE</u> <i>string</i>	Gives a list of compiler or assembler options. For more information, see the manual that describes the compiler or assembler options for the specific language you are using. For a list of restrictions on some options, see “COBOL Options” on page 213. NONE gives no options.
CPPCLASS	<i>dsname</i>	Specifies the data set containing C++ class libraries. The default is “CBC.V3R1M0.SCLB3CPP”.
CPPCLINK	<i>dsname</i>	Specifies the data set containing prelink utility modules used by the C++ compiler. The default is “CEE.V1R4M0.SCEERUN(EDCPRLK)”.
CPPCLLIB	<i>dsname</i>	Specifies the data set for C linkage editor automatic call library used by the C++ compiler. The default is “CEE.V1R4M0.SCEELKED”.
CPPCSLIB	<i>dsname</i>	Specifies data set containing the C compiler headers used by the C++ compiler. The default is “CBC.V1R4M0.SCEEH.H”.
CPPLLIB	<i>dsname</i>	Specifies the data set containing the C++ prelink automatic call library. The default is “CEE.V1R4M0.SCEECPP”.
CPPPMMSG	<i>dsname</i>	Specifies the data set containing prelink utility error messages used by the C++ compiler. The default is “CEE.V1R4M0.SCEEMSGP(EDCPMSGP)”.
CPPSLIB	<i>dsname</i>	Specifies the data set containing C++ header files for class libraries. The default is “CBC.V3R1M0.SCLB3H.H”.
CPPUTIL	<i>dsname</i>	Specifies the data set containing procedures to set up and execute the C++ compiler. The default is “CBC.V3R1M1.SCBC3UTL”.
DATE	ISO JIS USA EUR LOCAL	Specifies the format of date values that are to be returned overriding the format specified as the location default. The default is the value supplied when DB2 was installed, and is written in the data-only load module, DSNHDECP.

DSNH (TSO CLIST)

Table 19. General DSNH CLIST parameters (continued)

DSNH CLIST		
Parameter	Value	Comments
DBRMLIB	DEFAULT	<p>Specifies the partitioned data set, and optionally a member name, that contains the DBRM library and member name used during the DB2 precompile step. Because you can specify an individual DBRM member and library names during each individual phase, you must use the DBRMLIB parameter and associated prefixes to identify a specific phase. DBRMLIB specifies the DBRM library and member defined on the DBRMLIB DD statement during DB2 precompiler processing.</p> <p>DEFAULT indicates that the same DBRM library data set defined for the DB2 precompiler process (DBRMLIB(<i>parameter</i>)) is also used on the LIBRARY(<i>dsname</i>) subcommand keyword. If the precompiler DBRMLIB was not specified, then the default generated DBRMLIB library based upon the INPUT data set name is used.</p> <p><i>dsname</i> is generated using the DSNH OUTNAME parameter value, or its default TEMP, with the constant DBRM appended to the prefix; for example, <i>outname</i>.DBRM or TEMP.DBRM.</p> <p><i>member</i> is obtained from the data set member name specified on the DSNH INPUT parameter, or from the data set name as follows:</p> <p>Given INPUT(<i>outname</i>.DBRM(<i>dbrmmem</i>)):</p> <ul style="list-style-type: none"> – <i>outname</i>.DBRM(<i>dbrmmem</i>) - If member name is specified – <i>outname</i>.DBRM(<i>dbrm</i>) - If no member name is specified <p>NONE indicates that no LIBRARY(<i>dsname</i>) subcommand keyword is specified on invocation.</p>
	<i>dsname(member)</i>	
	NONE	
DECARTH	DEFAULT	<p>Sets the maximum precision of decimal numbers.</p> <p>DEFAULT designates the value chosen, during installation, for the DECIMAL ARITHMETIC field on the APPLICATION PROGRAMMING DEFAULTS panel.</p> <p>15 specifies that decimal arithmetic operations on decimal values with precision 15 or less are performed in accordance with the existing rules for determining the precision and scale of the result.</p> <p>31 specifies that decimal arithmetic operations on decimal values with precision 15 to 31 are performed in accordance with new rules for determining the precision and scale of the result.</p> <p>DECARTH is ignored for Fortran.</p>
	15	
	31	
DECIMAL	COMMA	<p>Gives the decimal point indicator for decimal and floating point literals. DECIMAL is valid only for COBOL programs; PERIOD is forced for all other programs.</p> <p>COMMA makes the indicator a comma.</p> <p>PERIOD makes the indicator a period.</p> <p>The default is the value of the DECIMAL POINT field, set on the DB2 APPLICATION PROGRAMMING DEFAULTS panel during installation.</p>
	PERIOD	

Table 19. General DSNH CLIST parameters (continued)

DSNH CLIST		
Parameter	Value	Comments
DELIMIT	DEFAULT APOST QUOTE	<p>Sets the APOST or QUOTE precompiler option to indicate the string delimiter used within host language statements. DELIMIT is effective only for COBOL programs; APOST is forced for all other programs.</p> <p>DEFAULT designates the value chosen, during installation, for the STRING DELIMITER field on the APPLICATION PROGRAMMING DEFAULTS panel.</p> <p>APOST specifies the apostrophe as the string delimiter for host language statements.</p> <p>QUOTE specifies a quotation mark as the string delimiter for host language statements.</p>
ENTRY	<i>entry-name</i>	<p>Specifies the entry point assigned by the linkage editor.</p> <p>The default depends on the host language and the value of RUN.</p> <ul style="list-style-type: none"> For the PL/I language, the ENTRY value default is: <ul style="list-style-type: none"> NONE if the RUN value is CICS PLISTART for any other RUN value. For the ASM language, the ENTRY value default is DLITASM if the RUN value is IMS. For COBOL, the ENTRY value default is DLITCBL if the RUN value is IMS. For any other language, the ENTRY value default is NONE (no specified entry point) for any RUN value.
FLAG	I C E W	<p>Tells what messages you want to see. Use one of the values listed to show messages of the corresponding types:</p> <ul style="list-style-type: none"> I All informational, warning, error, and completion messages W Only warning, error, and completion messages E Only error and completion messages C Only completion messages
FORTLIB	<i>dsname</i>	<p>Specifies the linkage editor include library to be used for Fortran routines.</p> <p>The default is “SYS1.VSF2FORT”.</p>
FORTLOAD	<i>dsname</i>	<p>Specifies a data set that contains the VS Fortran compiler load module. <i>dsname</i> can include a member name.</p> <p>The default is “SYS1.VSF2VCOMP(FORTVS2)”.</p>
GRAPHIC	NONE NO YES	<p>Specifies the value of the DSNHDECP MIXED option for the precompiler.</p> <p>NONE indicates that the default specified during install is used.</p> <p>NO indicates that the data is not mixed DBCS.</p> <p>YES indicates that all character data can be mixed DBCS.</p> <p>GRAPHIC is ignored for C.</p>

DSNH (TSO CLIST)

Table 19. General DSNH CLIST parameters (continued)

DSNH CLIST		
Parameter	Value	Comments
HOST	ASM	Defines the host language within which SQL statements are embedded.
	C CPP COBOL COB2 IBMCOB FORTRAN PLI	<p>If your program fits one of the following descriptions, you cannot use DB2I to prepare it:</p> <ul style="list-style-type: none"> An IBM COBOL for MVS & VM program that uses object-oriented extensions A C++ program that uses object-oriented extensions and consists of more than one compilation unit <p>The default is the value of the LANGUAGE DEFAULT field, set on the DB2 APPLICATION PROGRAMMING DEFAULTS panel during installation.</p>
IMSPRE	<i>prefix</i>	<p>Sets the prefix for RESLIB, used for routines to be included by the linkage editor for IMS.</p> <p>The default is IMSVS.</p>
INPUT	<i>dsname</i>	<p>Specifies the data set that contains the host language source and SQL statements.</p> <p><i>dsname</i> can include a member name.</p>
LINECOUNT	<i>integer</i>	<p>Tells how many lines, including headings, are to be printed on each page of printed output.</p> <p>The default is 60.</p>
LINK	<u>YES</u> NO	<p>Tells whether to execute the linkage editor upon successful completion of compilation or assembly.</p> <p>YES indicates that the linkage editor is to be executed. The DSNHLI entry point from the precompiler is directed to the appropriate language interface module specified by the RUN parameter.</p> <p>NO indicates that linkage editor processing is to be bypassed.</p>
LLIB LnLIB	NONE <i>dsname</i>	<p>Specifies a data set that contains object or load modules to be included by the linkage editor. The parameters LnLIB (where <i>n</i> can be 2, 3, or 4) are extensions of LLIB, used to simplify passing a list of data set names.</p> <p>The LLIB and LnLIB libraries are concatenated with the XLIB library and the linkage editor include libraries for the specific host language. Object and load module libraries must not be mixed in this concatenation.</p> <p>Use NONE to specify no data set.</p>
LOAD	<i>dsname</i>	<p>Specifies a data set that is to contain the output from the linkage editor (the load module).</p> <p><i>dsname</i> can include a member name.</p> <p>The default is RUNLIB.LOAD.</p>
LOPTION	<u>NONE</u> <i>string</i>	<p>Gives a list of linkage editor options. For information on options you can use, see the appropriate MVS/ESA publication.</p> <p>Use NONE to give no options.</p>

Table 19. General DSNH CLIST parameters (continued)

DSNH CLIST		
Parameter	Value	Comments
MACRO	YES	Tells whether the macro preprocessor is to be executed before the precompilation of a PL/I program. If the PL/I macro processor is used, the PL/I *PROCESS statement must not be used to pass options to the PL/I compiler. The COPTION parameter of the DSNH command can be used to pass the needed options to the PL/I compiler.
	NO	
NOFOR	NO	Allows elimination of all FOR UPDATE OF clauses in static SQL.
	YES	When NOFOR is in effect, the FOR UPDATE OF clause is optional. Positioned updates can be made to any columns that the user has authority to update.
		When NOFOR is not in effect, any query appearing in a DECLARE CURSOR statement must contain a FOR UPDATE OF clause if the cursor is used for positional updates. The clause must designate all the columns that the cursor can update.
		The option is implied when the STDSQL(YES) option is in effect.
OPTIONS	NO	Tells whether to print the options used when executing the precompiler or the CICS command translator with the output listing.
	YES	
OUTNAME	TEMP	Gives a prefix used to form intermediate data set names.
	string	
PARMS	NONE	Gives a parameter string to be passed to the compiled program during its execution; the run time execution environment requested is TSO. If CAF is specified as the run time execution environment, this parameter is ignored.
	string	
PASS		Use NONE to pass no parameter string.
	ONE or 1	Tells how many passes the precompiler is to use. One pass saves processing time, but requires that declarations of host variables in the program precede any reference to those variables. PASS has no effect for COBOL or Fortran; ONE is forced.
	TWO or 2	
PCLOAD		The default is ONE or 1 for PL/I and C.
		The default is TWO or 2 for assembler.
	dsname	Specifies the precompiler load module.
PLAN		dsname can include a member name.
		The default is “prefix.SDSNLOAD(DSNHPC)”.
	plan-name	Specifies the application plan created by the bind process.
		The default plan name is the first of the following available choices defined in the INPUT data set:
		• DBRM member name
		• Leftmost qualifier
		plan-name must not be DEFAULT.
		If no name is found, a plan is not created.

DSNH (TSO CLIST)

Table 19. General DSNH CLIST parameters (continued)

DSNH CLIST		
Parameter	Value	Comments
PLIB PnLIB	<u>NONE</u> <i>dsname</i>	Specifies the data set that contains host language source or SQL statements included by the SQL INCLUDE statement during precompilation. The parameters PnLIB (where <i>n</i> can be 2, 3, or 4) are extensions of PLIB, used to simplify passing a list of data set names. Use NONE to specify no data set.
PLI2LIB	<i>dsname</i>	Specifies the linkage editor common library used for PL/I routines. The default is “SYS1.SIBMBASE”.
PLILIB	<i>dsname</i>	Specifies the linkage editor base library used for PL/I routines. The default is “SYS1.PLIBASE”.
PLILOAD	<i>dsname</i>	Specifies a data set that contains the PL/I optimizing compiler load module. <i>dsname</i> can include a member name. The default is “SYS1.LINKLIB(IELOAA)”.
POPTION	<u>NONE</u> <i>string</i>	Gives a list of the C compiler language prelink utility options. For information on the options provided, refer to the <i>IBM SAA AD/Cycle C/370 User's Guide</i> . Use NONE to give no options.
PRECOMP	<u>YES</u> <u>NO</u>	Tells whether to precompile.
PRELINK	<u>YES</u> <u>NO</u>	Tells whether to execute the C compiler prelink utility to make your program reentrant. This utility concatenates compile-time initialization information (for writable static) from one or more text decks into a single initialization unit. If this step is requested, it must follow the compile step and precede the link-edit step. This parameter can apply to IBMCOB that also has a prelink step. Whether the prelink step applies to C or IBMCOB is determined by the choice of values C, CPP, or IBMCOB for the HOST parameter. Descriptions of the prelink process for C and IBMCOB are presented in their respective language publications. If PRELINK(YES) is specified or defaulted for a HOST language compiler that does not support the prelink utility, DB2 will issue warning message DSNH760I and prelink utility processing will be bypassed.

Table 19. General DSNH CLIST parameters (continued)

DSNH CLIST		
Parameter	Value	Comments
PRINT	NONE	<p>Tells where to send printed output, including the lists of options, source, cross-reference, error, and summary information.</p> <p>NONE omits printed output.</p> <p><i>dsname</i> specifies a data set to be used for the output. Do not enclose <i>dsname</i> between apostrophes. The current user profile is prefixed to <i>dsname</i>. The following suffixes are also added:</p> <ul style="list-style-type: none"> • SYSCPRT.LIST for PL/I macro listings (these listings are overwritten by the compiler listings) • PCLIST for precompiler listings • CXLIST for CICS command translator listings • LIST for compiler listings <p>The PRINT parameter is ignored for the compile step when HOST(CPP) is specified.</p> <ul style="list-style-type: none"> • SYSOUT.PRELLIST for C prelink utility listings • LINKLIST for link-edit listings <p>LEAVE sends output to the specified print data set. You can allocate the print data set:</p> <ul style="list-style-type: none"> • Dynamically • In the JCL used to run the DSNH CLIST (if in batch mode) • With the TSO ALLOCATE command (before running DSNH) <p>TERM sends output to the terminal.</p>
	<i>dsname</i>	
	LEAVE	
	TERM	
PSECSPAC	<i>integer</i>	<p>Tells the amount of secondary space to allocate for print data sets, in the units given by SPACEUN.</p> <p>The default is 20.</p>
PSPACE	<i>integer</i>	<p>Tells the primary size of the print data sets in the units given by SPACEUN.</p> <p>The default is 20.</p>
RCTERM	<i>integer</i>	<p>Gives the least value of the return code from the precompile step that prevents execution of later steps.</p> <p>The default is 8.</p>

DSNH (TSO CLIST)

Table 19. General DSNH CLIST parameters (continued)

DSNH CLIST		
Parameter	Value	Comments
RUN	TSO or YES	Tells whether to execute the compiled program if the previous steps are successful, and, if so, in which environment it executes. Your choice for the RUN parameter might affect your choice for LLIB.
	BATCH or NO	
	CAF	
	CICS	
	IMS	
	RRSAF	
		TSO or YES indicate that the application program is to be scheduled for execution in the TSO environment, and execute the compiled program.
		BATCH or NO indicate that the application program is not to be scheduled for execution, and default to TSO as the execution environment.
		CAF indicates that the application program is to be scheduled for execution in the call attachment facility environment. Specify BATCH or NO with CAF to indicate that the application program is not to be scheduled for execution, but to identify CAF as the execution environment. (BATCH,CAF) or (NO,CAF)
		CICS indicates that the application program is not to be scheduled for execution, and identifies CICS as the RUN time execution environment. (CICS applications cannot run in TSO.)
		IMS indicates that the application program is not to be scheduled for execution, and identifies IMS as the RUN time execution environment. (IMS applications cannot run in TSO.)
		RRSAF indicates that the application program is not to be scheduled for execution, and identifies RRSF as the RUN time execution environment. (RRSAF applications cannot run in TSO.)
RUNIN	TERM	Tells where to get input for the RUN step.
	<i>dsname</i>	
	LEAVE	
	NONE	
		TERM gets input from the terminal.
		<i>dsname</i> specifies a data set to be used for the input.
		LEAVE gets input from SYSIN if the only steps taken are LINK and RUN. LEAVE gets input from FT05F001 if the language is Fortran. Do not use LEAVE for any other cases.
		NONE allocates no input file.
RUNOUT	TERM	Tells where to send output from the RUN step.
	<i>dsname</i>	
	LEAVE	
	NONE	
		TERM sends output to the terminal.
		<i>dsname</i> specifies a data set to receive output.
		LEAVE sends output to SYSPRINT if the only steps taken are LINK and RUN. LEAVE sends output to FT06F001 if the language is Fortran. Do not use LEAVE for any other cases.
		NONE allocates no output file for the RUN step.
SOMDLLI	<i>dsname</i>	Tells the name to be passed of the SOM/MVS DLL import library.
		The default is “SOM.SGOSIMP”.
SOURCE	NO	Tells whether the source code and diagnostics are to be printed with output from the precompiler, CICS command translator, and compiler.
	YES	

Table 19. General DSNH CLIST parameters (continued)

DSNH CLIST		
Parameter	Value	Comments
SPACEUN	TRACK	Specifies the unit of space for PSPACE and WSPACE.
	CYLINDER	TRACK makes the space unit one track.
		CYLINDER makes the space unit one cylinder.
SQL	DB2	Interprets SQL statements and checks syntax for use by either DB2 for OS/390 and z/OS or other database management systems.
	ALL	DB2 indicates that SQL statements are to be interpreted and syntax is to be checked for use by DB2. SQL(DB2) is the recommended mode for DRDA access when the server is a DB2 subsystem.
		ALL indicates that SQL statements are to be interpreted for use by database management systems that are not DB2 for OS/390 and z/OS. SQL syntax checking is deferred until bind time so that the remote location can bind the resulting DBRM. When SQL(ALL) is in effect, the precompiler issues an informational message if SAA reserved words are used as identifiers. SQL(ALL) is the recommended mode if you have written your application to be executed in a environment that is not DB2 for OS/390 and z/OS.
		The default is SQL(DB2).
SQLDELIM	DEFAULT	Sets the APOSTSQL or QUOTESQL precompiler option, to specify the SQL string delimiter and, by implication, the SQL escape character within SQL statements. Whichever character is chosen to be the string delimiter, the other is used for the SQL escape character.
	APOSTSQL	This parameter is effective only for COBOL. For PL/I, Fortran, and assembler language programs, the precompiler forces the APOSTSQL option.
	QUOTESQL	DEFAULT designates the value chosen, during installation, for the SQL STRING DELIMITER field on the APPLICATION PROGRAMMING DEFAULTS panel.
		APOSTSQL specifies that the string delimiter is the apostrophe (') and the escape character is the quotation mark (").
		QUOTESQL specifies that the string delimiter is the quotation mark (") and the escape character is the apostrophe (').
SQLFLAG	IBM or SAA	Specifies the standard to be used to check the syntax of SQL statements. Deviations from the standard are flagged by informational messages written to the precompiler output listing.
	STD or 86	IBM or SAA requests the use of the IBM SQL Version 2 syntax.
	<i>ssname</i>	STD or 86 requests the use of the SQL92 Entry Level syntax.
	<i>qualifier</i>	<i>ssname</i> requests full semantics checking for catalog access using the specified DB2 subsystem name. If <i>ssname</i> is not specified, only syntax checking is performed.
		<i>qualifier</i> specifies the qualifier to be used for unqualified object names. If <i>qualifier</i> is specified, <i>ssname</i> must always be specified first. If <i>qualifier</i> is not specified, the default is the authorization ID of the process that executed the precompiler.

DSNH (TSO CLIST)

Table 19. General DSNH CLIST parameters (continued)

DSNH CLIST		
Parameter	Value	Comments
STDSQL	NO YES or 86	Interprets SQL using a subset of ANSI rules.
		NO specifies that DB2 rules are used.
		YES or 86 automatically implies that the NOFOR option is used.
SUFFIX	YES NO	Tells whether the TSO standard naming convention must be followed. That convention adds a TSO authorization ID prefix and a host language suffix to the name of the input data set (unless that name is enclosed between apostrophes, or already ends in the appropriate suffix). For example, names become <i>userid.name.COBOL</i> , <i>userid.name.PLI</i> , <i>userid.name.Fortran</i> , or <i>userid.name.ASM</i> .
SYSTEM	<i>subsystem-name</i>	Gives the DB2 subsystem name as it is known to MVS. The default is the installation-defined subsystem name (often DSN).
TERM	TERM <i>dsname</i> LEAVE NONE	Tells where to send terminal output, including error information, error statements, and summary information.
		TERM sends output to the terminal. <i>dsname</i> specifies a data set to be used for terminal output. Do not enclose <i>dsname</i> between apostrophes. The following suffixes are added to <i>dsname</i> : <ul style="list-style-type: none"> • PCTERM for precompiler output • LIST for compiler output
		LEAVE sends the output to the current allocation for SYSTERM. NONE omits terminal output.
TIME	ISO JIS USA EUR LOCAL	Specifies the format for time values that are to be returned, overriding the format specified as the location default.
		There is no default , because this option overrides the default previously specified.
VERSION	<i>version-id</i> AUTO	Specifies the name of the version ID for the program and associated DBRM during the DB2 precompile.
		AUTO specifies that the consistency token is used to generate the version ID. If the consistency token is a timestamp, the timestamp is converted into ISO character format and used as the version identifier.
		The default is no version ID if specified at precompiler invocation.
WORKUNIT	<i>unit</i>	Tells what device to use for print and work data sets.
		<i>unit</i> can be a unit name or a device type.
		The default in batch mode is any eligible device.
		The default in any other mode is the UADS unit name for the current TSO user.
WSECSPAC	<i>integer</i>	Tells the amount of secondary space to allocate for work data sets, in the units given by SPACEUN.
		The default is 20.
WSPACE	<i>integer</i>	Tells the primary size of the work data sets in the units given by SPACEUN.
		The default is 20.

Table 19. General DSNH CLIST parameters (continued)

DSNH CLIST		
Parameter	Value	Comments
XLIB	<i>dsname</i>	Specifies the linkage editor include library to be used for DB2 routines. The default is “ <i>prefix.SDSNLOAD</i> ”.
XREF	NO YES	Tells whether a sorted cross-reference listing of symbolic names used in source statements is to be printed with output from the precompiler.

DSNH/DSN subcommand summary

The following tables differentiate the functions that support BIND PLAN and BIND PACKAGE. Each table associates the DSNH CLIST parameter and its corresponding DSN BIND PLAN or BIND PACKAGE subcommand keyword, if any. In general:

- The function and value of a CLIST parameter is identical to that of its corresponding DSN subcommand keyword unless otherwise noted.
- A DSNH parameter value of NONE indicates that the corresponding DSN keyword is not specified on subcommand invocation. Exceptions are noted where applicable.

DSNH CLIST/BIND PLAN subcommand comparison

Table 20. DSNH CLIST/ BIND PLAN subcommand summary

DSNH CLIST		BIND PLAN subcommand		Comments
Parameter	Value	Keyword	Value	
ACQUIRE	USE ALLOCATE	ACQUIRE	USE ALLOCATE	
ACTION	REPLACE ADD	ACTION	REPLACE ADD	
BDMEM	DEFAULT ¹ <i>dbrm-member-name</i> NONE ²	MEMBER	<i>dbrm-member-name</i>	¹ DBRM member name obtained from one of the following sources, in the order listed: <ul style="list-style-type: none"> • BDBRMLIB member name • DBRMLIB member name • INPUT member name, or generated using <i>dsname</i>. ² Keyword is not specified on subcommand invocation.
BIND	YES ¹ NO ²	(<i>command-verb</i>)		¹ Execute BIND PLAN subcommand. ² Do not execute BIND PLAN subcommand.
BLIB	NONE ¹ <i>dsname</i>	LIBRARY	<i>dbrm-pds-name</i>	¹ Keyword is not specified on subcommand invocation.

DSNH (TSO CLIST)

Table 20. DSNH CLIST/ BIND PLAN subcommand summary (continued)

DSNH CLIST		BIND PLAN subcommand		Comments
Parameter	Value	Keyword	Value	
BnLIB ¹	NONE ² <i>dsname</i>	LIBRARY	<i>list of dbrm-pds-names</i>	¹ <i>n</i> can be 2, 3, 4, 5, 6, 7, or 8. Specify the first data set name using the BLIB parameter and any additional data set names using this parameter. ² No additional data set names.
BMEM ¹	NONE ² <i>list of dbrm-member -names</i>	MEMBER	<i>list of dbrm-member- names</i>	¹ Specify the first DBRM member name using the BDMEM parameter and any additional member names individually using this parameter. ² No additional DBRM member names.
CACHESIZE	NONE ¹ <i>decimal-value</i> ²	CACHESIZE	<i>decimal-value</i> ²	¹ The size is provided by the subsystem. ² Specify a size from 0 to 4096 bytes.
CICS	NONE ¹ <i>application-ids</i>	CICS	<i>application-ids</i>	¹ Keyword is not specified on subcommand invocation.
CURRENTDATA	YES NO NONE	CURRENTDATA	YES NO	
CURRENTSERVER	NONE ¹ <i>location-name</i>	CURRENTSERVER	<i>location-name</i>	
DBPROTOCOL	NONE DRDA PRIVATE	DBPROTOCOL	DRDA PRIVATE	
BDBRMLIB	DEFAULT ¹ <i>dsname(member)</i> NONE ²	LIBRARY	<i>dbrm-pds-name</i>	¹ The precompiler DBRMLIB data set is used. If the precompiler DBRMLIB is not specified, then the default-generated DBRMLIB library based upon the INPUT data set is used. ² Keyword is not specified on subcommand invocation.
DEFER	NONE ¹ PREPARE	DEFER	PREPARE	¹ Keyword is not specified on subcommand invocation.
DEGREE	1 ANY	DEGREE	1 ANY	

Table 20. DSNH CLIST/ BIND PLAN subcommand summary (continued)

DSNH CLIST		BIND PLAN subcommand		Comments
Parameter	Value	Keyword	Value	
DISABLE	NONE BATCH CICS DB2CALL IMS DLIBATCH IMSBMP IMSMPP RRSAF	DISABLE	NONE BATCH CICS DB2CALL IMS DLIBATCH IMSBMP IMSMPP RRSAF	
DISCONNECT	EXPLICIT AUTOMATIC CONDITIONAL	DISCONNECT	EXPLICIT AUTOMATIC CONDITIONAL	
DLIBATCH	NONE ¹ <i>list of connection-ids</i>	DLIBATCH	<i>connection-name</i>	¹ Keyword is not specified on subcommand invocation.
DYNAMICRULES	RUN BIND	DYNAMICRULES	RUN BIND	
ENABLE	NONE * BATCH CICS DB2CALL IMS DLIBATCH IMSBMP IMSMPP RRSAF	ENABLE	NONE * BATCH CICS DB2CALL IMS DLIBATCH IMSBMP IMSMPP RRSAF	
EXPLAIN	NO YES	EXPLAIN	NO YES	
FLAG	I C E W	FLAG	I C E W	
IMSBMP	NONE ¹ <i>imsid</i>	IMSBMP	<i>imsid</i>	¹ Keyword is not specified on subcommand invocation.
IMSMPP	NONE ¹ <i>imsid</i>	IMSMPP	<i>imsid</i>	¹ Keyword is not specified on subcommand invocation.
ISOLATION	RR RS CS UR	ISOLATION	RR RS CS UR	
KEEPDYNAMIC	NO YES	KEEPDYNAMIC	NO YES	
NODEFER	NONE ¹ PREPARE	NODEFER	PREPARE	¹ Keyword is not specified on subcommand invocation.
OPTHINT	(' ') (<i>'hint-id'</i>)	OPTHINT	(' ') (<i>'hint-id'</i>)	

DSNH (TSO CLIST)

Table 20. DSNH CLIST/ BIND PLAN subcommand summary (continued)

DSNH CLIST		BIND PLAN subcommand		Comments
Parameter	Value	Keyword	Value	
OWNER	NONE ¹ <i>authorization-id</i>	OWNER	<i>authorization-id</i>	¹ Keyword is not specified on subcommand invocation.
PATH	<i>(schema-name)</i> (USER)(<i>schema-name</i> , USER...)	PATH	<i>(schema-name)</i> (USER)(<i>schema-name</i> , USER...)	
PKLIST	NONE ¹ <i>list of collection-ids and package-names</i>	PKLIST	<i>list of collection-ids and package-names</i>	¹ The package names are not specified on subcommand invocation.
PLAN	<i>plan-name</i> ¹	PLAN (<i>primary-keyword</i>)	<i>plan-name</i>	¹ <i>plan-name</i> must not be DEFAULT. The default <i>plan-name</i> is the first of the following available choices defined in the INPUT data set: <ul style="list-style-type: none"> • DBRM member name • Leftmost qualifier If no name is found, a plan is not created.
QUALIFIER	NONE ¹ <i>implicit-qualifier</i>	QUALIFIER	<i>qualifier-name</i>	¹ Keyword is not specified on subcommand invocation.
RELEASE	COMMIT DEALLOCATE	RELEASE	COMMIT DEALLOCATE	
REOPT	NONE ¹ VARS	NOREOPT REOPT	VARS VARS	¹ Keyword is not specified on subcommand invocation.
RETAIN	NO ¹ YES ²	RETAIN		¹ Keyword is not specified on subcommand invocation. ² Keyword is specified on subcommand invocation.
SQLRULES	DB2 STD	SQLRULES	DB2 STD	
VALIDATE	RUN BIND	VALIDATE	RUN BIND	

DSNH CLIST/BIND PACKAGE subcommand comparison

Table 21. DSNH CLIST/ BIND PACKAGE subcommand summary

DSNH CLIST		BIND PACKAGE subcommand		Comments
Parameter	Value	Keyword	Value	
PACTION	REPLACE ADD	ACTION	REPLACE ADD	
PBIND	NO ¹ YES ²	(<i>command-verb</i>)		¹ Do not execute BIND PACKAGE subcommand. ² Execute BIND PACKAGE subcommand.

Table 21. DSNH CLIST/ BIND PACKAGE subcommand summary (continued)

DSNH CLIST		BIND PACKAGE subcommand		Comments
Parameter	Value	Keyword	Value	
PCICS	NONE ¹ <i>application-ids</i>	CICS	<i>application-ids</i>	¹ Keyword is not specified on subcommand invocation.
COPY	NONE ¹ <i>collection-id.</i> <i>package-id</i>	COPY	<i>collection-id.</i> <i>package-id</i>	¹ Keyword is not specified on subcommand invocation.
COPYVER	<i>version-id</i>	COPYVER	<i>version-id</i>	
PCURRENTDATA	NO YES NONE	CURRENTDATA	YES NO	
PDBPROTOCOL	NONE DRDA PRIVATE	DBPROTOCOL	DRDA PRIVATE	
PDBRMLIB	DEFAULT ¹ <i>dsname(member)</i> NONE ²	LIBRARY	<i>dbrm-pds-name</i>	¹ The precompiler DBRMLIB data set is used. If the precompiler DBRMLIB is not specified, then the default-generated DBRMLIB library based upon the INPUT data set is used. ² Keyword is not specified on subcommand invocation.
PDEFER	NONE ¹ PREPARE	DEFER	PREPARE	¹ Keyword is not specified on subcommand invocation.
PDEGREE	1 ANY	DEGREE	1 ANY	
PDISABLE	NONE BATCH CICS DB2CALL IMS DLIBATCH IMSBMP IMSMPP REMOTE RRSAF	DISABLE	NONE BATCH CICS DB2CALL IMS DLIBATCH IMSBMP IMSMPP REMOTE RRSAF	
PDLIBATCH	NONE ¹ <i>list of</i> <i>connection-ids</i>	DLIBATCH	<i>connection-name</i>	¹ Keyword is not specified on subcommand invocation.
PDMEM	DEFAULT ¹ <i>dbrm-member-name</i> NONE ²	MEMBER	<i>dbrm-member-name</i>	¹ DBRM member name obtained from one of the following sources, in the order listed: <ul style="list-style-type: none"> • PDBRMLIB member name • DBRMLIB member name • INPUT member name, or generated using <i>dsname</i> ² Keyword is not specified on subcommand invocation.

DSNH (TSO CLIST)

Table 21. DSNH CLIST/ BIND PACKAGE subcommand summary (continued)

DSNH CLIST		BIND PACKAGE subcommand		Comments
Parameter	Value	Keyword	Value	
PDYNAMICRULES	NONE RUN BIND DEFINE INVOKE	DYNAMICRULES	RUN BIND DEFINE INVOKE	
PENABLE	NONE * BATCH CICS DB2CALL IMS DLIBATCH IMSBMP IMSMPP REMOTE RRSAF	ENABLE	NONE * BATCH CICS DB2CALL IMS DLIBATCH IMSBMP IMSMPP REMOTE RRSAF	
EXPLAIN	NO YES	EXPLAIN	NO YES	
PFLAG	I C E W	FLAG	I C E W	
PIMSBMP	NONE ¹ <i>imsid</i>	IMSBMP	<i>imsid</i>	¹ Keyword is not specified on subcommand invocation.
PIMSMPP	NONE ¹ <i>imsid</i>	IMSMPP	<i>imsid</i>	¹ Keyword is not specified on subcommand invocation.
PISOLATION	NONE ¹ RR RS CS UR NC	ISOLATION ¹	RR RS CS UR NC	¹ For local packages, the default value is the same as that of the plan appended at execution time. For remote packages, the default value is RR.
PKEEPDYNAMIC	NONE NO YES	KEEPDYNAMIC	NO YES	
PNODEFER	NONE ¹ PREPARE	NODEFER	PREPARE	¹ Keyword is not specified on subcommand invocation.
POPTHINT	(' ') (<i>'hint-id'</i>)	OPTHINT	(' ') (<i>'hint-id'</i>)	
POWNER	NONE ¹ <i>authorization-id</i>	OWNER	<i>authorization-id</i>	¹ Keyword is not specified on subcommand invocation.
PACKAGE	DEFAULT ¹ <i>location-name.</i> <i>collection-id</i>	PACKAGE	<i>location-name.</i> <i>collection-id</i>	¹ Member name defined in the INPUT parameter data set, or the data set name if no member name was specified.
PPATH	(<i>schema-name</i>) (USER)(<i>schema-name</i> , USER , ...)	PATH	(<i>schema-name</i>) (USER)(<i>schema-name</i> , USER , ...)	

Table 21. DSNH CLIST/ BIND PACKAGE subcommand summary (continued)

DSNH CLIST		BIND PACKAGE subcommand		Comments
Parameter	Value	Keyword	Value	
PQUALIFIER	NONE ¹ <i>implicit-qualifier</i>	QUALIFIER	<i>qualifier-name</i>	¹ Keyword is not specified on subcommand invocation.
PRELEASE	NONE ¹ COMMIT DEALLOCATE	RELEASE ¹	COMMIT DEALLOCATE	¹ For local packages, the default value is the same as that of the plan appended at execution time. For remote packages, the default value is NONE.
REOPT	NONE ¹ VARS	NOREOPT REOPT	VARS VARS	¹ Keyword is not specified on subcommand invocation.
REMOTE	NONE ¹ <i>location-name,</i> <i><luname></i>	REMOTE	<i>network-name</i>	¹ Keyword is not specified on subcommand invocation.
REPLVER	NONE ¹ <i>version-id</i>	REPLVER	<i>version-id</i>	¹ <i>version-id</i> is not specified on subcommand invocation.
SQLERROR	NOPACKAGE CONTINUE	SQLERROR	NOPACKAGE CONTINUE	
PVALIDATE	RUN BIND	VALIDATE	RUN BIND	

Usage notes

CICS translator: Do not use CICS translator options in the source language for assembler programs; pass the options to the translator with the CICSOPT option.

COBOL options: The COBOL DYNAM option has several restrictions:

- You cannot use the option with CICS.
- You must use the VS COBOL II library or the Language Environment (Language Environment for MVS & VM) library.
- To use the option with TSO or batch, the SDSNLOAD library must precede the IMS RESLIB in the step library, job library, or link list concatenations.
- To use the option with IMS, the IMS RESLIB must precede DSNLOAD.

Several COBOL options require DD statements that are not provided by the DSNH CLIST, as shown in Table 22.

Table 22. COBOL options that require additional DD statements

Option	Statements required for...
CDECK	SYSPUNCH
COUNT	SYSCOUNT, SYSDBG, SYSDBOUT, SYSUT5, a debug file
DECK	SYSPUNCH
DUMP	SYSABEND, SYSDUMP, or SYSUDUMP
FDECK	SYSPUNCH
FLOW	SYSCOUNT, SYSDBG, SYSDBOUT, SYSUT5, a debug file
LVL	SYSUT6
STATE	SYSCOUNT, SYSDBG, SYSDBOUT, SYSUT5, a debug file

DSNH (TSO CLIST)

Table 22. COBOL options that require additional DD statements (continued)

Option	Statements required for...
SYMDUMP	SYSCOUNT, SYSDBG, SYSDBOUT, SYSUT5, a debug file
SYST	SYSOUT
SYSx	SYSOUx
TEST	SYSUT5

COBOL parameters: The BUF and SIZE parameters passed to the COBOL compiler might have to be changed.

COPTION: Do not use the COPTION parameter to specify values for the LINECOUNT, SOURCE, TERM, and XREF compiler options; use the DSNH LINECOUNT, SOURCE, TERM, and XREF keywords.

Fortran and PL/I considerations: Variable-format input records are not supported.

Library limits: There can be at most eight bind libraries, four precompile libraries, four compile libraries, and four link-edit libraries.

Link-edit:

- DSNH cannot process programs that need additional link-edit control statements, and cannot link-edit programs that use the call attachment facility.
- You cannot use the NOLOAD and SYNTAX link-edit options.

NONE is a reserved word: NONE cannot be the name of an input or a load library, or the value of the string passed with PARMS.

SQL host variables: SQL host variables must be explicitly defined.

SYSPROC: If compilation is done, the SYSPROC data set must include the DB2 CLIST library.

WORKUNIT parameter: You must use the WORKUNIT parameter when running the DSNH CLIST in batch mode. This insures that the temporary and intermediate data sets are allocated to the correct devices.

Examples

Example 1: Precompile, bind, compile, link-edit, and run the COBOL program in data set *prefix.SDSNSAMP*(DSN8BC4).

- The compiler load module is in SYS1.LINKLIB (IKFCBL00).
- Additional load modules to be included are in *prefix.RUNLIB.LOAD* and *prefix.SDSNSAMP*.
- The load module is be put into the data set *prefix.RUNLIB.LOAD*(DSN8BC4).
- The plan name is DSN8BC71 for the bind and run.
- DCLGEN data from *prefix.SRCLIB.DATA* is required for the precompile.

This example assumes that the DSNH CLIST is in your SYSPROC concatenation.

```
DSNH INPUT('prefix.SDSNSAMP(DSN8BC4)') -  
  COBLOAD('SYS1.LINKLIB(IKFCBL00)') -  
  LLIB('prefix.RUNLIB.LOAD') -  
  L2LIB('prefix.SDSNSAMP') -  
  LOAD('prefix.RUNLIB.LOAD') -  
  PLAN(DSN8BC71) -  
  PLIB('prefix.SRCLIB.DATA')
```


Example 2: Precompile, bind, compile, and link-edit the program in data set *prefix.SDSNSAMP.PLI*(DSN8BP4).

- The program is written in PL/I; the macro pass is not needed.
- The PL/I compiler options MAP and LIST are to be used.
- Additional load modules to be included are in *prefix.RUNLIB.LOAD* and *prefix.SDSNSAMP*.
- The PL/I optimizing compiler load module is in library SYS2.LINKLIB(IELOAA).
- The DB2 subsystem identifier is SSTR.
- The load module is put into the data set *prefix.RUNLIB.LOAD*(DSN8BC4).
- Printed output is sent to the following data sets:

Output Data set

Precompiler listings

prefix.PROG.PCLIST

Compiler listings

prefix.PROG.LIST

Link edit listings

prefix.PROG.LINKLIST

- The plan name is DSN8BC71 for the bind and run.
- The DCLGEN data from *prefix.SRCLIB.DATA* is required for the precompile.

```
DSNH INPUT('prefix.SDSNSAMP(DSN8BP4)') -
HOST(PLI) MACRO(NO) -
COPTION ('MAP LIST') -
LLIB('prefix.RUNLIB.LOAD') -
L2LIB('prefix.SDSNSAMP') -
PLILOAD('SYS2.LINKLIB(IELOAA)') -
SYSTEM(SSTR) -
LOAD('prefix.RUNLIB.LOAD') -
PRINT(PROG) -
PLAN(DSN8BC71) -
PLIB('prefix.SRCLIB.DATA')
```

The COPTION parameters are enclosed between single apostrophes so that they are passed by TSO as a single parameter. If a single token is being passed as a parameter, no apostrophes are needed. That same rule applies to the PARMS and CICSOPT parameters.

If a data set name is being passed as a parameter, and you want TSO to add your user prefix, no apostrophes are needed. If the usual TSO prefixing and suffixing must not be performed, the data set name must be enclosed between sets of three apostrophes if the CLIST is executed implicitly, and sets of six apostrophes if the CLIST is executed explicitly.

The user prefix for that example is *prefix*; if it had been SMITH, the listing data set names would be as shown above, except that SMITH would be used as the first level qualifier. For example, the compiler listings would have gone to SMITH.PROG.LIST.

Example 3: Invocation of the DB2-C sample application program *prefix.SDSNSAMP*(DSN8BD3).

- The C linkage editor include library is EDC.V1R1M1.SEDCBASE
- The C compiler load module is EDC.V1R1M1.SEDCCOMP(EDCCOMP)
- Printed output is sent to the following data sets:

Output Data set

Precompiler listings

user_id.TEMP.PCLIST

DSNH (TSO CLIST)

Compiler listings

user_id.TEMP.SYSCPRT.LIST

Prelink utility listings

user_id.TEMP.SYSOUT.PRELLIST

Link-edit listings

user_id.TEMP.LINKLIST

- The following C DD names are allocated based on the PRINT keyword value:

DD name

Allocation

SYSCPRT

Used in the compile step

SYSUT10

Used in the compile step

SYSOUT

Used in the prelink step.

SYSUT10 and SYSCPRT are always allocated to the same data set or destination.

- SYSTEM is used in the compile step. It is based on the TERM keyword.
- CEEDUMP is used in the run step. It is based on the RUNOUT keyword.
- The LOPTION keyword values of AMODE(31) and RMODE(ANY) are required when link editing the C sample program to insure 31-bit addressability during execution.

```
ALLOC      DD(SYSPROC) DSN('prefix.SDSNCLST ') SHR
%DSNH BIND(YES) ACQUIRE(USE) ACTION(REPLACE)-
EXPLAIN(NO) -
CICSXLAT(NO) -
COMPILE(YES) -
CCLLIB('EDC.V1R1M1.SEDCBASE')-
CCLOAD('EDC.V1R1M1.SEDCCOMP(EDCCOMP)')-
DBRM('prefix.DBRMLIB.DATA(DSN8BD3)')-
DECIMAL(PERIOD) DELIMIT(DEFAULT) FLAG(I)-
HOST(C) ISOLATION(RR)-
INPUT('prefix.SDSNSAMP(DSN8BD3)')-
LINK(YES)-
LLIB('prefix.RUNLIB.LOAD')-
L2LIB('prefix.SDSNLOAD')-
LOAD('prefix.RUNLIB.LOAD')-
LOPTION('AMODE(31) RMODE(ANY)')-
MACRO(NO)-
OUTNAME(TEMP)-
PLAN(DSN8BD31) PRECOMP(YES)-
PLIB('prefix.SDSNSAMP')-
PRELINK(NO)-
POPTION(NONE)-
PRINT(TEMP) RCTERM(8)-
RELEASE(COMMIT) RETAIN(YES)-
RUN(NO) RUNIN(TERM)-
RUNOUT(TERM) SOURCE(YES)-
SYSTEM(DSN) SQLDELIM(DEFAULT)-
VALIDATE(RUN)
```

END (DSN)

The DSN subcommand END is used to end the DSN session and return to TSO.

Environment

This subcommand originates from a TSO input stream when DSN is running in either background or foreground mode.

Data sharing scope: Member

Authorization

None is required.

Syntax

▶▶—END—▶▶

Usage note

Ending the DSN session in batch or foreground: In batch, if END is not found in the SYSIN stream, /* or // ends the DSN session. From the foreground, pressing the ATTENTION key twice ends the DSN session.

Example

End the DSN session and return to TSO.

```
TSO prompt : READY
USER enters: DSN SYS (SSTR)
DSN prompt : DSN
USER enters: RUN PROGRAM (MYPROG)
DSN prompt : DSN
USER enters: END
TSO prompt : READY
```

FREE PACKAGE (DSN)

FREE PACKAGE (DSN)

The DSN subcommand FREE PACKAGE can be used to delete a specific version of a package, all versions of a package, or whole collections of packages.

The FREE PACKAGE subcommand deletes corresponding table entries from the catalog tables. Authorization for a package name is only removed when no more versions of the package exist. After a version of a package has been freed, that package name is then available for use in a BIND PACKAGE subcommand to create a new package.

The FREE PACKAGE subcommand does not proceed until all currently executing applications using the package finish executing.

For additional information about packages, see Part 5 of *DB2 Application Programming and SQL Guide*.

Environment

You can enter this subcommand from DB2I, or from a DSN session under TSO that is running in either foreground or background.

Data sharing scope: Group


Authorization

To execute this subcommand, the privilege set of the process must include one of the following:

- Ownership of the package
- BINDAGENT privilege granted by the owner of the package
- SYSCTRL or SYSADM authority
- PACKADM authority for the collection or for all collections

The BIND privilege on a package is *not* sufficient to allow a user to free a package.

Syntax



Option descriptions

location-name

Specifies the location of the DBMS where the package is to be freed. The location name must be defined in the SYSIBM.LOCATIONS table. If this table does not exist or the DBMS is not found, you receive an error message. If the location name is specified, the name of the local DB2 must be defined. See Part 3 of *DB2 Installation Guide* for information on how to define a location name within SYSIBM.LOCATIONS.

The **default** is the local DB2 if you omit *location-name*.

collection-id or (*)

Identifies the collection of the package to be freed. There is no default.

You can use an asterisk (*) to free all local packages with the specified *package-id* in all the collections that you are authorized to free. (You cannot use the * to free remote packages.)

package-id or (*)

Identifies the package to be freed. There is no default.

You can use an asterisk (*) to free all local packages in *collection-id* that you are authorized to free. (You cannot use the * to free remote packages.)

version-id or (*)

Identifies the version of the package to be freed.

You can use an asterisk (*) to free all local packages in the *collection-id* and *package-id* that you are authorized to free. (You cannot use the * to free remote packages.)

If you specify () for *version-id*, then the empty string is used for the version ID.

If you omit the *version-id*, the default depends on how you specify *package-id*. If you use * for *package-id*, *version-id* defaults to *. If you provide an explicit value for *package-id*, *version-id* defaults to an empty string.

DBRMs created before DB2 Version 2 Release 3 use an empty string for *version-id* by default.

(*)

Frees all local DB2 packages that you are authorized to free.

Specifying (*) is equivalent to specifying the package name as (*.*(*)) or (*.*)

FLAG

Indicates what messages you want to see. Use one of the values listed to show messages of the corresponding types.

- (I) All: informational, warning, error, and completion messages.
- (W) Only warning, error, and completion messages.
- (E) Only error and completion messages.
- (C) Only completion messages.

Usage notes

Freeing multiple packages: If you free multiple packages with this subcommand, each successful free is committed before freeing the next package.

FREE PACKAGE (DSN)

If an error occurs on a certain package specified explicitly in a list or implicitly with (*), FREE PACKAGE terminates for that package and continues with the next package to be processed.

Freeing trigger packages: You cannot free a trigger package using the FREE PACKAGE subcommand.

For more information about dropping triggers, see Chapter 5 of *DB2 SQL Reference*.

Examples

Example 1: Free version *newver* of the package TEST.DSN8BC71 located at USIBMSTODB22. Generate only warning, error, and completion messages (not informational messages).

```
FREE PACKAGE (USIBMSTODB22.TEST.DSN8BC71.(newver)) FLAG(W)
```

Example 2: Free all packages at the local server in the collection named TESTCOLLECTION.

```
FREE PACKAGE (TESTCOLLECTION.*)
```

FREE PLAN (DSN)

The DSN subcommand FREE PLAN deletes application plans from DB2.

The FREE PLAN subcommand deletes corresponding table entries from the SYSIBM.SYSPLAN catalog tables. All authorization against an application plan name is dropped. The application plan name is then available for use in a BIND PLAN subcommand to create a new package.

The FREE PLAN subcommand does not proceed until all currently executing applications using that plan finish executing.

For additional information on plans, see Part 5 of *DB2 Application Programming and SQL Guide*.

Environment

You can enter this subcommand from DB2I, or from a DSN session under TSO that is running in either foreground or background.


Data sharing scope: Group

Authorization

To execute this command, the privilege set of the process must include one of the following:

- Ownership of the plan
- BIND privilege on the plan
- BINDAGENT privilege granted by the plan owner
- SYSCTRL or SYSADM authority

Syntax



Option descriptions

(plan-name, ...)

Lists the names of one or more plans you want to free.

(*) Frees *all* application plans over which you have BIND authority. Be careful when using this form of the command.

FLAG

Indicates what messages you want to see. Use one of the values listed to show messages of the corresponding types.

- (I)** All: informational, warning, error, and completion messages.
- (W)** Only warning, error, and completion messages.
- (E)** Only error and completion messages.

FREE PLAN (DSN)

(C) Only completion messages.

Usage notes

Freeing multiple plans: If you free multiple plans with this subcommand, each successful free is committed before freeing the next plan.

If an error occurs on a certain plan specified explicitly in a list or implicitly with (*), FREE PLAN terminates for that plan and continues with the next plan to be processed.

Example

Free plan DSN8BC71 from DB2. Generate only warning, error, and completion messages (not informational messages).

```
FREE PLAN (DSN8BC71) FLAG (W)
```


MODIFY irlmproc,ABEND (MVS IRLM)

The MODIFY *irlmproc*, ABEND command terminates the IRLM abnormally. IRLM processes this command even if there is a DB2 identified to it.

Abbreviation: F

Environment


This command can be issued only from an MVS console.

Data sharing scope: Member

Authorization

The command requires an appropriate level of MVS authority, as described in *OS/390 MVS System Commands*.

Syntax



Option descriptions

Parameters must be separated by commas with no spaces.

irlmproc

Identifies the procedure name of the IRLM that is to be terminated.

DUMP

Specifies that IRLM is to terminate abnormally with a U2020 abend. A system dump is taken to the SYS1.DUMPxx data set. IRLM does not de-register from ARM.

NODUMP

Specifies that IRLM is to FORCE the DBMS off and terminate normally without generating a dump. All DBMS work is quiesced and IRLM stops itself.

A second invocation will cause IRLM to terminate abnormally with a U2020 abend; no dump will be taken.

Usage notes

Terminating IRLM: If there are any difficulties terminating IRLM, see “Usage note” on page 324

Deregistering IRLM: You can use the NODUMP option to deregister IRLM before stopping it. This action prevents the automatic restart manager from immediately trying to restart IRLM.

Example

Enter on an MVS system console:

```
F KRLM001,ABEND
```

MODIFY ..., ABEND (MVS IRLM)

Response on the MVS system console:

```
DXR124E IR21001 ABENDED VIA MODIFY COMMAND
*IEA911E COMPLETE DUMP ON SYS1.DUMP00
FOR ASID(0004)
  ERROR ID = SEQ00001 CPU00 ASID0004 TIME08.34.59.9
DXR121I IR21001 END-OF-TASK CLEANUP SUCCESSFUL
IEF450I IR21001 IR21001 - ABEND=S000 U2020 REASON=00000000
```

The default is dump. If you do not want a dump, you must specify:

```
F KRLM001,ABEND,NODUMP
```

Abbreviation: F

This command can be issued only from an MVS console.

The command requires an appropriate level of MVS authority, as described in *OS/390 MVS System Commands*.

```

    >>—MODIFY—irlmproc,DIAG—,DELAY————><
        |,PLOCK|
        |,ALL—|
        |,NONE—|
        |,HANG—|

```

MODIFY ..., DIAG (MVS IRLM)

| **NONE**
| Disables generating all diagnostic dumps.

HANG
Collects IRLM SYSPLEX dumps when DEADLOCK or TIMEOUT issues are
suspected. The dumps are taken during DEADLOCK processing. The
DEADLOCK processing is stopped and the dynamic deadlock storage is
collected. MVS DUMP services then schedules an SRB to restart DEADLOCK
processing. Message DXR183I is issued by each IRLM as DEADLOCK
processing is restarted. If message DXR183I is not issued by an IRLM, that
IRLM must be terminated and restarted.

Note: Always start the IRLM XCF CTRACE internally and wait 30 seconds
before issuing this command.

Usage note

The MODIFY irlmproc,DIAG command should be used only under the direction of
IBM service.

Restrictions: This command is active for only one incident per IRLM, that is, after an IRLM instance detects the delay and initiates the dump. You can initiate one dump per IRLM in the group. You must re-enter the command to initiate another dump. Be aware that when you enter this command for one member of the data sharing group, *any* member that detects the delay initiates a dump.

The *irlmproc* identifies the procedure name for IRLM. If multiple IRLM instances exist in the same system, each procedure must have a unique procedure name.

Example

Issue this command to initiate one diagnostic dump for the IR21PROC IRLM subsystem. The dump occurs once, after the propagation of child locks takes longer than 45 seconds.

```
MODIFY IR21PROC,DIAG,DELAY
```

MODIFY irlmproc,PURGE (MVS IRLM)

The MODIFY irlmproc,PURGE command releases IRLM locks retained due to a DB2, IRLM, or system failure. The command causes all retained locks for the specified DB2 to be deleted from the system, thereby making them available for update. Since retained locks protect updated resources, it should be used only after understanding what the resources are and the consequence to data integrity if they are deleted.

Abbreviation: F

Environment

This command can be issued only from an MVS console.

Data sharing scope: Member

Authorization

The command requires an appropriate level of MVS authority, as described in *OS/390 MVS System Commands*.

Syntax

```
►►—MODIFY—irlmproc,PURGE,db2name—►►
```

Option descriptions

Use commas with no spaces to separate parameters.

irlmproc

Specifies the IRLM that is to process the command.

db2name

The DB2 name, as displayed by the STATUS command.

Usage notes

DB2 subsystem inactive: The DB2 subsystem which owns the retained locks must be inactive or else this command will fail.

Example

Example: Enter on an MVS system console:

```
F IR21I,PURGE,DB2A
```

Response on the MVS system console:

```
DXR109I IR21001 PURGE COMMAND COMPLETED FOR DB2A
```

MODIFY ..., SET (MVS IRLM)

MODIFY irlmproc,SET (MVS IRLM)

- The MODIFY irlmproc, SET command performs the following tasks:
- Dynamically sets the maximum CSA allowed for IRLM.
 - Dynamically sets the number of trace buffers allowed for IRLM.
 - Dynamically sets the number of LOCK LTE entries to be specified on the next connect to the XCF LOCK structure.
 - Dynamically sets the timeout value for a specified subsystem.
 - Dynamically sets the local deadlock frequency.

Abbreviation: F

Environment


This command can be issued only from an MVS console.

Data sharing scope: Member

Authorization

The command requires an appropriate level of MVS authority, as described in *OS/390 MVS System Commands*.

Syntax



Option descriptions

Use commas with no spaces to separate parameters.

irlmproc
Specifies the IRLM that is to process the command.

SET
Sets the following values for this IRLM:

CSA=nnn
Requests that IRLM dynamically set the maximum amount of common storage area (CSA) for this IRLM to use for lock control structures. *nnn* must be a one- to three-digit number from 1 through 999. The number indicates what multiple of 1 MB of storage the specified IRLM will use. For example, CSA=6 allows the IRLM to use 6 MB of CSA.

The lock control structures are allocated from extended common storage area (ECSA) when PC=NO, or from IRLM private region when PC=YES.

IRLM does not immediately allocate CSA storage for the new value you set using this command; IRLM allocates storage as needed, not to exceed the amount of CSA specified. If the amount of storage currently

MODIFY ..., SET (MVS IRLM)

allocated by IRLM is greater than the amount of CSA you specify using this command, IRLM does not obtain more storage until normal processing frees enough storage to bring the current allocation below the new CSA value you set.

DEADLOCK=nnnn

Specifies the number, in milliseconds, indicating how often the local deadlock processing is scheduled. *nnnn* must be a number from 100 through 5000 milliseconds. If a member of a sysplex group and all IRLMs are not enabled for subsecond deadlock processing, message DXR106E is issued.

LTE=nnnn

Specifies the number of LOCK Table Entries to be specified on the next connect to the XCF LOCK structure. *nnnn* must be a number from 0 through 1024, and be an even power of two. Each increment in value represents 1048576 LTE entries. Note that this parameter is used for data sharing only.

TIMEOUT=nnnn, subsystem-name

Requests that IRLM dynamically set the timeout value for the specified subsystem. *nnnn* must be a number from 1 through 3600.

subsystem-name is the DB2 subsystem name, as displayed by the MODIFY IRLMPROC,STATUS command.

TRACE=nnn

Requests that IRLM dynamically set the maximum number of 64 KB trace buffers per trace type to the value you specify in *nnn*. *nnn* must be a number from 10 through 255. If you specify a value outside of this range, IRLM automatically adjusts the value to a value within the range.

The **default** is 10.

This value is used only when the external CTRACE writer is not activated. The trace buffers are allocated from extended common storage area (ECSA).

IRLM does not immediately acquire the number of trace buffers you set using this command; IRLM allocates buffers as needed, not to exceed the number of buffers you specified. If the number of trace buffers you set is less than the number of currently allocated buffers, IRLM brings the number within your specified range by releasing the oldest buffers at the end of the next deadlock or timeout cycle.

Usage notes

Determining limits for CSA values: Do not modify the CSA value without first contacting the system programmer to determine the amount of CSA storage that can be used for IRLM.

Effect of an IRLM restart: The values you set using the MODIFY IRLMPROC,SET command do not persist through a stop and restart of IRLM. The number of trace buffers for each trace type returns to the default value of 10, and the value for MAXCSA returns to the value you set for the MAXCSA parameter on the IRLM startup procedure.

TIMEOUT considerations: The TIMEOUT value must be a multiple of the local deadlock parameter. If the value entered is not an even multiple of the deadlock parameter, IRLM will increase the timeout value to the next highest multiple. This new value is used until the IRLM or identified subsystem is terminated, or the

MODIFY ..., SET (MVS IRLM)

| timeout is changed again by the operator. The value specified on the command
| does *not* affect the timeout value in the DB2 ZParms.

Effect of the LTE parameter: If a syntax error is made, message DXR106E is
issued. Syntax errors include LTE value out-of-range. If this IRLM is *not* connected
to the group, but the value specified is valid, a message DXR177I is issued stating
that the value has been set, but the value will not be sent to any other member. If
the member is already in the group, the value is sent to the Global Deadlock
Manager IRLM to be broadcast to all other members. If the GDM does not have the
code applied, no DXR177I message is issued on any member. If the GDM has the
code, then all members with the code applied will issue the DXR177I message as
the command is processed. This value is only used if the IRLM is the first to join
the data sharing group, causing structure allocation or during a REBUILD. If any
IRLM joins later, it will not have the updated value. If multiple MODIFY commands
are issued on the same or multiple IRLMs, some DXR177I messages may be
missing. The last DXR177I message issued is the value to be used on the next
CONNECT.

The value for the number of LOCK Table Entries specified during normal group
startup and during REBUILD are used in the following order:

1. The value specified on the MODIFY irlmproc,SET,LTE= command, if greater
than 0.

2. The value from the LTE= in the IRLMPROC, if greater than 0.

| 3. The existing logic, which determines the nearest power of 2 after dividing the
| QUERY size returned by 2 times LTE width based on MAXUSRS.

| If an attempt is made to use a nonzero value from either option number 1 or 2, and
| that value is too large for the structure size returned on the QUERY, then the value
| from the next option in the sequence will be used instead.

Deadlock value range for non-supporting members: When an IRLM that
supports subsecond deadlock joins a group that has a member that does not
support subsecond deadlock, if the deadlock value of the new member is less than
one second, then the value is set to one second.

Examples

Example 1: Enter on an MVS system console:

F IR21I,SET,CSA=10

Response on the MVS system console:

DXR177 I IR21001 MAXCSA IS SET TO 10

Explanation: IR21001 is the IRLM subsystem name concatenated with the IRLM
system ID.

Example 2: Enter on an MVS system console:

F IR21PROC,SET,TRACE=20

Response on the MVS system console:

DXR177I IR21033 THE VALUE FOR TRACE IS SET TO 20.

Example 3: Enter on an MVS system console:

F IR21PROC,SET,TIMEOUT=60,DBMS

MODIFY ..., SET (MVS IRLM)

Response on the MVS system console:

DXR177I IR21033 THE VALUE FOR TIMEOUT IS SET TO 60 FOR DBMS

Example 4: Enter on an MVS system console:

F IR21PROC,SET,LTE=1024

Response on the MVS system console:

DXR177I IR21033 THE VALUE FOR LTE IS SET TO 1024

Example 5: Enter on an MVS system console:

F IR21I,SET,DEADLOCK=1000

Response on the MVS system console:

DXR177I IR21033 THE VALUE FOR DEADLOCK IS SET TO 1000 MILLISECONDS

MODIFY irlmproc,STATUS (MVS IRLM)

This command displays information for one or more subsystems connected to the specified IRLM designated using *irlmproc*. Each subsystem connected to the specified IRLM is listed, including subsystem name, status, work unit and lock information. Additionally, you can list an IRLM's ID and service level. For a specified IRLM, you can display the current storage allocated, as well as the greatest amount of storage that has been allocated since the last time this IRLM was started.

Abbreviation: F

Environment


This command can be issued only from an MVS console.

Data sharing scope: Member or group, depending on which option you choose

Authorization

The command requires an appropriate level of MVS authority, as described in *OS/390 MVS System Commands*.

Syntax



Option descriptions

irlmproc

Specifies the IRLM that is to process the command.

irlmx

Specifies which IRLM's status is to be displayed. *irlmx* is the concatenation of the IRLM subsystem name and IRLM member ID as specified in the IRLM startup procedure (DB2 installation panel DSNTIPI). An example is DB2G2 (ID is 2).

ALLD

Requests the DB2 subsystem name and status of a DB2 that is identified to an IRLM. In the data sharing group, this command lists information about all DB2s that are currently identified to an IRLM, assuming that the IRLM on which the command is issued is connected to the data sharing group. You can determine if the IRLM is connected by issuing a `MODIFY irlmproc,STATUS` command and checking that the output shows `SCOPE=GLOBAL`.

If a DB2 is down and holds retained locks, that DB2 is also displayed. However, the IRLM that is displayed with that DB2 can vary depending on several circumstances:

- Normally, it is the last IRLM to which DB2 identified.

MODIFY ..., STATUS (MVS IRLM)

- If there was a rebuild of the lock structure after the retained locks were created, it is the IRLM with the lowest member ID at the time the rebuild occurred.
- If a group restart is occurring and one DB2 is recovering on behalf of another DB2, the IRLM that is displayed is the one associated with the DB2 doing the peer recovery. For example, if DB2A is doing a peer recovery of DB2B, the display might show:

NAME	STATUS	...	IRLM_NAME
DB2A	UP		IRLA
DB2B	DOWN		IRLA

ALLI

Requests the IRLM subsystem name, ID, status, and service level. In a data sharing group, this command lists information about all IRLMs in the data sharing group, assuming that the IRLM on which the command is issued is connected to the data sharing group. You can determine if the IRLM is connected by issuing a MODIFY irlmproc,STATUS command and checking that the output shows SCOPE=GLOBAL.

If an IRLM is down, it is displayed only if its associated DB2 is down and holds retained locks. The IRLM that is displayed can vary depending on several circumstances:

- Normally, it is the last IRLM to which DB2 identified.
- If there was a rebuild of the lock structure after the retained locks were created, it is the IRLM with the lowest member ID at the time the rebuild occurred.
- If the failed DB2 had recovery done on its behalf by another DB2, the IRLM that is displayed is the one associated with the DB2 that did the peer recovery.

MAINT

For this IRLM only, displays the maintenance levels of IRLM load module CSECTS in a two-column format.

STOR

For this IRLM only, displays the current and "high-water" allocation for CSA and ECSA storage.

TRACE

Requests information about IRLM subcomponent trace types. Information includes whether a subcomponent trace type is active, how many trace buffers are used by the trace, and whether the component trace external writer is active for the trace.

Usage notes

Messages: If *irlmx* is not specified, or if this IRLM is in a non-data-sharing environment, message DXR101I is issued. That message lists each subsystem connected to the IRLM specified by *irlmx*, with an indication as to whether the connection is active.

Displaying IRLM IDs: If *irlmproc* is started specifying SCOPE=GLOBAL, the second line of the display indicates the IRLM IDs of the IRLMs.

Examples

Example 1: Enter on the MVS1 system console:

```
F IRTPROC,STATUS
```

MODIFY ..., STATUS (MVS IRLM)

Response on MVS1 system console:

```
DXR101I IR2T001 STATUS SCOPE=LOCAL
SUBSYSTEMS IDENTIFIED PT01
NAME STATUS UNITS HELD WAITING RET_LKS
DSNT1 UP-NS 0005 0010 0002 0
```

Explanation: The operator on system 1 has requested information about the DB2 systems connected to the IRLM identified by the IRLM procedure named IRTPROC.

If the IRLM is SCOPE=GLOBAL on the irlmproc and is not connected to any group, the status message shows:

```
DXR101I IR21001 STATUS SCOPE=DISCON
```

Example 2: Assume you have a data sharing group. Enter on a system console:

```
F DB1GIRLM,STATUS,ALLD
```

Response on system console:

```
# 14.02.10 STC00086 DXR102I DJ1G001 STATUS
# SUBSYSTEMS IDENTIFIED PT01
# NAME STATUS RET_LKS IRLMID IRLM_NAME IRLM_LEVEL
# DB4G UP 0 004 DJ4G 006
# DB3G UP 0 003 DJ3G 012
# DB2G UP 0 002 DJ2G 021
# DB1G UP 0 001 DJ1G 021
#
```

Explanation: The output shows all the DB2s that are connected to IRLMs in this data sharing group (the group to which the IRLM processing the request belongs). The value “UP” in the STATUS field indicates that the DB2 is active. Other possible values for STATUS include:

DOWN

The DB2 is failed. All “modify” type locks held by this DB2 have been retained by IRLM. The DB2 is known to be down only if it has retained locks.

SYSFAIL

The IRLM that DB2 is identified to has been disconnected from the data sharing group. All “modify” type locks held by this DB2 have been retained by IRLM. The DB2 is known to be SYSFAIL only if it has retained locks.

Example 3: Again, assume data sharing is in effect. Enter the following on the system console:

```
F DB1GIRLM,STATUS,ALLI
```

The response on the console is:

```
17.17.03 STC00092 DXR103I LRLM007 STATUS
IRLMS PARTICIPATING IN DATA SHARING GROUP FUNCTION LEVEL=006
IRLM_NAME IRLMID STATUS LEVEL SERVICE MIN_LEVEL MIN_SERVICE
JRLM 005 UP 013 PN92893 006 IRLM2.1
KRLM 006 UP 006 IRLM2.1 006 IRLM2.1
LRLM 007 UP 013 PN92893 006 IRLM2.1
```

Explanation: The output shows the IRLMs that are participating in this data sharing group (the group which includes the IRLM processing the request). Other information includes:

STATUS

The value “UP” in the STATUS field indicates that the IRLM is active.

MODIFY ..., STATUS (MVS IRLM)

STATUS shows "DOWN" if the IRLM is failed. An IRLM is known to be "DOWN" only if the DB2 that was identified to it has retained locks. This connection between a failed DB2 and IRLM is lost after a rebuild or a group restart.

LEVEL

The current IRLM function level.

SERVICE

The IRLM service or release that corresponds to the function level given in "LEVEL".

MIN_LEVEL

The minimum IRLM function level this IRLM can coexist with.

MIN_SERVICE

The IRLM service or release that corresponds to the function level given in "MIN-LEVEL".

Group Function Level

The IRLM function level in use by all the IRLMs in the data sharing group.

Example 4: Assume that this command is issued in a non-data sharing environment. Enter the following on the system console:

```
F DB1GIRLM,STATUS,ALLI
```

The response on the console is:

```
15.12.01 STC00092 DXR103I VRLM007 STATUS
          IRLMS PARTICIPATING IN DATA SHARING GROUP FUNCTION LEVEL=016
          IRLM_NAME IRLMID STATUS LEVEL SERVICE MIN_LEVEL MIN_SERVICE
          VRLM      007    UP    016 PQ15854    012    PN90337
```

Explanation: The output shows information only for the IRLM specified. The group function level shown is the function level for the specified IRLM. Refer to Example 3 on page 234 for additional information on interpreting output.

Example 5: Enter the following command on the system console:

```
F IR21PROC,STATUS,STOR
```

The response on the console is:

```
DXR100I IR21001 STOR STATS
          PC: NO    MAXCSA:    6M
CSA USE: ACNT:    132K AHW:    132K CUR:  4048K HWM:  4086K
          ABOVE 16M:    72 4033K  BELOW 16M:    6    15K
CLASS  TYPE  SEGS    MEM  TYPE  SEGS    MEM  TYPE  SEGS    MEM
ACCNT  T-1    1    64K  T-2    1    64K  T-3    1    4K
PROC   WRK   11    58K  SRB    3    3K   OTH    2    2K
MISC   VAR   60   4081K  N-V    6   22K   FIX    1   24K
```

Explanation: The example shows that current storage allocated for IRLM is 4048 KB, and the greatest amount that has been allocated since the last time IRLM was started is 4086 KB. The storage for the locking structures (RHB and RLB) is contained within ECSA, because this IRLM is defined with PC=NO. Use the following information to interpret the display output:

PC

Displays the current value for the PC option of the IRLM startup procedure.

MODIFY ..., STATUS (MVS IRLM)

MAXCSA	Displays the current value for the MAXCSA option of the IRLM startup procedure. The MAXCSA value is 6 MB in this example.
CSA USE	Shows storage use that is accountable toward the MAXCSA value of the IRLM procedure. In this output, the current use accountable storage (ACNT) is 132 KB. The high water mark since the last time IRLM was started (AHWM) is also 132 KB.
CUR	Shows the total current CSA and ECSA usage. In this case, the current usage (CUR) is 4048 KB, and the high water mark (HWM) is 4086 KB. The accountable storage is a subset of this total storage.
ACCNT	<p>The ACCNT row of the report is a breakdown of lock control block structures and their storage use.</p> <p>T-1 Type one structures are for resources. In this case, it shows that one storage segment is held for a total of 64 KB.</p> <p>T-2 Type two structures are for all resource requests after the first request for a specific resource. This example shows that one storage segment is held for a total of 64 KB.</p> <p>T-3 Type three structures are for requesters or work units that are waiting for or hold resources. This example shows that one storage segment is held for a total of 4 KB.</p>
PROC and MISC rows	These rows contain usage information for CSA, ECSA, and private storage used to process DBMS requests. Use this information under the guidance of IBM® Support Center for diagnosing problems.

For more information, see the explanation of message DXR100I in *DB2 Messages and Codes*.

Example 6: Assume the IRLM was started with PC=YES. Enter the following command on the system console:

```
F IR21PROC,STATUS,STOR
```

The response on the console is:

```
DXR100I JR21001 STOR STATS
      PC: YES  MAXCSA:  N/A
CSA USE: ACNT:      OK AHWM:      OK CUR: 4362K HWM: 5830K
      ABOVE 16M:  78 4376K  BELOW 16M:  23  32K
CLASS  TYPE  SEGS  MEM  TYPE  SEGS  MEM  TYPE  SEGS  MEM
ACCNT  T-1    1    64K  T-2    1    64K  T-3    1    4K
PROC   WRK   11    58K  SRB   20   20K  OTH    2    2K
MISC   VAR   68  4497K  N-V    6   22K  FIX    1   24K
```

Explanation: This example was created using a poorly-tuned application, and shows how important a well-tuned system is for predicting system storage needs. This example illustrates what can happen when an application generates a high IRLM

MODIFY ..., STATUS (MVS IRLM)

lock contention rate; the high value of 20 segments with 20 KB each for type SRB storage, and the high value of 23 segments with 23 KB each for storage below the 16 MB line are some of the results.

For more information about reducing lock contention, see Part 5 (Volume 2) of *DB2 Administration Guide*. For more information about tuning your system, see Chapter 6 of *DB2 Data Sharing: Planning and Administration*.

Example 7: Enter the following command on the system console:

```
F PR21PROC,STATUS,TRACE
```

The response on the console is:

```
DXR179I PR21034 TRACE USAGE
TRACE BUFFER STORAGE IN USE: 256 KB
MAXIMUM NUMBER OF TRACE BUFFERS ALLOWED PER TRACE TYPE: 10
TRACE TYPE  ACTIVE  BUFFERS IN USE  CTRACE WRITER
-----
SLM          N          0          N
XIT          Y          2          N
XCF          N          0          N
DBM          N          0          N
EXP          Y          1          N
INT          Y          1          N
```

Explanation: This example shows that the storage currently allocated for IRLM tracing is 256 KB, the maximum number of trace buffers allowed per trace type is set to 10, and the external CTRACE writer is not active. For more information about the trace types, see “TRACE CT (MVS IRLM)” on page 340.

Use the TRACE CT command of MVS on page 340 to activate or deactivate traces. You cannot turn off the EXP and INT traces. The XIT (for data sharing), EXP, and INT traces are automatically activated when you start IRLM. All traces are automatically activated with IRLMPROC TRACE=YES.

The trace size for each buffer is 64 KB. Use the MODIFY irlmproc,SET,TRACE=nnn command on page 228 to change the maximum number of trace buffers.

Example 8: Enter the following command on the system console:

```
F IR21I, STATUS, MAINT
```

The response on the console is:

```
DXR104I IR21240 Maintenance levels
      LMOD.Csect  MaintLv  Date      Csect  APAR      DATE
DXRRLM00.DXRRL010 PQ35083 02/22/00 DXRRL020 PQ35083 02/22/00
      DXRRL030  PQ27464 08/18/99  DXRRL040 PQ35083 02/22/00
```

Explanation: The output shows the maintenance levels of IRLM load module CSECTS in a two-column format.

-MODIFY TRACE (DB2)

-MODIFY TRACE (DB2)

The DB2 command MODIFY TRACE does the following:

- Changes the trace events (IFCIDs) being traced for a particular active trace.
- Stops any IFCID previously active for the specified trace.
- Writes statistics records.

Abbreviation: -MOD TRA

Environment

This command can be issued from an MVS console, a DSN session, a DB2I panel (DB2 COMMANDS), an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

Data sharing scope: Member

Traces started by a IFI/IFC program:

Before you modify an active trace, ensure that an IFI application program or the IFC Selective Dump utility (DSN1SDMP) did not start the trace. If you modify a trace started by DSN1SDMP, the DSN1SDMP utility abnormally terminates. When DSN1SDMP terminates, it stops the trace. This stop could interfere with the MODIFY TRACE command which stops and restarts the trace.


Authorization

To execute this command, the privilege set of the process must include one of the following:

- TRACE privilege
- SYSOPR, SYSCTRL, or SYSADM authority

DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.

Syntax



Option descriptions

TRACE

Determines which IFCIDs are started. For more descriptions of each trace type, see “-START TRACE (DB2)” on page 299.

Table 23. Trace types

Type	Description	Abbreviation
PERFM	Performance records of specific events	P
ACCTG	Accounting records for each transaction	A
STAT	Statistical data	S
AUDIT	Audit data	AU
MONITOR	Monitor data	MON

One additional trace type is not described here. It is intended for service and is to be used under the direction of IBM support personnel. For details, see *DB2 Diagnosis Guide and Reference*.

CLASS(integer, ...)

Limits the list to IFCIDs started for specified classes.

Abbreviation: C

integer is a class to which the list of IFCIDs started is limited. For descriptions of the allowable classes, see “-START TRACE (DB2)” on page 299.

The **default** is **CLASS(*)**, which starts all default IFCID classes.

TNO(integer)

Specifies the particular trace to be modified, identified by its trace number (1 to 32, 01 to 09). You can only specify one trace number. TNO is a required option for the MODIFY TRACE command.

No default exists for the TNO keyword.

IFCID(ifcid_nbr, ...)

Specifies which other IFCIDs (trace events), in addition to those IFCIDs contained in the classes specified in the CLASS option, are to be started. To start only those IFCIDs specified in the IFCID option, use trace classes 30-32. These classes have no predefined IFCIDs and are available for a location to use. (See “Example” for an example of activating only those trace events specified in the IFCID option.)

If you do not specify the IFCID option, only those IFCIDs contained in the activated trace classes are started.

The maximum number of IFCIDs is 156. The range of values that are valid for the IFCID option is 1 through 350, with the exception of: 4, 5, 185, 187, 217, 232, 234, 240, and 241.

The **default** is **IFCID(*)**.

COMMENT(string)

Gives a comment that is reproduced in the trace output record (except in the resident trace tables).

string is any character string; it must be enclosed between apostrophes if it includes a blank, comma, or special character.

Example

Change trace number 6 so that it collects only statistics and accounting data. You can define CLASS(30) at your site.

```
-MODIFY TRACE(S) IFCID(1,2,3) TNO(6) CLASS(30)
COMMENT ('STATS AND ACCOUNTING ON')
```

REBIND PACKAGE (DSN)

The DSN subcommand REBIND PACKAGE rebinds an application package when you make changes that affect the package, but have not changed the SQL statements in the program. For example, you can use REBIND PACKAGE when you change the authorizations, create a new index for the package, or use RUNSTATS. When the REBIND PACKAGE(*) command is issued, trigger packages will not be affected.

REBIND PACKAGE is generally faster and more economical than BIND PACKAGE. You should use BIND PACKAGE with the ACTION(REPLACE) option under the following conditions:

- When you change the SQL statements
- When you recompile the program
- You previously ran BIND PACKAGE with the SQLERROR(CONTINUE) option

For more information on using REBIND PACKAGE, see Part 5 of *DB2 Application Programming and SQL Guide*.

Environment

You can use REBIND PACKAGE through DB2I, or enter the REBIND PACKAGE subcommand from a DSN session running in foreground or background.

Data sharing scope: Group

Authorization

The package owner must have authorization to execute *all* SQL statements embedded in the package for REBIND PACKAGE to build a package without producing error messages. For VALIDATE(BIND), DB2 verifies the authorization at bind time. For VALIDATE(RUN), DB2 verifies the authorization initially at bind time, but if the authorization check fails, DB2 rechecks it at run time.

Table 24 explains the authorization required to run REBIND PACKAGE, depending on the options specified.

Table 24. Summary of privileges for REBIND PACKAGE

Option	Authorization required to run REBIND PACKAGE
REBIND PACKAGE with no change in ownership, because the OWNER keyword is not specified.	The authorization IDs of the process must have one of the following: <ul style="list-style-type: none">• Ownership of the package• BIND privilege on the package• BINDAGENT privilege from the owner of the package• PACKADM authority on the collection or on all collections• SYSADM or SYSCTRL authority
REBIND PACKAGE with no change in ownership, although the original owner is specified for the OWNER keyword.	The authorization IDs of the process must have one of the following: <ul style="list-style-type: none">• OWNER <i>authorization-id</i> must be one of the primary or secondary authorization IDs of the binder• BINDAGENT privilege from the owner of the package• SYSADM or SYSCTRL authority


Table 24. Summary of privileges for REBIND PACKAGE (continued)


Option	Authorization required to run REBIND PACKAGE
REBIND PACKAGE with change of ownership. (An authorization ID that is not the original owner is specified in the OWNER keyword.)	<p>The new OWNER must have one of the following:</p> <ul style="list-style-type: none"> • BIND privilege on the package • PACKADM authority on the collection or on all collections • SYSADM or SYSCTRL authority <p>Specifying the OWNER: If any of the authorization IDs have the BINDAGENT privilege granted from the owner, then <i>authorization-id</i> can specify the grantor as OWNER. Otherwise, OWNER <i>authorization-id</i> must be one of the primary or secondary authorization IDs of the binder.</p>

For additional information on the authorization required to execute BIND PLAN, see Part 5 (Volume 2) of *DB2 Administration Guide*.

REBIND PACKAGE (DSN)

Syntax





Option descriptions

For descriptions of the options shown in the syntax diagram, see “Options of BIND and REBIND for PLAN, PACKAGE, and TRIGGER PACKAGE” on page 44.

Usage note

If you rebind multiple packages, DB2 commits each successful rebind before rebinding the next package.

Example

Rebind packages TEST.DSN8BC71.(MAY_VERSION) and PRODUCTION.DSN8BC71.(DEC_VERSION), both located at the local location USIBMSTODB22. The packages can run only from the CICS or the DLIBATCH environments if the connection ID is CON2. This replaces the CON1 specified on the BIND PACKAGE command.

```

REBIND PACKAGE (USIBMSTODB22.TEST.DSN8BC71.(MAY_VERSION),
                USIBMSTODB22.PRODUCTION.DSN8BC71.(DEC_VERSION)) -
  ENABLE (CICS,DLIBATCH) CICS (CON2)

```

REBIND PLAN (DSN)

The DSN subcommand REBIND PLAN rebinds an application plan when you make changes that affect the plan, but do not change the SQL statements in the programs. For example, you can use REBIND PLAN when you change authorizations, create a new index for the plan, or use RUNSTATS. If the rebind is successful, the process prepares an application plan and updates its description in the catalog table SYSPLAN.

REBIND PLAN is generally faster and more economical than BIND PLAN. But if you change the SQL statements or recompile a program, you should use BIND PLAN with the option ACTION(REPLACE).

For more information on using REBIND PLAN, see Part 5 of *DB2 Application Programming and SQL Guide*.

Environment

You can use REBIND PLAN through DB2I, or enter the REBIND PLAN subcommand from a DSN session running in foreground or background.

Data sharing scope: Group

Authorization

The plan owner must have authorization to execute *all* SQL statements embedded in the plan for REBIND PLAN to build a plan without producing error messages. For VALIDATE(BIND), DB2 verifies the authorization at bind time. For VALIDATE(RUN), DB2 verifies the authorization initially at bind time, but if the authorization check fails, DB2 rechecks it again at run time. If you use the PKLIST keyword, you must have EXECUTE authority for the packages or collections specified on PKLIST.

Table 25 explains the authorization required to run REBIND PLAN, depending on the options specified.

Table 25. Summary of privileges for REBIND PLAN

Option	Authorization required to run REBIND PLAN
REBIND PLAN with no change in ownership, because the OWNER keyword is not specified.	The authorization IDs of the process must have one of the following: <ul style="list-style-type: none">• Ownership of the plan• BIND privilege on the plan• BINDAGENT privilege from the owner of the plan• SYSADM or SYSCTRL authority
REBIND PLAN with no change in ownership, although the original owner is specified for the OWNER keyword.	The authorization IDs of the process must have one of the following: <ul style="list-style-type: none">• OWNER <i>authorization-id</i> must be one of the primary or secondary authorization IDs of the binder• BINDAGENT privilege from the owner of the plan• SYSADM or SYSCTRL authority


Table 25. Summary of privileges for REBIND PLAN (continued)

Option	Authorization required to run REBIND PLAN
REBIND PLAN with change of ownership. (An authorization ID that is not the original owner is specified in the OWNER keyword.)	<p>The new OWNER must have one of the following:</p> <ul style="list-style-type: none"> • BIND privilege on the plan • SYSADM or SYSCTRL authority <p>Specifying the OWNER: If any of the authorization IDs has the BINDAGENT privilege granted from the owner, then <i>authorization-id</i> can specify the grantor as OWNER. Otherwise, OWNER <i>authorization-id</i> must be one of the primary or secondary authorization IDs of the binder.</p>
PKLIST, specifying individual packages	<p>Authorization ID of the process must include one of the following:</p> <ul style="list-style-type: none"> • EXECUTE privilege on each package specified in the PKLIST • PACKADM authority on specific collections containing packages or on collection * • SYSADM authority
PKLIST, specifying (*), indicating all packages in the collection	<p>Authorization ID of the process must include one of the following:</p> <ul style="list-style-type: none"> • EXECUTE privilege on each package in the collection • EXECUTE privilege on <i>collection-id</i>.* • PACKADM authority on <i>collection-id</i> or on * • SYSADM authority

For additional information on the authorization required to execute REBIND PLAN, see Part 5 (Volume 2) of *DB2 Administration Guide*.


REBIND PLAN (DSN)

Syntax



Notes:

- 1 The **PATHDEFAULT** keyword is mutually exclusive with the **PATH** keyword. Do not specify both keywords in the same REBIND command.



Option descriptions

For descriptions of the options shown in the syntax diagram, see “Options of BIND and REBIND for PLAN, PACKAGE, and TRIGGER PACKAGE” on page 44.

Usage note

If you rebind multiple plans, DB2 commits each successful rebind before rebinding the next plan.

Example

Rebind plan DSN8BC71 to enable DB2 to take advantage of a newly created index. Use FLAG(W) to issue warning, error, and completion messages, but not informational messages. Use VALIDATE(BIND) to point out any error conditions during the bind process. Use ISOLATION(CS) to prevent other applications from changing the database values that this application uses only while the application is using them. This isolation level protects changed values until the application commits or terminates. Omit the OWNER keyword to leave the plan's owner authorization ID the same. Omit the ENABLE or DISABLE keywords to use the connections previously defined for the plan.

```

REBIND PLAN (DSN8BC71) -
  FLAG (W) -
  VALIDATE (BIND) -
  ISOLATION (CS)
  
```

REBIND TRIGGER PACKAGE (DSN)

The DSN subcommand REBIND TRIGGER PACKAGE rebinds a package that was created when DB2 executed a CREATE TRIGGER statement. You can use this subcommand to change a limited subset of the default bind options that DB2 used when creating the package. You might also rebind a trigger package to re-optimize its SQL statements after you create a new index or use the RUNSTATS utility. Additionally, you can rebind a trigger package if it has been marked invalid because an index, or another object it was dependent on, was dropped.

If the rebind is successful, the trigger package is marked valid. When REBIND TRIGGER PACKAGE(*) is issued, the rebind will affect all trigger packages that the issuer is authorized to rebind. Trigger packages cannot be rebound remotely. The location name is permitted when specifying the package name on a REBIND TRIGGER PACKAGE subcommand. However, the location name must not refer to a remote location.

For more information on using REBIND TRIGGER PACKAGE, see Part 5 of *DB2 Application Programming and SQL Guide*.

Environment

You can use REBIND TRIGGER PACKAGE through DB2I, or enter the REBIND TRIGGER PACKAGE subcommand from a DSN session that is running in foreground or background.

Data sharing scope: Group

Authorization

To build a package without producing error messages, the package owner must have authorization to execute *all* SQL statements that are embedded in the package for REBIND TRIGGER PACKAGE.

To execute this subcommand, the privilege set of the process must include one of the following authorities:


- Ownership of the trigger package
- BIND privilege on the trigger package
- BINDAGENT privilege from the owner of the trigger package
- PACKADM authority on the collection or on all collections
- SYSADM or SYSCTRL authority

When the trigger package is bound, the privileges of the current authorization ID are used when checking authority to bind statements within the triggered action. On REBIND TRIGGER PACKAGE, one of the following authorizations is needed:

- Ownership of the package
- BIND privilege on the package
- BINDAGENT privilege granted from owner
- PACKADM, SYSADM, or SYSCTRL

For additional information on the authorization required to execute REBIND TRIGGER PACKAGE, see Part 5 (Volume 2) of *DB2 Administration Guide*.

Syntax



Option descriptions

TRIGGER PACKAGE

Determines what trigger package or packages to rebind.

The following options identify the location, collection, and package name of the package. You can identify a location and collection. For REBIND TRIGGER, you must identify a trigger package name.

location-name

Identifies the current local location. Remote rebind of a trigger package is not allowed. *location-name* is the location of the DBMS where the package rebinds and where the description of the package resides.

The **default** is the local DBMS.

collection-id or *

Identifies the schema-name that already contains the trigger package to rebind. No default exists.

For REBIND TRIGGER, you can use an asterisk (*) to rebind all local packages with the specified *package-id* in all the collections for which you have bind privileges.

package-id or *

Identifies the name of the trigger package to rebind, as listed in the NAME column of the SYSPACKAGE catalog table. No default exists.

You can use the pattern-matching character (*) to rebind all local triggers in *collection-id* for which you have bind privileges.

For descriptions of the options shown in the syntax diagram, see “Options of BIND and REBIND for PLAN, PACKAGE, and TRIGGER PACKAGE” on page 44.

REBIND TRIGGER PACKAGE (DSN)

For more information about specifying schema names and trigger packages for the REBIND TRIGGER PACKAGE command, see Part 4 of *DB2 Application Programming and SQL Guide*.

Usage notes

Restrictions on trigger packages: A trigger package can be explicitly rebound, but it cannot be explicitly bound using the BIND PACKAGE subcommand.

A trigger package cannot be explicitly freed using the FREE PACKAGE subcommand or the DROP PACKAGE statement. Use the DROP TRIGGER statement to delete the trigger package.

A trigger package cannot be copied, and it can only be rebound locally. Remote rebind of a trigger package is not allowed.

Rebinding multiple trigger packages: If you rebind multiple trigger packages, DB2 commits each successful rebind before rebinding the next package.

Output

REBIND TRIGGER PACKAGE updates the COLLID and NAME columns in the SYSPACKAGE catalog table.

Example

Issue the following command to rebind trigger package TRIG1 in the ADMF001 collection of packages:

```
REBIND TRIGGER PACKAGE (ADMF001.TRIG1);
```

This command produces output similar to the following output:

```
DSNT254I - DSNTBRB2 REBIND OPTIONS FOR
          PACKAGE = STLEC1.ADMF001.TRIG1.()
          ACTION
          OWNER      ADMF001
          QUALIFIER   ADMF001
          VALIDATE    BIND
          EXPLAIN     NO
          ISOLATION   CS
          RELEASE     COMMIT
          COPY
DSNT255I - DSNTBRB2 REBIND OPTIONS FOR
          PACKAGE = STLEC1.ADMF001.TRIG1.()
          SQLERROR    NOPACKAGE
          CURRENTDATA YES
          DEGREE       1
          DYNAMICRULES BIND
          NODEFER      PREPARE
          NOREOPT      VARS
          KEEPDYNAMIC  NO
          DBPROTOCOL   DRDA
          QUERYOPT     1
          PATH
"SYSIBM","SYSFUN","SYSPROC","SYSADM","ADMF001"
DSNT232I - SUCCESSFUL REBIND FOR
          PACKAGE = STLEC1.ADMF001.TRIG1.()
```

-RECOVER BSDS (DB2)

The DB2 command RECOVER BSDS reestablishes dual bootstrap data sets (BSDS) after one has been disabled by a data set error. Follow these steps to reestablish dual BSDS mode:

1. Use access method services to rename or delete the failing BSDS, which DB2 has deallocated, and define a new BSDS with the same name as the failing BSDS. You can find control statements in job DSNTIJIN.
2. Issue the DB2 command RECOVER BSDS to make a copy of the good BSDS in the newly allocated data set and to reinstate dual BSDS mode.

Abbreviation: -REC BSDS

Environment

This command can be issued from an MVS console, a DSN session, a DB2I panel (DB2 COMMANDS), an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

Data sharing scope: Member

Authorization

To execute this command, the privilege set of the process must include one of the following:

- BSDS privilege
- SYSCTRL or SYSADM authority

DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.

Syntax

►►—RECOVER BSDS—◄◄

Usage note

-RECOVER BSDS following a BSDS I/O error: For a detailed description of steps the installation must take to reestablish dual BSDS mode after a BSDS I/O error occurs, see Part 4 (Volume 1) of *DB2 Administration Guide*.

Example

Reestablish dual BSDS mode.

-RECOVER BSDS

-RECOVER INDOUBT (DB2)

-RECOVER INDOUBT (DB2)

The DB2 command RECOVER INDOUBT recovers threads left indoubt because DB2 or a transaction manager could not automatically resolve the indoubt status with the commit coordinator.

This command should only be used when automatic resolution will not work. It is also critical that the commit/abort decision (that is made by the coordinator) must be determined.

Abbreviation: -REC IND

Environment

This command can be issued from an MVS console, a DSN session, a DB2I panel (DB2 COMMANDS), an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

Data sharing scope: Member


Authorization

To execute this command, the privilege set of the process must include one of the following:

- RECOVER privilege
- SYSOPR, SYSCTRL, or SYSADM authority

DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.

Syntax



Option descriptions

(connection-name)

Is a one- to eight-character connection name. Allied threads (including those that are distributed) belonging to that connection name are recovered. This parameter is ignored if LUWID is specified.

-RECOVER INDOUBT (DB2)

The **default** is the connection name from which you enter the command. If you enter this command from an MVS console, and you are recovering an allied thread using the ID or NID parameter, you *must* supply a connection name; no default is available.

ACTION

Tells whether to commit or cancel the indoubt thread. If there are any downstream participants for which the local thread is the coordinator, then the commit or abort decision is propagated to these participants.

Abbreviation: ACT

(COMMIT)

Commits the thread.

(ABORT)

Cancels the thread.

ID(*correlation-id*, ...)

Tells whether to recover a specific allied thread or all allied threads (including those that are distributed) associated with the connection name.

correlation-id

Is the correlation ID (of 1 to 12 characters) of a specific thread to be recovered. If you use more than one correlation ID, separate items in the list by commas.

Do not use a correlation ID that has more than one network ID associated with it. Instead, use the NID option.

- (*) Recovers all indoubt threads associated with the connection name. Even threads having the same correlation ID are resolved.

NID(*network-id*, ...)

Identifies threads by their network IDs.

network-id is a network ID associated with an individual thread. You can use more than one network ID for the same connection name.

For IMS and CICS connections, a network ID is the name of the form *net-node.number*, from 3 to 25 characters in length.

- *net-node* is the network node name of the system that originated the unit of work. It uses from 1 to 8 characters.
- *number* is a unique number within the system of origin. It uses from 1 to 16 characters.

For RRSF connections, a network ID is the OS/390 RRS unit of recovery ID (URID) that is used to uniquely identify a unit of work. An OS/390 RRS URID is a 32-character number.

The network ID appears on the recovery log of the commit coordinator as a unique identification of a unit of work. It uses 16 bytes.

- For IMS and CICS, the network ID is an 8-byte node name immediately followed by an 8-byte number.
- For RRSF connections, the network ID is a 16-byte number.

LUWID

Recovers the indoubt thread that has the specified LUWID.

-RECOVER INDOUBT (DB2)

luwid

Consists of an LU network name, an LUW instance number, and a commit sequence number.

The LU network name consists of a one- to eight-character network ID, a period, and a one- to eight-character network LU name. The LUW instance number consists of a period followed by 12 hex characters. The last element of the LUWID is the commit sequence number of 4 hex characters, preceded by a period.

token

A token is an alternate way to express an LUWID. DB2 assigns a token to each thread it creates. It is a one- to six-digit decimal number that appears after the equal sign in all DB2 messages that display a LUWID.

If you enter one to six decimal digits, DB2 assumes that you are supplying a token. The token that DB2 assigns to a specific LUWID is unique for that DB2 subsystem, but not necessarily unique across all subsystems.

Usage note

When to use a network ID: *network-id* is not normally needed, because *correlation-id* can identify indoubt threads. However, if *correlation-id* is not unique, *network-id* must be used. This statement does not apply if a LUWID is specified.

If a thread that is specified in the command is part of a global transaction, the command is executed against all threads in the global transaction. See the *DB2 Administration Guide* for an explanation of global transactions.

Examples

Example 1: Recover indoubt allied threads. Schedule a commit for all threads associated with the connection name from which the command is entered.

```
-RECOVER INDOUBT ACTION(COMMIT) ID(*)
```

Example 2: Recover an indoubt thread from a remote requester. Schedule a commit for the indoubt thread whose token is 1332.

```
-RECOVER INDOUBT ACTION(COMMIT) LUWID(1332)
```

Example 3: Recover indoubt threads from remote requesters. Schedule an abort for two indoubt threads. The first has an LUWID = DB2NET.LUNSITE0.A11A7D7B2057.0002. (The '0002' in the last segment of the LUWID represents the commit sequence number.) The second has a token = 442.

```
-RECOVER INDOUBT ACTION(ABORT)  
      LUWID (DB2NET.LUNSITE0.A11A7D7B2057.0002, 442)
```


-RECOVER POSTPONED (DB2)

The DB2 command RECOVER POSTPONED completes back-out processing for units of recovery that are left incomplete during an earlier restart (POSTPONED ABORT units of recovery). Use this command when automatic resolution was not selected.

Abbreviation: -REC POST

Environment

This command can be issued from an MVS console, a DSN session, a DB2I panel (DB2 COMMANDS), or an IMS or CICS terminal.

Data sharing scope: Member


Authorization

To execute this command, the privilege set of the process must include one of the following authorities:

- RECOVER privilege
- SYSOPR, SYSCTRL, or SYSADM authority

DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.

Syntax



Option descriptions

CANCEL

Specifies to stop DB2 processing of all postponed abort units of recovery immediately. Cancelling postponed abort units of recovery leaves objects in an inconsistent state.

Objects that the postponed units of recovery modify are recovered (backed out). If back out processing fails, the objects are marked REFRESH PENDING (REFP) and either RECOVER PENDING (RECP) or REBUILD PENDING (RBDP or PSRBD) in the database exception table. Resolve the REFP status of the object by running the RECOVER utility to recover the object to a prior point in time or by running LOAD REPLACE on the object.

Usage note

Recovery action: Recovery (rollback) action is always taken for all POSTPONED ABORT units of recovery.

Output

The output from -RECOVER POSTPONED consists of informational messages only.

-RECOVER POSTPONED (DB2)

Progression of -RECOVER POSTPONED: Message DSN1024I indicates the completion of back-out work against the page set or partition, and the removal of the page set or partition from the restart-pending status.

If backout processing lasts for an extended period, progress message DSNR047I is
displayed at periodic intervals until backout processing is complete.

DB2 issues message DSN9022I after successful completion of the -RECOVER POSTPONED command, or message DSN9023I if the command completed unsuccessfully. Message DSNV434I indicates that -RECOVER POSTPONED was issued when no postponed-abort units of recovery needed to be resolved.

Example

Issue the following command to recover postponed-abort units of recovery.

```
-RECOVER POSTPONED
```

If postponed-abort units of recovery are found, output similar to the following output is generated:

```
DSNV435I - RESOLUTION OF POSTPONED ABORT URS HAS BEEN SCHEDULED
DSNI024I - DSNIARPL BACKOUT PROCESSING HAS COMPLETED
           FOR PAGESET DBKD0103.IPKD013A PART 00000004.
DSNI024I - DSNIARPL BACKOUT PROCESSING HAS COMPLETED
           FOR PAGESET DBKD0103.TPKD0103 PART 00000004.
DSNI024I - DSNIARPL BACKOUT PROCESSING HAS COMPLETED
           FOR PAGESET DBKD0103.IXKD013C PART (n/a).
DSNI024I - DSNIARPL BACKOUT PROCESSING HAS COMPLETED
           FOR PAGESET DBKD0103.IUKD013B PART (n/a).
DSNI024I - DSNIARPL BACKOUT PROCESSING HAS COMPLETED
           FOR PAGESET DBKD0103.IPKD013A PART 00000002.
DSNI024I - DSNIARPL BACKOUT PROCESSING HAS COMPLETED
           FOR PAGESET DBKD0103.TPKD0103 PART 00000002.
DSNI024I - DSNIARPL BACKOUT PROCESSING HAS COMPLETED
           FOR PAGESET DBKD0101.IXKD011C PART (n/a).
DSNI024I - DSNIARPL BACKOUT PROCESSING HAS COMPLETED
           FOR PAGESET DBKD0101.IXKD011B PART (n/a).
DSNI024I - DSNIARPL BACKOUT PROCESSING HAS COMPLETED
           FOR PAGESET DBKD0101.IUKD011A PART (n/a).
DSNI024I - DSNIARPL BACKOUT PROCESSING HAS COMPLETED
           FOR PAGESET DBKD0101.TLKD0101 PART (n/a).
DSN9022I - DSNVRP 'RECOVER POSTPONED' NORMAL COMPLETION
```

If no postponed units of recovery are found, the following output is returned:

```
DSNV434I - DSNVRP NO POSTPONED ABORT THREADS FOUND
DSN9022I - DSNVRP 'RECOVER POSTPONED' NORMAL COMPLETION
```

-RESET GENERICLU (DB2)

The RESET GENERICLU command allows you to purge information stored by VTAM in the coupling facility for one or more partners of a particular DB2 subsystem. The command must be issued from the DB2 that has the VTAM affinity to the particular partner LU whose information you are purging.

Abbreviation: -RESET GENERIC

Environment

This command can be issued from an MVS console, a DSN session under TSO, a DB2I panel (DB2 COMMANDS), an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

Data sharing scope: Member


Authorization

To execute this command, the privilege set of the process must include one of the following:

- SYSOPR authority
- SYSCTRL authority
- SYSADM authority

DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.

Syntax



Option descriptions

(luname)

Specifies the real VTAM LU name of the partner whose generic LU name mapping is being purged. The NETID of this partner LU must be the same as the local DB2 NETID.

(netid.luname)

Indicates the VTAM shared memory information associated with the specified NETID and LUNAME is purged.

(*) Purges the VTAM shared memory information for all partners of this DB2 subsystem. This command option should only be used if you are planning to remove this DB2 subsystem from the DB2 group.

Usage notes

The following conditions must be satisfied for the RESET GENERICLU command to be successful:

-RESET GENERICLU (DB2)

- DDF must be started.
- No VTAM sessions can be active to the partner LU specified on the command.
- DB2 must not have any indoubt thread resolution information associated with the specified partner LU.

Examples

Example 1: Purge the VTAM generic name mapping associated with partner NET1.USER5LU.

```
-DB2A RESET GENERICLU(NET1.USER5LU)
```

Example 2: Purge the VTAM generic name mappings for all LUs that are partners of this DB2 subsystem. Use this version of the command only when removing this DB2 from the data sharing group.

```
-DB2A RESET GENERICLU(*)
```

-RESET INDOUBT (DB2)

The DB2 command RESET INDOUBT purges information displayed in the indoubt thread report generated by the DISPLAY THREAD command.

This command *must* be used to purge indoubt thread information in the following situations:

- For threads where DB2 has a coordinator responsibility that it cannot fulfill because of participant cold start, sync point protocol errors, or indoubt resolution protocol errors.
- For threads that were indoubt but were resolved with the RECOVER INDOUBT command, and subsequent resynchronization with the coordinator shows heuristic damage.

The RESET column of a display thread report for indoubt threads indicates whether information in the report must be purged with this command.

This command can also be used to purge indoubt thread information for threads where:

- DB2 has a coordinator responsibility even when no errors have been detected that preclude automatic resolution with the participants. The FORCE keyword must be specified to purge this information. Resynchronization with affected participants is not performed.
- DB2 has a participant responsibility even when no errors have been detected that preclude automatic resolution with the coordinator. Resynchronization with the coordinator will not be performed.

Abbreviation: -RESET IND

Environment

This command can be issued from an MVS console, a DSN session under TSO, a DB2I panel (DB2 COMMANDS), an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

Data sharing scope: Member

Authorization


To execute this command, the privilege set of the process must include one of the following:

- RECOVER privilege
- SYSOPR, SYSCTRL, or SYSADM authority

DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.

-RESET INDOUBT (DB2)

Syntax



Option descriptions

LUNAME(luname, ...)

Purges all qualifying indoubt information that pertains to the named LUNAME.

luname

Is expressed as a one- to eight-character name. If you use more than one LUNAME, separate items in the list by commas.

(*) Purges indoubt information for all SNA locations.

FORCE

Forces the purging of coordinator and participant indoubt resolution responsibility even when no errors that preclude automatic resolution have been detected. FORCE can be used in conjunction with IPADDR or LUNAME.

Purging resynchronization information when no errors that preclude automatic resynchronization have been detected simulates a cold start. Thus, no connections can exist between DB2 and the named partner when this command is executed. After execution of the FORCE option, the next connection with the named partner location will be a cold start connection. If a connection with the named partner exists at the time this command is executed, execution fails with message DSNL448I.

FORCE can be used to bypass warm start connectivity problems when errors occurring in the recovery log name exchange result in the partner refusing the connection attempt.

LOCATION(location-name, ...)

Purges all qualifying indoubt information pertaining to the named location.

location-name is expressed as a 1- to 16-character name, and identifies the partner, whether it is a requester or server. If the partner is not a DB2 for OS/390 and z/OS subsystem, the location name may be expressed as a:

- One- to eight-character luname, as defined to VTAM at the server location. This name must be enclosed with the less than (<) and the greater than (>) characters to distinguish it from a DB2 location name.
- Dotted decimal TCP/IP address.

IPADDR(*nnn.nnn.nnn.nnn:port*)

Purges all qualifying indoubt information pertaining to the dotted decimal IP address that is associated with the resync port number.

This keyword can be used in place of the LUNAME keyword when the partner uses TCP/IP instead of SNA.

nnn.nnn.nnn.nnn:port

Is the dotted decimal IP address of the remote site followed by the resync port number. If you use more than one IP address and port, use commas to separate the items in the list.

(*) Purges indoubt information for all TCP/IP locations.

LUWID

Purges indoubt information for the thread with the specified LUWID.

luwid

Consists of an LU network name, an LUW instance number, and a commit sequence number.

The LU network name consists of a 1- to 8-character network ID, a period, and a 1- to 8-character network LU name. The LUW instance number consists of a period followed by 12 hex characters. The last element of the LUWID is the commit sequence number, of 4 hex characters, preceded by a period.

token

A token is an alternate way to express an LUWID. DB2 assigns a token to each thread it creates. It is a one- to six-digit decimal number that appears after the equal sign in all DB2 messages that display an LUWID.

If you enter one to six decimal digits, DB2 assumes that you are supplying a token. The token that DB2 assigns to a specific LUWID is unique for that DB2 subsystem, but not necessarily unique across all subsystems.

Output

The response from this command includes any of the messages from DSNL440I through DSNL449I.

If you specify RESET INDOUBT incorrectly, you receive message DSNL440I.

Usage notes

Purging participant indoubt information: Be cautious when using the FORCE option to purge participant indoubt information. Normally, after the use of the RECOVER INDOUBT command, automatic resolution with the coordinator determines if heuristic damage has occurred. This detection is lost if RESET INDOUBT is used before automatic resolution with the coordinator can be achieved.

Purging coordinator indoubt information: Be cautious when using the FORCE option to purge coordinator indoubt information when no errors are precluding automatic resolution. When the information is purged, any participant that is indoubt is forced to use a heuristic decision process to resolve the indoubt logical unit of work.

RUN (DSN)

RUN (DSN)

The DSN subcommand RUN executes an application program, which can contain SQL statements.

Environment

This subcommand can be issued under the DSN command processor running in either foreground or background mode, or it can be issued using the DB2I RUN panel.

Data sharing scope: Member


Authorization

To execute this command, the privilege set of the process must include one of the following:

- EXECUTE privilege on the plan
- Ownership of the plan
- SYSADM authority

To run an application, the plan must be enabled for your local server. Any associated packages from which you execute statements must also be enabled.

Syntax



Option descriptions

Use at least one of the two following clauses, but do not use the same clause twice.

PROGRAM (*program-name*)

Identifies the program you want to run.

CP

Directs input to the user's command processor, and causes a prompt to be issued: 'ENTER TSO COMMAND'. This is useful for running command processors and debugging programs (for example, COBTEST).

Processing the specified TSO command creates a new task control structure under which the TSO command executes. All application programs initiated from this TSO command session also execute under the same task structure, and must establish a new connection to DB2 if they use SQL requests.

When the TSO command completes, the new task structure is terminated, and control is returned to the original DB2 connection and task structure established by the DSN command.

Later TSO commands can be issued directly from the DSN session, or through the RUN subcommand with the CP option.

PLAN(*plan-name*)

Is optional after PROGRAM, but required after CP.

plan-name is the name of the application plan for the program.

When PROGRAM is used, the **default** plan name is *program-name*.

LIBRARY(*library-name*)

Specifies the name of the data set containing the program to be run.

If *library-name* is not specified, normal MVS library searching is used. The data sets specified in the STEPLIB DD statements are first searched for the entry point name of the program. If STEPLIB is not present, then the data sets specified in the JOBLIB DD statements are searched. If the entry point name is not found there, then the link list is searched.

Subprograms: Normal MVS library searching is **always** used for any subprograms loaded by the main program. If the subprograms reside in the same library as the main program, then library-name must also be defined for the normal MVS search pattern (STEPLIB, JOBLIB, link list). If a library defined in that way contains both the main program and any loaded subprograms, then you need not use the LIBRARY option.

PARMS(*parameter-string*)

parameter-string is a list of parameters that are to be passed to your application program. Separate items in the list by commas, blanks, or both, and enclose the list between apostrophes. If the list contains apostrophes, represent each of them by two consecutive apostrophes. The list is passed as a varying-length character string of a minimum of 1 to a maximum of 100 decimal characters.

For Assembler: Use a list of the form 'program parameters'. There are no run-time parameters.

No run-time or application parameter validation is performed by the RUN subcommand on the *parameter-string* passed to your application program. All specified parameter values are assumed to adhere to the parameter syntax and format criteria defined by the language in which the application program is written.

For COBOL: If Language Environment is not the run-time environment, use a list of the form B/A, where B represents a list of parameters for the COBOL application program, and A represents a list of run-time options. If program parameters are not needed, write the list in the form of /A.

If Language Environment is the run-time environment, use a list of the form A/B, where A represents a list of run-time options, and B represents a list of parameters for the COBOL application program. If run-time options are not needed, write the list in the form of /B. For compatibility, Language Environment provides the CBLOPTS run-time option. When CBLOPT(YES) is specified in CEEDOPT or CEEUOPT and the main routine is COBOL, specify the list in the form of B/A, the same form as when the run-time environment is not Language Environment CBLOPT(NO) is the default.

For Fortran: Use a list of the form A/B, where A represents a list of Fortran run-time options and B represents a list of parameters for the Fortran application program. If Fortran run-time options are not needed, write the list in the form of B or /B. The second form must be used if a slash is present within the program arguments. If only Fortran run-time options are present, write the list in the form of A/.

For PL/I: Use a list of the form A/B, where A represents a list of run-time options, and B represents a list of parameters for the PL/I application program.

RUN (DSN)

If run-time options are not needed, write the list in the form /B. If the PL/I NOEXECOPS procedure option is specified, omit the "/". System message IBM003I indicates that either you have omitted the slash, or the value passed to the PL/I run-time package was not valid.

For C: Use a list of the form A/B, where A represents a list of run-time options, and B represents a list of parameters for the C application program. If run-time options are not needed, write the list in the form /B. If the NOEXECOPS run-time option is in effect, omit the "/".

Usage note

Multitasking restriction: When running a program that uses a multitasking environment, the first task to issue an SQL statement must issue all subsequent SQL calls. That is, only one task in a multitasking environment can issue SQL calls. This task must be a subtask of, or running at the same TCB level as, the DSN main program.

Examples

Example 1: Run application program DSN8BC4. The application plan has the same name. The program is in library 'prefix.RUNLIB.LOAD'.

```
DSN SYSTEM (DSN)
RUN PROGRAM (DSN8BC4) LIB ('prefix.RUNLIB.LOAD')
```

Example 2: Run application program DSN8BP4. The application plan is DSN8BE71. The program is in library 'prefix.RUNLIB.LOAD'. Pass the parameter O'TOOLE to the PL/I application program with no PL/I run-time options.

```
DSN SYSTEM (DSN)
RUN PROGRAM (DSN8BP4) PLAN (DSN8BE71) -
  LIB ('prefix.RUNLIB.LOAD') PARMS ('/O'TOOLE')
```

-SET ARCHIVE (DB2)

The DB2 command SET ARCHIVE sets the upper limit for the number of and the deallocation time of tape units for the archive log. This command overrules the values specified during installation or in a previous invocation of the SET ARCHIVE command. The changes that SET ARCHIVE makes are temporary; at restart, DB2 again uses the values set during installation.

Abbreviation: -SET ARC

Environment

This command can be issued from an MVS console, a DSN session under TSO, a DB2I panel (DB2 COMMANDS), an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

Data sharing scope: Member


Authorization

To execute this command, the privilege set of the process must include one of the following:

- ARCHIVE privilege
- SYSOPR, SYSCTRL, or SYSADM authority

DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.

Syntax



Option descriptions

The following options overrule the READ TAPE UNITS(COUNT) and DEALLC PERIOD TIME subsystem parameters specified at installation.

COUNT(integer)

Specifies the maximum number of tape units that can be dedicated to reading archive logs. This value affects the allowed concurrent reads for unique archive data sets residing on tapes.

integer can range from 1 to 99.

- If the number specified is greater than the current specification, the maximum number of tape units allowable for reading archive logs increases.
- If the number specified is less than the current specification, tape units that are not being used are immediately deallocated to adjust to the new COUNT

-SET ARCHIVE (DB2)

value. Active (or premounted) tape units remain allocated; a tape unit is a candidate for deallocation because of a lowered COUNT value only if there is no activity for the unit.

TIME

Specifies the length of time during which an allocated archive read tape unit is allowed to remain unused before it is deallocated.

(minutes)

Specifies the maximum number of minutes.

minutes must be an integer between 0 and 1439.

(seconds)

Specifies the maximum number of seconds.

seconds must be an integer between 1 and 59.

(NOLIMIT) or (1440)

Indicates that the tape unit will never be deallocated. Specifying TIME(1440) is equivalent to TIME(NOLIMIT). The seconds specification is not allowed when you specify that TIME is 1440.

DEFAULT

Resets the COUNT and TIME parameters back to the values that were specified during DB2 installation.

Usage notes

Archive tape reading performance: To achieve the best performance for reading archive tapes, specify the maximum values allowed (within system constraints) for both the COUNT and TIME options.

IEF238D “REPLY DEVICE NAME OR CANCEL”: Replying “CANCEL” to this message resets the COUNT value to the current number of tape units. For example, if the current COUNT value is 10, but you reply “CANCEL” to the request for the seventh tape unit, the COUNT value is reset to 6.

Delaying tape deallocation in a data sharing environment: When you submit a recover job on a member of a data sharing group that requires a tape unit that must remain unused for a certain length of time before being deallocated, the archive tape is not available to any other members of the group until the specified time has expired. Unless all recover jobs will be submitted from the same member, you might not want to use the COUNT option and ensure that field DEALLOC PERIOD on installation panel DSN TIP A has a value of 0.

Output

The response from this command includes any of the messages from DSNJ334I through DSNJ337I.

Examples

Example 1: Allocate two tape units that can remain unused for 30 seconds before they are deallocated.

```
-SET ARCHIVE COUNT(2) TIME(,30)
```

Example 2: Allocate four tape units that can remain unused for 2 minutes before they are deallocated.

```
-SET ARCHIVE COUNT(4) TIME(2)
```

Example 3: Allocate one tape unit that is never deallocated.

```
-SET ARCHIVE COUNT(1) TIME(1440)
```

-SET SYSPARM (DB2)

-SET SYSPARM (DB2)

The DB2 command SET SYSPARM lets you change subsystem parameters while DB2 is up.

Environment


This command can be issued from an MVS console, a DSN session under TSO, a DB2I panel (DB2 COMMANDS), an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

Data sharing scope: Member

Authorization

To execute this command, the privilege set of the process must include SYSOPR, SYSCTRL, or SYSADM authorities. DB2 commands that are issued from an MVS console are not associated with any secondary authorization IDs.

Syntax



Option descriptions

LOAD(*load-module-name*)

Specifies the name of the load module to load into storage. The default load module is **DSNZPARM**.

RELOAD

Reloads the last named subsystem parameter load module into storage.

STARTUP

Resets loaded parameters to their startup values.

Usage notes

To update the subsystem parameters on a subsystem, follow these steps:

1. Run through the installation process in Update mode.
2. Produce a new subsystem parameter load module.
3. Issue the SET SYSPARM command.

Examples

Example 1: Change from DSNZPARM to ADMPARM1

```
-SET SYSPARM LOAD(ADMPARM1)
```

Example 2: Reload ADMPARM1

```
-SET SYSPARM RELOAD
```

Example 3: Reload the subsystem parameters that the DB2 subsystem loaded at startup

-SET SYSPARM (DB2)

```
| -SET SYSPARM STARTUP  
|
```

-SET LOG (DB2)

The DB2 command SET LOG modifies the checkpoint frequency specified during installation. This command also overrides the value that was specified in a previous invocation of the SET LOG command. The changes that SET LOG makes are temporary; at restart, DB2 again uses the values that were set during installation. The new LOGLOAD value takes affect following the next system checkpoint.

Environment

This command can be issued from an MVS console, a DSN session under TSO, a DB2I panel (DB2 COMMANDS), an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

Data sharing scope: Member

Authorization

To execute this command, the privilege set of the process must include one of the following authorities:

- ARCHIVE privilege
- SYSOPR, SYSCTRL, or SYSADM authority

DB2 commands that are issued from an MVS console are not associated with any secondary authorization IDs.

Syntax



Option descriptions

The following option overrides the LOGLOAD subsystem parameter that is specified in the CHECKPOINT FREQ field on panel DSNTIPN at installation.

LOGLOAD(integer)

Specifies the number of log records that DB2 writes between the start of successive checkpoints. You can optionally specify a value of 0 to initiate a system checkpoint without modifying the current LOGLOAD value.

integer can be 0, or within the range from 200 to 16000000.

CHKTIME(integer)

Specifies the number of minutes between the start of successive checkpoints. This option overrides log records specified by installation options or the LOGLOAD option that are based on checkpoint frequency.

integer can be any integer value from 0 to 60. Specifying 0 starts a system checkpoint immediately without modifying the checkpoint frequency.

SUSPEND

Specifies to suspend logging and update activity for the current DB2 subsystem until SET LOG RESUME is issued. DB2 externalizes unwritten log buffers, takes a system checkpoint (in non-data sharing environments), updates the

SET LOG (DB2)

BSDS with the high-written RBA, then suspends the update activity. Message DSNJ372I is issued and remains on the console until update activity resumes.

This option is not allowed when a system quiesce is active by either the ARCHIVE LOG or STOP DB2 commands. Update activity remains suspended until SET LOG RESUME or STOP DB2 is issued. (Also, once logging is suspended, do not issue the ARCHIVE LOG command without also specifying CANCEL OFFLOAD).

Recommendation: Do not keep log activity suspended during periods of high activity or for long periods of time. Suspending update activity can cause timing-related events such as lock timeouts or DB2 and IRLM diagnostic dumps.

RESUME

Specifies to resume logging and update activity for the current DB2 subsystem and remove the message DSNJ372I from the console.

Recommendation: Issue this command from an MVS console or from the install SYSADM ID to avoid possible contention during command authorization checking. When logging has been suspended by the -SET LOG SUSPEND command, the contention generated by holding the log write latch can cause command authorization checking to hang until logging has been resumed.

Usage notes

How LOGLOAD and CHKTIME values affect DB2 performance: LOGLOAD and CHKTIME values can affect the amount of time needed to restart DB2 after abnormal termination. A large value for either option can result in lengthy restart times. A low value can result in excessive checkpointing. However, When you specify LOGLOAD(0) or CHKTIME(0), the checkpoint request is synchronous when issued from a batch job, and asynchronous when issued from an MVS or TSO console.

Use the DISPLAY LOG command to display the current LOGLOAD setting.

The value that you specify for LOGLOAD or CHKTIME is reset to the value specified in the subsystem parameter when DB2 is restarted. If you load a different value by issuing the command SET SYSPARM, the new value is used.

When to suspend logging: Specify SET LOG SUSPEND before making a remote copy of the entire database and logs for a system-level, point-in-time recovery or disaster recovery. You can make remote copies with peer-to-peer remote recovery (PPRC) and FlashCopy. Suspending logging to make a remote copy of the database lets you avoid quiescing update activity. Read-only activity continues while logging is suspended.

The backup made between the SET LOG SUSPEND and the SET LOG RESUME window might contain uncommitted data. If you must restore the entire DB2 subsystem to the time when the log was suspended, restore the entire database and logs from the backup, then restart DB2 to recover the entire DB2 subsystem to a consistent state. For details, see Part 4 (Volume 1) of *DB2 Administration Guide*.

Examples

Example 1: Initiate a system checkpoint without modifying the current LOGLOAD value.

```
-SET LOG LOGLOAD(0)
```

SET LOG (DB2)

Example 2: Modify the system checkpoint interval to every 150000 log records.

```
-SET LOG LOGLOAD(150000)
```

Example 3: Suspend logging activity.

```
-SET LOG SUSPEND
```

Example 4: Resume logging activity.

```
-SET LOG RESUME
```

SPUFI (DSN)

The DSN subcommand SPUFI executes the SQL processor using file input.

Environment

You can use this subcommand only under ISPF. You can issue it from ISPF option 6, or from a CLIST.

Data sharing scope: Member

Authorization

None is required.

Syntax

```
►►—SPUFI—◄◄
```

Usage notes

SPUFI session: The effect of the SPUFI subcommand is to execute SPUFI and to present the SPUFI panel as the start of a SPUFI session. For a description of the panel and instructions on using SPUFI, see Part 1 of *DB2 Application Programming and SQL Guide*.

In the SPUFI session, you can access the CURRENT SPUFI DEFAULTS panel. You can change DB2I defaults by splitting the screen and accessing the DB2I DEFAULTS panel, or by changing the defaults before starting the SPUFI session.

SPUFI panel variables: The SPUFI panel variables you enter after invoking SPUFI directly with the DSN command are not saved in the same place. Panel variables therefore vary depending on whether you execute the facility directly, or through DB2I.

/SSR (IMS)

/SSR (IMS)

The IMS /SSR command allows the IMS operator to enter an external subsystem command.

Environment

This command can be issued only from an IMS terminal.

Data sharing scope: Member

Authorization

This command requires an appropriate level of IMS authority, as described in the *IMS Administration Guide: System*.

In addition, the set of privileges held by the primary authorization ID or any of the secondary authorization IDs must include the authority to enter the DB2 command that follows /SSR. For a description of the privileges required to issue a DB2 command, see the description of the appropriate DB2 command in this book.

Syntax

►►—/SSR—*subsystem-command*—◄◄

Option description

subsystem-command

Specifies a valid subsystem command. The first character following /SSR must be the subsystem recognition character of the subsystem to which the command is to be directed (DB2).⁴

Usage note

Routing the command: IMS uses the command recognition character (CRC) to determine which external subsystem, in this case DB2, receives the command. The only action taken by IMS is to route the command to the appropriate subsystem.

4. The subsystem recognition character is defined in the IMS SSM member for the external subsystem.

/START (IMS)

The IMS /START command (with the SUBSYS parameter) makes connection between IMS and the specified external subsystem available. Establishing the connection allows application programs to access resources managed by the external subsystem.

The following is only a partial description of the /START command. For a complete description, see *IMS Command Reference*.

Environment


This command can be issued only from an IMS terminal.

Data sharing scope: Member

Authorization

This command requires an appropriate level of IMS authority, as described in the *IMS Administration Guide: System*.

Syntax



Option descriptions

SUBSYS

Specifies one or more names of external subsystems to be connected to IMS, or all external subsystems.

subsystem-name, ...

Identifies one or more names of external subsystems to be connected to IMS.

ALL

Indicates that all external subsystems are to be connected to IMS.

Usage note

Inactive entries: The copy in main storage of the external subsystem PROCLIB entry is refreshed as part of /START command function when that entry is not active (that is, when the connection does not exist). This allows the installation to stop the subsystem connection, change the specifications in the PROCLIB entry, then restart the subsystem connection without bringing down IMS.

-START DATABASE (DB2)

-START DATABASE (DB2)

The DB2 command START DATABASE is typically used after a previous STOP DATABASE command, or after a table space, partition, or index has been placed in group buffer pool RECOVER pending status (GRECP), or if pages have been put on the logical page list (LPL) for that object. This command makes the specified database available for use. Depending on the options you specify, the database can be made available for read-only processing, read-write processing, or utility-only processing.

In a data sharing environment, the command can be issued from any DB2 on the group that has access to the database.

Abbreviation: -STA DB

Environment

This command can be issued from an MVS console, a DSN session, a DB2I panel (DB2 COMMANDS), an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

Data sharing scope: Group

Authorization

All databases specified for which the privilege set of the process has the STARTDB privilege are started. The privilege set of the process must include one of the following:

- STARTDB privilege
- DBMAINT, DBCTRL, or DBADM authority
- SYSCTRL or SYSADM authority


When this set does not contain the STARTDB privilege for a specified database, an error message is issued.

DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.

When data definition control is active, installation SYSOPR or installation SYSADM authority is required to start the database, a table space, or an index space containing a registration table or index.

Database DSNDB06 contains the table spaces and index spaces required to check the authorization for using START DATABASE. If a table or index space required for this authorization check is stopped, or is unavailable because it is in LPL or GRECP status, then installation SYSADM authority is required to start any data base, table space, or index space, including the ones required for the authorization check. Installation SYSOPR authority may also start DSNDB06 but only when in LPL or GRECP status and if access mode is not changed.

Syntax



Option descriptions

(*database-name*, ...)

Is the name of a database, or database for the table spaces or index spaces that are to be started. If you use more than one name, separate names in the list by commas.

- (*) Starts all databases for which the privilege set of the process has at least DBMAINT authority (except databases that are already started). You cannot use (*) with ACCESS(FORCE).

You can start DSNDB01, DSNDB06, and work file databases, such as DSNDB07, only by specifying them explicitly (for example, START DATABASE(DSNDB01)).

dbname and *dbstring* can have any of the forms in the following list (where *dbname1* and *dbname2* represent any strings of from 1 to 8 characters, and *dbname* represents any string of from 1 to 7 characters):

Form Starts

dbname1:dbname2

All databases whose names collate greater than or equal to *dbname1* and less than or equal to *dbname2*

dbname*

All databases whose names begin with the string *dbname*

-START DATABASE (DB2)

***dbname**

All databases whose names end with the string *dbname*

dbname

All databases whose names contain the string *dbname*

dbstring1*dbstring2

All databases whose names contain the strings *dbstring1* and *dbstring2*

SPACENAM

Tells what particular table spaces or indexes within the database are to be started. If you use ACCESS(FORCE), you must use SPACENAM with a list of table space and index names.

Abbreviation: SPACE, SP

(space-name, ...)

Is the name of a table space or index space that is to be started. You can use a list of several names of table spaces and index spaces. Separate names in the list by commas.

You can write *space-name* like *database-name* to designate:

- The name of a single table space or index space
- A range of names
- A partial name, including a beginning or ending pattern-matching character (*), a pattern-matching character (*) between two strings, or any combination of these uses.⁵

You cannot use a partial name or range of names with the ACCESS(FORCE) option.

(*) Starts all table spaces and index spaces in the specified database. You cannot use (*) with ACCESS(FORCE).

spacename and *spacestring* can have any of the forms in the following list (where *spacename1* and *spacename2* represent any strings of from 1 to 8 characters, and *spacename* represents any string of from 1 to 7 characters):

Form Displays the status of

spacename1:spacename2

All table spaces or index spaces whose names collate greater than or equal to *spacename1* and less than or equal to *spacename2*

spacename*

All table spaces or index spaces whose names begin with the string *spacename*

***spacename**

All table spaces or index spaces whose names end with the string *spacename*

spacename

All table spaces or index spaces whose names contain the string *spacename*

spacestring1*spacestring2

All table spaces or index spaces whose names contain the strings *spacestring1* and *spacestring2*

5. Consecutive pattern-matching characters (*) are not allowed, and you cannot specify two pattern-matching characters (*) in the middle of a keyword string.

PART (*integer*, ...)

Indicates the partition number of one or more partitions, within the specified table space or index, that are to be started. The start or stop state of other partitions does not change.

The *integer* specified must identify a valid partition number for the corresponding space name and database name. If you specify nonvalid partition numbers, you receive an error message for each nonvalid number, but all other valid partitions that you specified are started.

integer can be written to designate either:

- A list of one or more partitions, or
- A range of all partition numbers that collate greater than or equal to *integer1* and less than or equal to *integer2*

Both a list and a range cannot be specified.

The PART option is valid with partitioned table spaces, partitioned indexes, and nonpartitioned type 2 indexes of partitioned table spaces. If you specify PART with a nonpartitioned table space or index on a nonpartitioned table space, you receive an error message, and the nonpartitioned space is not started.

ACCESS

Tells whether the objects started can be read from and written to, read from only, or accessed by utilities only.

Abbreviation: ACC

(RW)

Allows programs to read from or write to the specified databases, table spaces, indexes, or partitions.

(RO)

Allows programs to only read from the specified databases, table spaces, indexes, or partitions. Any programs attempting to change data will not succeed. Do not use this option for a database for declared temporary tables (databases created with the AS TEMP option).

(UT)

Allows only DB2 online utilities to access the specified databases, table spaces, indexes, or partitions.

(FORCE)

Resets any indications that a table space, index, or partition is unavailable because of pages in the logical page list, pending deferred restarts, write error ranges, read-only accesses, or utility controls. FORCE also resets the CHECK pending, COPY pending, and RECOVER pending states. Full access to the data is forced. FORCE cannot be used to reset the restart pending (RESTP) state.

With ACCESS(FORCE) you must use a single database name, the SPACENAM option, and an explicit list of table space and index names. You cannot use any range or combination of pattern-matching characters (*), including DATABASE (*) or SPACENAM (*).

A utility restrictive state is reset (the utility is terminated) only if all the target objects are reset with this command. To identify which objects are target objects of the utility, use the DISPLAY DATABASE command, or run the DIAGNOSE utility with the DISPLAY SYSUTIL option.

-START DATABASE (DB2)

A table space or index space started with ACCESS(FORCE) might be in an inconsistent state. See “Usage notes” for further instructions.

Usage notes

Data sets offline: It is not necessary for every disk pack containing partitions, table spaces, or indexes to be online when a database is started. Packs must, however, be online when partitions, table spaces, or indexes are first referred to. If they are not, an error in opening occurs.

Table spaces and indexes explicitly stopped: If table spaces and indexes are stopped explicitly (using the STOP DATABASE command with the SPACENAM option), they must be started explicitly. Starting the database does not start table spaces or indexes that have been explicitly stopped.

Effect on objects marked with GRECP or with LPL entries: If a table space, partition, or index is in the group buffer pool RECOVER pending (GRECP) status, or if it has pages in the logical page list (LPL), the START DATABASE command begins recovery of the object. You must specify the SPACENAM option and ACCESS (RW) or (RO).

This recovery operation is performed even if SPACENAM specifies an object that is already started.

If the object is stopped when the command is issued, then the START DATABASE command both starts the object and clears the GRECP or LPL status. If the GRECP or LPL recovery action cannot complete, the object is still started.

When recovering objects that are in GRECP or LPL status, avoid using pattern-matching characters (*) for both the database name and the space name. Multiple START DATABASE(*dbname*) SPACENAM(*) commands running in parallel should complete faster than one START DATABASE(*) SPACENAM(*) command.

If you use pattern-matching characters (*) for both the database name and space name, you must have DBMAINT authority and ensure that the catalog and directory databases have already been explicitly started in this order:

- START DATABASE(DSNDB01) SPACENAM(*)
- START DATABASE(DSNDB06) SPACENAM(*)

Although not recommended, you can start an object using START DATABASE ACCESS(FORCE). That deletes all LPL and write error page range entries without recovering the pages. It also clears the GRECP status.

When starting a LOB table space defined as LOG NO and either in GRECP or having pages in the LPL, the LOB table space will be placed in the AUXW state and the LOB will be invalidated if DB2 detects that log records required for LPL recovery are missing due to the LOG NO attribute.

Use of ACCESS(FORCE): The ACCESS(FORCE) option is intended to be used when data has been restored to a previous level after an error, by DSN1COPY, or by a program that is not DB2 for OS/390 and z/OS, and the exception states resulting from the error still exist and cannot be reset. When using ACCESS(FORCE), it is up to the user to ensure the consistency of data with respect to DB2. For information on DSN1COPY, see *DB2 Utility Guide and Reference*.

-START DATABASE (DB2)

#

If an application process requests a transaction lock on a table space that is in a restrictive status (RECP) or has a required index in a restrictive status, DB2 acquires the lock. DB2 does not detect the status until the application tries to access the table space or index, when the application receives an error message indicating that the resource is not available (SQLCODE -904). After receiving this message, the application should release the lock, either by committing or rolling back (if the value of the RELEASE option is COMMIT) or by ending (if the value of RELEASE is DEALLOCATE). If you issue the command START DATABASE ACCESS(FORCE) for either the table space or the index space while the lock is in effect, the command fails.

If an object has retained locks (that is, a member of a DB2 data sharing group has failed and the locks it held on the object are retained in the lock structure), then START DATABASE ACCESS (FORCE) is not allowed.

START DATABASE ACCESS(FORCE) does not execute if postponed abort or indoubt units of recovery exist. If you attempt to issue the START DATABASE ACCESS(FORCE) command in this situation, the command fails. FORCE cannot be used to reset the restart pending (RESTP) state. See Part 2 of *DB2 Utility Guide and Reference* for information about resetting the RESTP state.

Restricted mode (RO or UT): When a START DATABASE command for a restricted mode (RO and UT) takes effect depends upon whether applications are started after the START DATABASE command has completed, or whether applications are executing at the time the command is issued. For applications started after START DATABASE has completed, access restrictions are effective immediately. For applications executing at the time START DATABASE is issued, the access restrictions take effect when a subsequent claim is requested or the application is allowed to run to completion. Whether the application is interrupted by the START DATABASE command depends upon various factors. These factors include the ACCESS mode specified on the START DATABASE command, the type of drain activity, if any, on the table space or partition, and whether there are held cursors on the table space or partition.

Do not start table spaces or index spaces for defined temporary tables with RO or UT access. You can start a temp file database with UT access to accommodate the REPAIR DBD utility.

If the table space, index, or partition must be accessed in a mode that is incompatible with the ACCESS type currently in effect, DB2 issues a resource unavailable message.

For shared owner databases, a STOP DATABASE command must be issued to quiesce a database or table space prior to issuing the START DATABASE command.

Communications database or resource limit facility: If the communications database (CDB) or resource limit facility (RLF) is currently being used by any member of the data sharing group, any attempt to start either active database or table space with ACCESS(UT) fails.

Synchronous processing completion: Message DSN9022I indicates that synchronous processing has completed successfully.

Asynchronous processing completion: Recovery of objects in GRECP status or with pages on the LPL is performed asynchronously. Message DSN1022I is issued

-START DATABASE (DB2)

periodically to give you the progress of the recovery. The starting of databases, table spaces, or indexes (a synchronous task) often completes before the recovery operation starts. Therefore, when DB2 issues message DSN9022I, which indicates that synchronous processing has completed, the recovery of objects might not be complete. Message DSN1006I is issued in response to START DATABASE when the object (table space or index space) identified by TYPE and NAME had group buffer pool RECOVER pending (GRECP) or logical page list (LPL) status, and recovery was triggered. The START DATABASE command does not complete until the asynchronous task of recovery completes.

Message DSN1021I indicates that asynchronous processing for an object has completed. You can issue the command DISPLAY DATABASE to determine whether the recovery operation for all objects is complete. If it is complete, the output from the command shows either a RW or a RO status without LPL or GRECP.

Starting a LOB table space: The START DATABASE command can be used to start LOB table spaces and indexes on auxiliary tables. LOB table spaces are started independently of the base table space with which the LOB table space is associated.

Examples

Example 1: Start table space DSN8S71E in database DSN8D71A. Recover the table space if it is in GRECP status or recover the pages on the LPL if one exists.

```
-START DATABASE (DSN8D71A) SPACENAM (DSN8S71E)
```

Example 2: Start all databases (except DSNDB01, DSNDB06, and work file databases) for which you have authority. Recovery for any objects with GRECP or LPL status is not performed.

```
-START DATABASE (*)
```

Example 3: Start the third and fourth partitions of table space DSN8S71E in database DSN8D71A for read-only access. Recover the partitions if they are in GRECP status or recover the pages on the LPL if one exists.

```
-START DATABASE (DSN8D71A) SPACENAM (DSN8S71E) PART (3,4) ACCESS (RO)
```

Example 4: Start all table spaces that begin with "T" and end with the string "IQUA03" in database DBIQUA01 for read and write access.

```
-START DATABASE (DBIQUA01) SPACENAM (T*IQUA03) ACCESS (RW)
```

This command produces output similar to the following output:

```
DSN9022I - DSNTDDIS 'START DATABASE' NORMAL COMPLETION
```


-START DB2 (DB2)

Abbreviation: ACC

(*) Makes access general; all authorized users can connect to DB2.

The **default** is **ACCESS(*)**.

(MAINT)

Prohibits access to any authorization IDs other than install SYSADM and install SYSOPR.

For data sharing, ACCESS(MAINT) restricts access on only the DB2 member on which you execute this command. Other members of the data sharing group are unaffected.

LIGHT

Specifies whether a light restart is to be performed in a data sharing environment.

NO

Restart light is not performed.

YES

Specifies that a restart light is to be performed. DB2 starts with reduced storage and terminates normally after freeing retained locks.

MSTR(*jcl-substitution*)

Gives parameters and values to be substituted in the EXEC statement of the JCL that executes the startup procedure for the system services address space.

DBM1(*jcl-substitution*)

Gives parameters and values to be substituted in the EXEC statement of the JCL that executes the startup procedure for the database services address space.

DIST(*jcl-substitution*)

Gives parameters and values to be substituted in the EXEC statement of the JCL that executes the startup procedure for the distributed services address space.

(jcl-substitution)

One or more character strings of the form *keyword = value*, enclosed between apostrophes. If you use more than one character string, separate the strings by commas and enclose the entire list between a single pair of apostrophes.

Recommendation: Omit the keyword and use the parameters provided in the startup procedure.

Usage notes

Command prefix: If your installation has more than one DB2 subsystem, you must define more than one command prefix.

Conditional restart: A conditional restart control record can prevent a complete restart, and specify “current status rebuild” only. In that case, these actions occur during restart:

- Log records are processed to the extent determined by the conditional restart control record.
- These values are displayed:
 - The relative byte address (RBA) of the start of the active log
 - The RBA of the checkpoint record
 - The status counts for units of recovery

-START DB2 (DB2)

- The display table for restart unit of work elements
- The restart operation terminates with an abend.

Light restart with ARM: To enable a light restart in an ARM environment, you must code an ARM policy for DB2 and IRLM.

The following example shows an ARM policy for DB2, where the element name is the DB2 data sharing group name and member name concatenated. For example, DSNDB0GDB1G.

```
ELEMENT(elementname)
```

```
RESTART_METHOD(SYSTEM,STC,'cmdprfx STA DB2,LIGHT(YES)')
```

The following example shows an ARM policy for IRLM, where the element name is the IRLM group name and the ID concatenated. For example, DXRDB0GDJ1G001.

```
ELEMENT(elementname)
```

```
RESTART_METHOD(SYSTEM,STC,'cmdprfx S irlmproc,PC=YES')
```

The element name that DB2 uses is the DB2 data sharing group name and member name concatenated. For example, DSNDB0GDB1G. F

Endless wait during start: It is possible for the start operation to begin and fail to complete, if the system services address space starts and the database services address space cannot start. If a seemingly endless wait occurs, cancel the system services address space from the console, and check both startup procedures for JCL errors.

Starting members of a data sharing group: To start members of a data sharing group, you must enter a START DB2 command for each subsystem in the group. If it is the first startup of the group, you must start the originating member (the first DB2 installed) first.

Examples

Example 1: Start the DB2 subsystem.

```
-START DB2
```

Example 2: Start the DB2 subsystem and provide a new value for the REGION parameter in the startup procedure for the system services address space.

```
-START DB2 MSTR('REGION=6000K')
```

Example 3: Start the DB2 subsystem. Assuming that the EXEC statement of the JCL that executes the startup procedure for the system services address space uses the symbol RGN, provide a value for that symbol.

```
-START DB2 MSTR('RGN=6000K')
```

Example 4: DB2 subsystems DB1G and DB2G are members of a data sharing group. Both were installed with a command prefix scope of STARTED. Start DB1G and DB2G by routing the appropriate commands to the MVS system on which they are to be started, MVS1 and MVS2.

```
ROUTE MVS1,-DB1G START DB2  
ROUTE MVS2,-DB2G START DB2
```


-START DDF (DB2)

-START DDF (DB2)

The DB2 command START DDF starts the distributed data facility (DDF) if it has not already been started.

Abbreviation: -STA DDF

Environment

This command can be issued from an MVS console, a DSN session under TSO, a DB2I panel (DB2 COMMANDS), an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

Data sharing scope: Member

Authorization

To execute this command, the privilege set of the process must include one of the following:

- SYSOPR authority
- SYSCTRL authority
- SYSADM authority

DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.

Syntax

▶▶—START DDF—▶▶

Usage note

The START DDF command activates the DDF interface to VTAM and TCP/IP. When issued after STOP DDF MODE(SUSPEND), suspended threads are resumed and DDF activity continues.

Example

Start the distributed data facility.

-START DDF

-START FUNCTION SPECIFIC (DB2)

The DB2 command START FUNCTION SPECIFIC activates an external function that is stopped. Built-in functions or user-defined functions that are sourced on another function cannot be started with this command.

On successful completion of the command, queued requests for the specified functions begin executing. The abend counts for those functions are set to zero.

You do not need to issue the START FUNCTION SPECIFIC command when defining a new function to DB2. DB2 automatically activates the new function on the first SQL statement that invokes the new function.

Historical statistics in the DISPLAY FUNCTION SPECIFIC report (MAXQUE, TIMEOUT) are reset each time a START FUNCTION SPECIFIC command is issued for a given function.

Abbreviation: -STA FUNC SPEC

Environment

This command can be issued from an MVS console, a DSN session under TSO, a DB2I panel, an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

#

Data sharing scope: Group or local, depending on the value of the SCOPE option.

Authorization

To execute this command, the privilege set of the process must include one of the following authorities for each function:

- Ownership of the function
- SYSOPR authority
- SYSCTRL authority
- SYSADM authority


If -START FUNCTION SPECIFIC *.* or schema.partial-name* is specified, the privilege set of the process must include one of the following authorities:

- SYSOPR authority
- SYSCTRL authority
- SYSADM authority

DB2 commands that are issued from an MVS console are not associated with any secondary authorization IDs.

Syntax

-START FUNCTION SPECIFIC



Option descriptions

* (asterisk)(*)

Starts all functions in all schemas. This is the default.

schema.specific-function-name

Starts the specific function name in the schema. You cannot specify a function name as you can in SQL; you must use the specific name. If a specific name was not specified on the CREATE FUNCTION statement, query SYSIBM.SYSROUTINES for the correct specific name:

```

SELECT SPECIFICNAME, PARM_COUNT
FROM SYSIBM.SYSROUTINES
WHERE NAME='function_name'
AND SCHEMA='schema_name';
  
```

For overloaded functions, this query can return multiple rows.

*schema.partial-name**

Starts all functions or a set of functions in the specified schema. The specific names of all functions in the set begin with *partial-name* and can end with any string, including the empty string. For example, schema1.ABC* starts all functions with specific names that begin with ABC in schema1.

SCOPE

Specifies the scope of the command.

(LOCAL)

Specifies that the command applies only to the current member.

(GROUP)

Specifies that the command applies to all members of the data sharing group.

Usage notes

Language Environment® in the WLM-established stored procedure address space:

The -START FUNCTION SPECIFIC command does not refresh the Language Environment in the WLM-established stored procedure address space. You must issue the WLM command. For example, if you need to refresh the Language Environment to get new copies of UDF load modules, issue the following WLM command.

```
VARY WLM, APPLENV=applenv,REFRESH
```

Examples

Example 1: Start all functions.

```
-START FUNCTION SPECIFIC
```

Output similar to the following output is generated:

```
DSN9022I - DSNX9COM '-START FUNC' NORMAL COMPLETION
```

Example 2: Start functions USERFN1 and USERFN2. If any requests are queued for these functions, the functions are executed.

```
-START FUNCTION SPECIFIC(PAYROLL.USERFN1,PAYROLL.USERFN2)
```

Output similar to the following output is generated:

```
DSN9022I - DSNX9COM '-START FUNC' NORMAL COMPLETION
```

START....(MVS IRLM)

START irlmproc (MVS IRLM)

The START *irlmproc* command starts an IRLM component with a procedure put in place by the installation. Symbolic parameters in the procedure can be overridden on the START *irlmproc* command.

Environment


This command can be issued only from an MVS console.

Data sharing scope: Member

Authorization

The command requires an appropriate level of MVS authority, as described in *OS/390 MVS System Commands*.

Syntax



Options must be separated by commas with no spaces.

Option descriptions

irlmproc

Is the procedure name of the IRLM to be started.

None of the following options is required:

DEADLOK='iiii,kkkk'

Specifies the local deadlock-detection interval in seconds (*iiii*), and the number of local cycles (*kkkk*) that are to occur before a global detection is initiated.

iiii Is a one- to four-digit number from 1 to 9999 that specifies the length in seconds of the IRLM local deadlock-detection interval. Any value from 1 to 9999 may be specified but if the value is greater than 5, IRLM uses 5.

kkkk

Is a one- to four-digit number from 1 to 9999 that specifies the number of local deadlock cycles that must expire before global deadlock detection is performed. Any value from 1 to 9999 may be specified but IRLM uses 1. The recommended value to specify is 1.

In a data sharing environment, IRLM synchronizes all of the DEADLOCK values in the group to the values specified on the most recent IRLM to join the group. The DEADLOCK values may be changed by starting a member with the values desired. To reduce confusion, it is recommended that the installation specify the same value for DEADLOCK on all of its IRLM start-up procedures and use the *START irlmproc* command to override this value only when the interval must be increased from its original value.

IRLMGRP=*'irlm-group-name'*

Specifies the name of the cross system coupling facility (XCF) group, in a data sharing environment, to which the IRLM belongs as the lock manager for DBMSs sharing the same data. All IRLMs in the same group must specify the same value for LOCKTABL and unique values for IRLMID.

The group name is used as the XCF group name. The name must not start with 'SYS' and must not be the same name specified for LOCKTABL.

In a non-data-sharing environment (SCOPE=LOCAL), IRLMGRP is ignored.

IRLMID=*n*

Specifies a decimal number that is used to distinguish between IRLMs in a data sharing group. The IRLM with the lowest ID in the group becomes the global deadlock manager for the group when in you are in a data sharing mode.

n can be either a 1- to 3-digit number from 1 to 255, or a printable character in quotation marks. Note that this IRLM ID does not relate directly to the limit of IRLM members that can be in the group. That limit is determined by the current hardware limits (currently 32).

When *n* is specified as a printable character, IRLM uses the EBCDIC value of the printable character as the IRLMID (such as X'C4'). The printable character must be surrounded by enough single quotes to permit IRLM to see it as a printable character. Because of the way MVS interprets quotes, there must be single quotes on either side of the characters. For example, if you want to specify the printable character 'D', you must specify it here as IRLMID='D'.

A unique IRLMID must be specified for each IRLM in a group (IRLMs with the same value specified for the IRLMGRP option).

IRLMNM=*irlmname*

Specifies a 4-byte MVS subsystem name assigned to this IRLM. (Although MVS can accept names that are less than 4 bytes, IRLM requires a 4-byte name.)

LOCKTABL=*irlmltnm*

Specifies the lock table to be used by this group. This option is overridden by DB2; it is needed in an IMS environment.

In a non-data-sharing environment (SCOPE=LOCAL), LOCKTABL is ignored.

MAXCSA=*nnn*

Specifies the maximum amount of CSA (including ECSA) the IRLM can use

START....,(MVS IRLM)

for its lock structures. *nnn* must be a one- to three-digit number from 1 to 999. The number indicates what multiple of 1 MB of storage the IRLM will use. For example, MAXCSA=5 allows the IRLM to use 5 MB of CSA and ECSA. In displays, this storage is called *accountable* storage because it is accountable to the value you set for MAXCSA. This parameter is ignored when PC=YES.

The **default** value for MAXCSA is **6 MB**.

Use the accountable storage high water mark (AHWM) data from messages DXR100I and DXR121I to monitor IRLM's usage of common storage, and as a basis for adjustments to the MAXCSA value.

MAXUSRS=*nnn*

Specifies the initial maximum number of members in the data sharing group. The specified value determines the size of each lock entry in the lock table portion of the lock structure, as shown in Table 26.

Table 26. Effect of MAXUSRS on initial lock table entry size

MAXUSRS	Initial size of lock entry
7 or less	2 bytes
≥ 8 and < 24	4 bytes
≥ 24 and < 33	8 bytes

nnn must be a one- to two-digit number from 1 to 32. The default is 7. The recommended value is 7 or less.

In a non-data-sharing environment (SCOPE=LOCAL), MAXUSRS is ignored.

PC=

Specifies whether the IRLM is to use the MVS cross-memory services. The specification of this value indicates where the lock control block resides.

YES Uses the cross-memory services. The lock control block resides in IRLM private storage. The MAXCSA parameter is ignored.

NO Does not use the cross-memory services. The lock control block resides in ECSA. The MAXCSA parameter is used.

PGPROT=

Specifies whether the IRLM load modules that are resident in common storage are placed in MVS page protected storage.

YES The IRLM load modules that are resident in common storage are placed in MVS page-protected storage.

NO The IRLM load modules that are resident in common storage are not placed in MVS page-protected storage.

SCOPE=

Specifies whether the IRLM is to be used in a data sharing environment.

LOCAL

Specifies the IRLM is in a non-data-sharing environment and there is no intersystem sharing.

GLOBAL

Specifies the IRLM is in a data sharing environment and that intersystem sharing is to be performed.

NODISCON

Specifies that IRLM is in a data sharing environment and that intersystem sharing is to be performed. IRLM remains connected to the data sharing group even when no DBMSs are identified to it. You must explicitly stop IRLM to bring it down.

If you specify the NODISCON option, there is less impact on other systems when a DB2 subsystem fails because MVS is not required to perform certain recovery actions that it normally performs when IRLM comes down. Using the NODISCON option might allow DB2 to restart more quickly after a DB2 subsystem normally or abnormally terminates because it does not have to wait for IRLM to rejoin the IRLM data sharing group.

TRACE=

Specifies whether the IRLM is to capture traces in wrap-around IRLM buffers. Each buffer is reused when the previous buffer is filled. Traces are captured at IRLM startup.

NO

Does not capture traces unless the TRACE CT command is issued. See "TRACE CT (MVS IRLM)" on page 340 for details.

YES

Captures traces in wrap-around buffers.

Example

Enter the following command on the MVS system console:

```
S ir1mproc,MAXCSA=8
```

This command starts the IRLM with 8 MB for MAXCSA which controls the CSA (including ECSA) usage for locks when PC=NO.

-START PROCEDURE (DB2)

-START PROCEDURE (DB2)

For both DB2-established and WLM-established stored procedure address spaces, the DB2 command START PROCEDURE activates the definition of a stored procedure that is stopped or refreshes one that is cached. You can qualify stored procedure names with a schema name.

One of the following can also occur:

- If the DB2-established stored procedures address space is not connected to DB2, MVS starts it.
- If the stored procedures address space is already connected, and some procedure listed in the command is stopped, DB2 stops and restarts the Language Environment environment. At restart, DB2 deletes the existing stored procedure load modules from memory. A deleted load module is reloaded when a CALL statement for that procedure is executed. For WLM-established stored procedures address spaces, a WLM command is needed to do the reload. For example:

```
MVS VARY WLM,APPLENV=applenv,REFRESH
```

On successful completion of the command, queued requests for the specified stored procedures begin executing. The abend counts for those procedures are set to zero. DB2 resets the MAXQUE and TIMEOUT statistics to 0 each time you execute the START PROCEDURE command.

You do not have to issue START PROCEDURE when defining a new stored procedure to DB2. DB2 automatically activates the new definition when it first receives an SQL CALL statement for the new procedure.

Abbreviation: -STA PROC

Environment

This command can be issued from an MVS console, a DSN session under TSO, a DB2I panel (DB2 COMMANDS), an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

Data sharing scope: Group or local, depending on the value of the SCOPE option.


Authorization

To execute this command, the privilege set of the process must include one of the following:

- SYSOPR authority
- SYSCTRL authority
- SYSADM authority
- Ownership of the stored procedure.

DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.

Syntax



Option descriptions

(*,*)

Marks all stored procedures in all schemas as available to be called.

(schema.procedure-name)

Starts the specified stored procedure in the specified schema.

(schema.partial-name*)

Starts a set of stored procedures in the specified schema. The names of all procedures in the set begin with *partial-name* and can end with any string, including the empty string. For example, PAYROLL.ABC* starts all stored procedures with names beginning with ABC in the PAYROLL schema.

procedure-name

Marks the one or more specific stored procedures as available to be called.

partial-name*

Marks a set of stored procedures in the SYSPROC schema as available to be called. The names of all procedures in the set begin with *partial-name* and can end with any string, including the empty string. For example, ABC* starts all stored procedure names that begin with ABC in the SYSPROC schema.

SCOPE

Specifies the scope of the command.

(LOCAL)

Starts the specified stored procedures in the local member only.

(GROUP)

Starts the specified stored procedures in all members of the data sharing group.

#

Usage notes

Errors in a definition of a stored procedure: Errors are detected at create time for a stored procedure. See CREATE PROCEDURE in Chapter 5 of *DB2 SQL Reference* for more information.

Management of stored procedures address space: The START PROCEDURE command works differently depending upon how the DB2 stored procedures address spaces are managed. WLM-established stored procedure address spaces are controlled by MVS WLM, rather than the START PROCEDURE command. For more information, see Part 5 (Volume 2) of *DB2 Administration Guide*.

-START PROCEDURE (DB2)

Examples

Example 1: Start all stored procedures.

```
-START PROCEDURE
```

This command produces output similar to the following output:

```
DSNX946I - DSNX9ST2 START PROCEDURE SUCCESSFUL FOR *.*
DSN9022I - DSNX9COM '-START PROC' NORMAL COMPLETION
```

Example 2: Make specific stored procedures available to be called, and start any requests waiting for those procedures.

```
-START PROCEDURE(USERPRC1,USERPRC2)
```

This command produces output similar to the following output:

```
DSNX946I - DSNX9ST2 START PROCEDURE SUCCESSFUL FOR USERPRC1
DSNX946I - DSNX9ST2 START PROCEDURE SUCCESSFUL FOR USERPRC2
DSN9022I - DSNX9COM '-START PROC' NORMAL COMPLETION
```

-START RLIMIT (DB2)

The DB2 command START RLIMIT starts the resource limit facility (governor) and specifies a resource limit specification table for the facility to use.

You can issue START RLIMIT even if the resource limit facility is active. The resource limit specification table you identify is used for new threads, and existing threads continue to be subject to the limits in the table that was active at the time they were created.

Abbreviation: -STA RLIM

Environment

This command can be issued from an MVS console, a DSN session under TSO, a DB2I panel (DB2 COMMANDS), an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

Data sharing scope: Member

Authorization

To execute this command, the privilege set of the process must include one of the following:

- SYSOPR authority
- SYSCTRL authority
- SYSADM authority

DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.

Syntax

```
▶▶—START RLIMIT—┐ID=id┘▶▶
```

Option description

The following keyword is optional.

ID=id

Identifies the resource limit specification table for the governor to use.

id is the one or two identification characters specified when the table was created. See Part 5 (Volume 2) of *DB2 Administration Guide* for more information about resource limit specification tables.

The full name of the table is *authid.DSNRLSTid*, where *authid* is the value that was specified in field RESOURCE AUTHID on installation panel DSNTIPP.

The **default** ID is the value that was specified in field RLST NAME SUFFIX on installation panel DSNTIPO.

-START RLIMIT (DB2)

Example

Start the resource limit facility.

```
-START RLIMIT ID=01
```

-START TRACE (DB2)

The DB2 command START TRACE starts DB2 traces. For more information about the trace facility, see Part 5 (Volume 2) of *DB2 Administration Guide*.

There is an additional option to this command and values for a few options that are not described here. They are intended for service and use under the direction of IBM support personnel. For details, see *DB2 Diagnosis Guide and Reference*.

Abbreviation: -STA TRA

Environment

This command can be issued from an MVS console, a DSN session, a DB2I panel (DB2 COMMANDS), an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

#

Data sharing scope: Group or local, depending on the value of the SCOPE option.

Authorization


To execute this command, the privilege set of the process must include one of the following:

- TRACE privilege
- SYSOPR, SYSCTRL, or SYSADM authority

DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.

-START TRACE (DB2)

Syntax



Option descriptions

You must specify a trace type.

The options PERFM, ACCTG, STAT, AUDIT, and MONITOR identify the type of trace started.

(PERFM)

Is intended for performance analysis and tuning, and includes records of specific events in the system.

Abbreviation: P

(ACCTG)

Is intended to be used in accounting for a particular program or authorization ID, and includes records written for each thread.

Abbreviation: A

(STAT)

Collects statistical data broadcast by various components of DB2, at time intervals that can be chosen during installation.

Abbreviation: S

LOCATION cannot be specified when you choose a statistics trace.

(AUDIT)

Collects audit data from various components of DB2.

Abbreviation: AU

(MONITOR)

Collects monitor data. Makes trace data available to DB2 monitor application programs.

Abbreviation: MON

COMMENT(*string*)

Gives a comment that is reproduced in the trace output (except in the resident trace tables), and can be used to record why the command was issued.

string is any character string; it must be enclosed between apostrophes if it includes a blank, comma, or special character.

SCOPE

Specifies the scope of the command.

(LOCAL)

Starts the trace only on the local DB2 subsystem.

(GROUP)

Starts the trace on all members of a data sharing group.

#

The destination block

DEST

Specifies where the trace output is to be recorded. You can use more than one value, but do not use the same value twice. If you do not specify a value, the trace output is sent to the default destination shown in Table 27 on page 302.

If the specified destination is not active or becomes inactive after you issue the START TRACE command, you receive message DSNW133I, which indicates that the trace data is lost. This applies for destinations GTF, SRV, and SMF. You also receive this message for destinations OP*n* and OPX if START TRACE is not issued by an application program.

Abbreviation: D

The allowable values and the default value depend on the type of trace started, as shown in the following table:

-START TRACE (DB2)

Table 27. Allowable destinations for each trace type

Type	GTF	SMF	SRV	OP n	OPX
PERFM	Default	Allowed	Allowed	Allowed	Allowed
ACCTG	Allowed	Default	Allowed	Allowed	Allowed
STAT	Allowed	Default	Allowed	Allowed	Allowed
AUDIT	Allowed	Default	Allowed	Allowed	Allowed
MONITOR	Allowed	Allowed	Allowed	Allowed	Default

The meaning of each value is as follows:

Value Trace output is recorded by

GTF The MVS generalized trace facility (GTF). The record identifier for records from DB2 is X'0FB9'.

SMF The system management facility. The SMF record type of DB2 trace records depends on the IFCID record, as shown in the following list:

IFCID record

SMF record type

1 (System Services Statistics)

100

2 (Database Services Statistics)

100

3 (Agent Accounting)

101

202 (Dynamic System Parameters)

100

230 (Data Sharing Global Statistics)

100

239 (AGENT ACCOUNTING OVERFLOW)

101

All Others

102

SRV An exit to a user-written routine. For instructions and an example of how to write such a routine, see the macro DSNWVSER in library *prefix.SDSNMACS*.

OP n A specific destination.
 n can be an integer from 1 to 8.

OPX A generic destination which uses the first free OP n slot.

Only applications that start a trace to an OP n buffer can read that buffer. For further information on starting a trace via an application program, see Appendix E (Volume 2) of *DB2 Administration Guide*.

All traces to an OPX destination must be stopped before the buffer is marked as not in use. Traces that are started to an OPX buffer that was formerly in use write over the storage any previous traces had set.

The constraint block

The constraint block places optional constraints on the kinds of data collected by the trace. The allowable constraints depend on the type of trace started, as shown in the following table:

Table 28. Allowable constraints for each trace type

Type	PLAN	AUTHID	CLASS	LOCATION
PERFM	Allowed	Allowed	Allowed	Allowed
ACCTG	Allowed	Allowed	Allowed	Allowed
STAT	NO	NO	Allowed	NO
AUDIT	Allowed	Allowed	Allowed	Allowed
MONITOR	Allowed	Allowed	Allowed	Allowed

The meaning of each option is as follows:

PLAN(*plan-name*, ...)

Introduces a list of specific plans for which trace information is gathered. You cannot use this option for a STAT trace.

The **default** is **PLAN(*)**.

(*) Starts a trace for all plans.

plan-name

Is the name of an application plan. You can use up to eight names; a separate trace is started for each name. If you use more than one name, you can use only one value for AUTHID and LOCATION.

AUTHID(*authorization-id*, ...)

Introduces a list of specific authorization IDs for which trace information is gathered. The authorization IDs specified must be the primary authorization IDs. You cannot use this option for a STAT trace.

The **default** is **AUTHID(*)**.

(*) Starts a trace for all authorization IDs.

authorization-id

Specifies an authorization ID. You can use up to eight identifiers; a separate trace is started for each identifier. If you use more than one identifier, you can use only one value for PLAN and LOCATION.

CLASS(*integer*, ...)

Introduces a list of classes of data gathered. What classes are allowable, and their meaning, depends on the type of trace started.

Abbreviation: C

When this option is omitted, all the default classes within the trace type are activated. The **default** classes for each trace type are marked by asterisks (*) in Table 29.

(*) Starts a trace for all classes of the trace type.

integer

Is any number in the list that follows. You can use any number of classes that are allowed for the type of trace started.

Table 29. Classes for DB2 trace types

Trace type	Class	Description of class	Activated IFCIDs
Accounting	1*	Standard accounting data	3,106,239
	2	Entry or exit from DB2 event signalling	232
	3	Elapsed wait time in DB2	6-9,32,33,44,45,117,118,127,128,170,171,174,175,213-216,226,227,242,243,321,322,329

-START TRACE (DB2)

Table 29. Classes for DB2 trace types (continued)

Trace type	Class	Description of class	Activated IFCIDs
	4	Installation-defined accounting record ¹	151
	5	Time spent processing IFI requests	187
	6	Reserved	
	7	Entry or exit from DB2 event signalling for package and DBRM accounting	232,240
	8	Wait time for a package	6-9,32,33,44,45,117,118,127,128,170,171,174,175,213-216,226,227,241-243,321,322
	10 - 29	Reserved	
	30 - 32	Available for local use	
Audit	1*	Access attempts denied due to inadequate authorization	140
	2	Explicit GRANT and REVOKE	141
	3	CREATE, ALTER, and DROP operations against audited tables	142
	4	First change of audited object	143
	5	First read of audited object	144
	6	Bind time information about SQL statements that involve audited objects	145
	7	Assignment or change of authorization ID	55,83,87,169,312
	8	Utilities	23,24,25
	9	Installation-defined audit record ¹	146
	10 - 29	Reserved	
	30 - 32	Available for local use	
Statistics	1*	Statistics data	1,2,105,106,202
	2	Installation-defined statistics record ¹	152
	3	Deadlock, group buffer pool, data set extension information, and indications of long-running URs and active log space shortages	172,196,250, 258,261,262,313,330
	4	DB2 exceptional conditions	191-195,203-210,235,236,238,267,268
	5	DB2 data sharing statistics record	230
	6	Storage usage details	217
	7	Reserved	
	8	Data set I/O statistics	199
	9 - 29	Reserved	
	30 - 32	Available for local use	
Performance	1*	Background events	1,2,31,42,43,76-79,102,103,105-107,153
	2*	Subsystem events	3,68-75,80-89,106,174,175,
	3*	SQL events	22,53,55,58-66,92,95-97,106,112,177,233,237,250,272,273,325
	4	Reads to and writes from the buffer and EDM pools	6-10,29-30,105-107,127,128,226,227,321,322
	5	Write to log; archive log	32-41,104,106,114-120,228,229
	6	Summary lock information	20,44,45,105-107,172,196,213,214,218
	7	Detailed lock information	21,105-107,223
	8	Data scanning detail	13-18,105-107,125,221,222,231,305, 311
	9	Sort detail	26-28,95-96,106
	10	BIND, commands, and utilities detail	23-25,90,91,105-107,108-111,201,256

Table 29. Classes for DB2 trace types (continued)

Trace type	Class	Description of class	Activated IFCIDs
#	11	Execution unit switch and latch contentions	46-52,56,57,93,94,106,113
	12	Storage manager	98-101,106
	13	Edit and validation exits	11,12,19,105-107
	14	Entry from and exit to an application	67,106,121,122
	15	Installation-defined performance record ¹	154
	16	Distributed processing	157-163,167,183
	17	Claim and drain information	211-216
	18 - 19	Reserved	
	20	Data sharing coherency summary	249-251,256-257,261,262,267,268
	21	Data sharing coherency detail	255,259,263
	22	Authorization exit parameters	314
	23 - 29	Reserved	
	30 - 32	Available for local use	
Monitor	1*	Activate the READS IFCIDs	1,2,106,124,129,147,148-150, 199,202, 230,254,306,316 ⁽²⁾ ,317
	2	Entry or exit from DB2 event signalling	232
	3	DB2 wait time for I/O, locks; resource usage information	6-9,32,33,44,45,117,118,127, 128,170,171,174,175,213,214, 215,216,226,227,242,243,321,322
	4	Installation-defined monitor record ¹	155
	5	Time spent processing IFI requests	187
	6	Changes to tables created with DATA CAPTURE CHANGES	185
	7	Entry or exit from DB2 event signalling for package and DBRM accounting	232,240
	8	Wait time for a package	6-9,32,33,44,45,51,52,56,57, 117,118,127,128,170,171,174, 175,213-216,226,227,241-243,321,322
	9 - 29	Reserved	
	30 - 32	Available for local use	

Notes to Table 29:

- An asterisk (*) indicates a default class for a trace type.
- 1. For instructions on using the IFCIDs, see Appendix D (Volume 2) of *DB2 Administration Guide*.
- 2. DB2 does not collect statistical data for this record unless IFCID 318 is activated. IFCID 318 is not associated with any trace class; you must start it on its own.

IFCID(ifcid, ...)

Specifies which other IFCIDs (trace events), in addition to those IFCIDs contained in the classes specified in the CLASS option, are to be started. To start only those IFCIDs specified in the IFCID option, use trace classes 30-32. These classes have no predefined IFCIDs and are available for a location to use. (See "Example 1" on page 308 for an example of activating only those trace events specified in the IFCID option.)

If you do not specify the IFCID option, only those IFCIDs contained in the activated trace classes are started.

-START TRACE (DB2)

The maximum number of IFCIDs is 156. The range of values that are valid for the IFCID option is 1 through 350, with the exception of: 4, 5, 185, 187, 217, 232, 234, 240, and 241. These exceptions are invalid values for the IFCID option. IFCIDs 4 and 5 are always automatically active. Some of the other invalid IFCIDs can be activated only by certain trace classes. The invalid values for the IFCID option that can be started only by trace classes are:

To start...	Start...
IFCID 185	monitor trace class 6
IFCID 232	monitor trace class 2 or 7, or accounting trace class 2 or 7
IFCID 240	monitor trace class 7 or accounting trace 7
IFCID 241	monitor trace class 8 or accounting trace 8

The **default** is **IFCID(*)**.

BUFSIZE(*k_bytes*, ...)

Specifies the size of an IFC managed buffer that receives the trace data. You can specify this option only if you specified an *OPn* destination.

k_bytes can range from 8 KB to 1024 KB in 4 KB increments. If you specify a value outside of this range, then the range limit closest to the specified value is used. To allocate a buffer size of 8 KB, you would specify **BUFSIZE(8)**.

The **default** is **BUFSIZE(*)**, which is the size set when DB2 was installed.

TDATA

Specifies the product section headers to be placed into the product section of each trace record. If you do not specify **TDATA**, then the type of trace determines the type of product section header. The product section of a trace record can contain multiple headers.

All IFC records have a standard IFC header. The correlation header is added for accounting, performance, audit, and monitor records. The trace header is added for serviceability records.

CORRELATION

Places a correlation header on the record.

Abbreviation: COR

TRACE

Places a trace header on the record.

Abbreviation: TRA

CPU

Places a CPU header on the record. The CPU header contains the current processor time for the MVS TCB or SRB executing.

DISTRIBUTED

Places a distributed header on the record.

Abbreviation: DIST

LOCATION(*location-name*, ...)

Introduces a list of specific location names for which trace information is gathered. The use of the **LOCATION** option precludes tracing threads that have no distributed data relationship. **LOCATION** cannot be specified when you want to start a statistics trace.

-START TRACE (DB2)

location-name

Identifies the DB2 subsystems whose distributed threads you want to trace. Activates the DB2 trace for the remote TCP/IP or SNA location that you specify by *location-name*.

You can specify up to 8 locations; a separate trace is started for each one. You can specify only one location if you use more than one plan name or authorization ID.

<luname>

Activates the DB2 trace for the remote clients that are connected to DDF through the remote SNA LU name that you specified in *luname*.

ipaddr

Activates the DB2 trace for the remote clients that are connected to DDF through the remote TCP/IP host. *nnn.nnn.nnn* is the dotted decimal IP address.

- (*) Indicates that you want to start trace events that occur under distributed threads regardless of which location they are connected to. Specifying the local location name is equivalent to specifying LOCATION(*).

Clients other than DB2 for OS/390 and z/OS: DB2 does not receive a location name from clients that are not DB2 for OS/390 and z/OS subsystems. To start a trace for a client that is not a DB2 for OS/390 and z/OS subsystem, enter its LUNAME or IP address. Enclose the LUNAME by the less-than (<) and greater-than (>) symbols. Enter the IP address in the form *nnn.nnn.nnn.nnn*. For example, to start a trace for a client with the LUNAME of LULA, enter the following command:

```
-START TRACE (PERFM) CLASS (*) LOCATION (<LULA>)
```

To start a trace for a client with the IP address of 123.34.101.98, enter the following command:

```
-START TRACE (PERFM) CLASS (*) LOCATION (123.34.101.98)
```

Usage notes

Number of traces: If you use one or no values for PLAN, AUTHID, or LOCATION, the START TRACE command starts a single trace. If you use multiple values for PLAN, AUTHID, or LOCATION, the command starts a trace for each plan, authorization ID, or location. There can be up to 32 traces going at one time. If a START TRACE command is entered from the console or from the DB2I panels to an OPn or an OPX destination, message DSNW133I is issued to indicate trace data lost.

Using the options PLAN, AUTHID, or LOCATION when starting monitor trace class 1 has no effect on the amount of data returned on IFI READS requests. See Appendix E (Volume 2) of *DB2 Administration Guide* for more information on qualifying monitor trace class 1 IFCIDs.

Using the options PLAN, AUTHID, or LOCATION has no effect when starting either accounting or monitor trace classes 2, 5, or 7.

Stopping and starting DB2: If DB2 is stopped and started after you have started a trace, the trace is not restarted automatically.

Specifying SCOPE GROUP: When you issue START TRACE with SCOPE(GROUP), DB2 issues a START TRACE command on each member of the data sharing group. The data goes to the destination as it is defined for each

#

-START TRACE (DB2)

```
# member of the data sharing group. If you want to gather trace data for all members
# of the data sharing group in one place, use a monitor program with IFI READA or
# READS calls to collect the data. See Appendix E (Volume 2) of the DB2
# Administration Guide for more information.

# If a trace is started with SCOPE(GROUP), and a new member joins the data
# sharing group after the trace is started, the new member also writes the trace data
# that is specified by the START TRACE command.

# Starting a trace with SCOPE(GROUP) can generate large amounts of trace data, so
# you may need to increase the size of the return area in your monitor program to
# hold the extra data.
```

Examples

Example 1: Start a performance trace for threads with remote activity to location USIBMSTODB21. Only activate IFCIDs 44 (lock suspends) and 54 (lock contention). Trace class 30 is available for installation use.

```
-START TRACE (PERFM)
  DEST(GTF)
  LOCATION(USIBMSTODB21)
  CLASS(30)
  IFCID(44)
```

Example 2: Start an accounting trace for plan DSN8BC71. Write records to SMF (that will happen by default). Include a comment to identify the trace.

```
-START TRACE (ACCTG)
  PLAN (DSN8BC71)
  COMMENT ('ACCTG TRACE FOR DSN8BC71')
```

Example 3: Start the statistics trace. Write records to SMF (by default).

```
-START TRACE=S
```

Example 4: Start monitor tracing (usually done by an application program). Write records to OPX (by default).

```
-START TRACE(MON)
```

```
# Example 5: Start monitor tracing (usually done by an application program) on the
# data sharing group. Write records to OPX (by default).
```

```
# -START TRACE(MON) SCOPE(GROUP)
```

```
#
```

/STOP (IMS)

The IMS /STOP command (with the SUBSYS parameter) prevents application programs from accessing external subsystem resources.

The following is only a partial description of the /STOP command. For a complete description, see *IMS Command Reference*.

Environment


This command can be issued only from an IMS terminal.

Data sharing scope: Member

Authorization

This command requires an appropriate level of IMS authority, as described in the *IMS Administration Guide: System*.

Syntax



Option descriptions

SUBSYS

Specifies whether connection is to be stopped for one or more names of external subsystems presently connected to IMS, or for all of them.

subsystem-name, ...

Specifies one or more names of external subsystems whose connection to IMS is to be stopped.

ALL

Indicates that connection is to be stopped for all external subsystems presently connected to IMS.

Usage note

When to use /STOP: The /STOP command allows application programs currently accessing external resources to complete normally. When all applications have terminated, the connection to the external subsystem is also terminated. A /START command must be issued to reestablish the connection.

The /STOP command can also be used to stop the subsystem connection in order to change the specifications in the external subsystem's PROCLIB member entry. The /START command then refreshes the copy in main storage of the PROCLIB entry with the modified entry.

-STOP DATABASE (DB2)

-STOP DATABASE (DB2)

The DB2 command STOP DATABASE makes the specified databases unavailable for applications and closes their data sets.

In a data sharing environment, the command applies to every member of the data sharing group. If a GBP-dependent object is stopped with the command STOP DATABASE, DB2 performs the necessary processing to make the object no longer GBP-dependent.

Abbreviation: -STO DB

Environment

This command can be issued from an MVS console, a DSN session under TSO, a DB2I panel (DB2 COMMANDS), an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

Data sharing scope: Group

Authorization

All databases specified for which the set of privileges held by the privilege set of the process has the STOPDB privilege are stopped. Error messages are produced for those databases specified for which this set does not have the STOPDB privilege.

The privilege set of the process must include one of the following:


- STOPDB privilege
- DBMAINT, DBCTRL, or DBADM authority
- SYSCTRL or SYSADM authority

DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.

When data definition control is active, installation SYSOPR or installation SYSADM authority is required to stop the database, a table space, or an index space containing a registration table or index.

Database DSNDB06 contains the table spaces and index spaces required to check authorization. If you stop any table space or index space required for the START DATABASE authorization check, then installation SYSADM authority is required to restart it.

Syntax



Option descriptions

One of the following two options is required.

(*database-name*, ...)

Specifies the names of the database, or database for the table spaces or index spaces to stop. If you use more than one name, separate names in the list by commas.

(*) Stops all databases for which the privilege set of the process has at least DBMAINT authority.

However, DSNDB01, DSNDB06, and work file databases, such as DSNDB07, can be stopped only by specifying them explicitly (for example, STOP DATABASE(DSNDB01)).

dbname and *dbstring* can have any of the forms in the following list (where *dbname1* and *dbname2* represent any strings of from 1 to 8 characters, and *dbname* represents any string of from 1 to 7 characters):

Form Stops...

dbname1:dbname2

All databases whose names collate greater than or equal to *dbname1* and less than or equal to *dbname2*

dbname*

All databases whose names begin with the string *dbname*

***dbname**

All databases whose names end with the string *dbname*

-STOP DATABASE (DB2)

dbname

All databases whose names contain the string *dbname*

dbstring1*dbstring2

All databases whose names contain the strings *dbstring1* and *dbstring2*

SPACENAM(*space-name*, ...)

Indicates names of table spaces or indexes within the specified database to stop.

Abbreviation: SPACE, SP

space-name

Is the name of one or more table spaces or index spaces to stop.

You can write *space-name* like *database-name* to designate:

- The name of a single table space or index space
- A range of names
- A partial name, including a beginning or ending pattern-matching character (*), pattern-matching character between two strings, or any combination of these uses.⁶

See “Usage notes” on page 313 for instructions on how to start a table space or index space again.

(*) Stops all table spaces and indexes of the specified database.

spacename and *spacestring* can have any of the forms in the following list (where *spacename1* and *spacename2* represent any strings of from 1 to 8 characters, and *spacename* represents any string of from 1 to 7 characters):

Form Displays the status of...

spacename1:spacename2

All table spaces or index spaces whose names collate greater than or equal to *spacename1* and less than or equal to *spacename2*

spacename*

All table spaces or index spaces whose names begin with the string *spacename*

***spacename**

All table spaces or index spaces whose names end with the string *spacename*

spacename

All table spaces or index spaces whose names contain the string *spacename*

spacestring1*spacestring2

All table spaces or index spaces whose names contain the strings *spacestring1* and *spacestring2*

PART (*integer*, ...)

Indicates the partition number of one or more partitions, within the specified table space or index, that are to be stopped. The START or STOP state of other partitions does not change.

The *integer* specified must identify a valid partition number for the corresponding space name and database name. If you specify nonvalid

6. Consecutive pattern-matching characters (*) are not allowed, and you cannot specify two pattern-matching characters in the middle of a keyword string.

-STOP DATABASE (DB2)

partition numbers, you receive an error message for each nonvalid number, but all valid partitions that you specified are stopped.

integer can be written to designate either:

- A list of one or more partitions, or
- A range of all partition numbers that collate greater than or equal to *integer1* and less than or equal to *integer2*

Both a list and a range cannot be specified.

PART is valid with partitioned table spaces, partitioned indexes, and nonpartitioned type 2 indexes of partitioned table spaces. If you specify PART with a nonpartitioned table space or index on a nonpartitioned table space, you receive an error message, and the nonpartitioned space is not stopped. When a logical partition is stopped, the index is not closed. A nonpartitioning index must be stopped without the use of PART to close the index.

AT(COMMIT)

Marks the specified object as being in STOPP status to prevent access from new requesters. Currently running applications are allowed to continue access until their next commit. After commit, further access by the committing application is prohibited. The object is actually stopped and put in STOP status when all jobs release their claims on it and all utilities release their drain locks on it. Specify AT(COMMIT) to break in on threads that are bound with RELEASE(DEALLOCATE), especially in situations where there is high thread reuse.

The option is ignored for declared temporary databases and table spaces within it.

Usage notes

Explicitly stopped databases: If table spaces and indexes are stopped explicitly (using the STOP DATABASE command with the SPACENAM option), they must be started explicitly using the START DATABASE command. Starting the database does not start table spaces or indexes that have been stopped explicitly.

Stopped table spaces, indexes, and partitions: Table spaces, indexes, and partitions are physically closed when the STOP DATABASE command is issued, except for logical partitions of a nonpartitioning index of a partitioned table space. Index spaces for declared temporary tables cannot be stopped or started.

Operation in TSO, MVS, and batch: When the STOP DATABASE command is issued from a TSO or an MVS console, the command operates asynchronously to keep the terminal free. When the command is issued from a batch job, it operates synchronously in case later steps depend on the database being stopped. The STOP DATABASE command drains work in progress on the database before stopping it. If it cannot get the drain locks on the first request, it repeatedly tries again. The command fails if it times out more than 15 times trying to get the locks or if a serious deadlock situation occurs.

Ensuring that all databases are stopped: When the STOP DATABASE command is processing asynchronously, message DSN9022I might be issued before the command completes. Message DSNT736I is issued to indicate that the asynchronous processing of the STOP DATABASE command is complete.

-STOP DATABASE (DB2)

Use the DISPLAY DATABASE command to check the stopped status of table spaces and indexes in a database. A status of STOPP indicates that the object is in the process of being stopped. A status of STOP indicates that the stop has completed and the object is in a stopped state. An object is not stopped until all currently active threads accessing the object are quiesced.

An object might remain in the STOP pending (STOPP) status if the STOP DATABASE command does not successfully complete processing.

Databases DSNDDF and DSNRLST: If the communication database (CDB) and the resource limit database (RLST) are active, they cannot be stopped. Those databases are active when created and are activated by DB2. For more information on the CDB, see Part 1 (Volume 1) of *DB2 Installation Guide*, and for the RLST, see Part 5 (Volume 2) of *DB2 Administration Guide*.

Stopping DSNDB01: If you try to stop the DSNDB01 database while an application plan or package is executing, you might receive a time out because of locking contention on DSNDB01. This is most likely to occur when an application plan or package is executing for the first time since DB2 was started, or if the skeleton cursor table (SKCT) for the plan or the skeleton package table (SKPT) for the package was swapped out of the EDM pool.

Table space in a restrictive status: If an application process requests a transaction lock on a table space that is in a restrictive status (RECP) or has a required index in a restrictive status, DB2 acquires the lock and does not detect the status until the application tries to access the table space or index. The application then receives SQLCODE -904 ("resource not available") and should release the lock, either by committing or rolling back (if the value of the RELEASE option is COMMIT) or by ending (if the value of RELEASE is DEALLOCATE). If you issue the command STOP DATABASE for either the table space or the index space while a transaction lock is in effect, the command is suspended. It repeatedly tries to get the locks needed to drain the work in progress before stopping the database. If the command times out more than 15 times trying to get the locks, it fails.

After a disk failure: Issuing the STOP DATABASE command before interrupting the I/O interface between the failed device and DB2 can result in incomplete I/O requests. To prevent this hang situation, create an interruption either by forcing the device offline using the MVS command VARY with the FORCE option, or by setting the I/O timing interval for the device before any failures. You can set the I/O timing interval through the IECIOSxx MVS parmlib member or by issuing the MVS command:

```
SETIOS MIH,DEV=dddd,IOTIMING=mm:ss
```

Stopping a LOB table space: The STOP DATABASE command can be used to stop LOB table spaces and indexes on auxiliary tables. LOB table spaces are stopped independently of the base table space with which the LOB table space is associated.

The following table summarizes the locking used by the STOP DATABASE command.

Table 30. Locking used by the STOP DATABASE command

Command	Table space type		Locks acquired
STOP AT COMMIT	Partitioned	PART	IX mass delete lock. Drain-all on partitions specified.

Table 30. Locking used by the STOP DATABASE command (continued)

Command	Table space type	Locks acquired
		IX mass delete lock. Drain-all on all partitions.
	<i>Non-partitioned</i>	IX mass delete lock. Drain-all on table space.
STOP	<i>Partitioned LOCKPART YES</i> PART	X-lock partitions specified. Drain-all on partitions specified.
		X-lock all partitions. Drain-all on all partitions.
	<i>Partitioned LOCKPART NO</i> PART	X-lock table space. Drain-all on partitions specified.
		X-lock table space. Drain-all on all partitions.
	<i>Non-partitioned</i>	X-lock table space. Drain-all on table space.

Examples

Example 1: Stop table space DSN8S71E in database DSN8D71A and close the data sets that belong to that table space.

```
-STOP DATABASE(DSN8D71A) SPACENAM(DSN8S71E)
```

Example 2: Stop all databases (except DSNDB01, DSNDB06, and work file databases)

```
-STOP DATABASE(*)
```

Example 3: Stop all databases (except DSNDB01, DSNDB06, and work file databases) when all jobs release their claims and all utilities release their drain locks.

```
-STOP DATABASE(*) AT(COMMIT)
```

Example 4: Stop the first partition of XEMP2, a nonpartitioning index of a partitioned table space in database DSN8D71A. Partition 1 is logically stopped and cannot be accessed by applications; however, no data sets are closed because parts of a nonpartitioning index are not associated with separate physical data sets.

```
-STOP DATABASE(DSN8D71A) SPACENAM(XEMP2) PART(1)
```

Example 5: Stop all table spaces with names that begin with "T" and end with the "IQUA03" string in database DSN8D71A.

```
-STOP DATABASE(DSN8D71A) SPACENAM(T*IQUA03)
```

Output similar to the following output indicates that the command completed successfully:

```
DSN9022I - DSNTDDIS 'STOP DATABASE' NORMAL COMPLETION
DSNT736I - ASYNCHRONOUS STOP DATABASE COMMAND HAS
COMPLETED FOR COMMAND: STOP DB(DSN8D71A) SPACE(T*IQUA03)
```

-STOP DB2 (DB2)

-STOP DB2 (DB2)

The DB2 command STOP DB2 stops the DB2 subsystem.

Abbreviation: -STO DB2

Environment

This command can be issued from an MVS console, a DSN session, a DB2I panel (DB2 COMMANDS), an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

Data sharing scope: Member


Authorization

To execute this command, the privilege set of the process must include one of the following:

- STOPALL privilege
- SYSOPR, SYSCTRL, or SYSADM authority

DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.

Syntax



Option descriptions

MODE

Indicates whether currently executing programs will be allowed to complete. For the effects of this option on distributed threads, see the description of the MODE option of “-STOP DDF (DB2)” on page 318.

(QUIESCE)

Allows currently executing programs to complete processing. No new program is allowed to start.

(FORCE)

Terminates currently executing programs, including utilities. No new program is allowed to start. MODE(FORCE) will probably cause indoubt situations. Some tasks, such as stored procedures tasks and DB2 service tasks, terminate abnormally. When they terminate abnormally, you might see dumps and messages from these failures.

CASTOUT

Specifies whether the DB2 member performs castout processing for the page sets or partitions for which the member was last updated. The CASTOUT option only applies in a data sharing environment.

YES

Allow group buffer pool castout processing.

NO

Skip group buffer pool castout processing.

Usage notes

MODE(QUIESCE): If MODE(QUIESCE) is used, all connected address spaces must terminate all connections before the DB2 subsystem stops. The system operator can tell whether any connections remain by using the DISPLAY THREAD command, and can cancel them by using the DB2 CANCEL command or MVS commands.

MODE(FORCE): A forced stop does not cause an immediate abend. If a connected task is executing outside DB2, DB2 posts an exit to stop the task from accessing DB2. If a task is executing in DB2, it stops when the next “suspend” or “execution unit switch” occurs. In some cases, the delay before stopping can be significant.

CASTOUT(NO): Consider using CASTOUT(NO) when shutting down a DB2 data sharing member for maintenance, because the option can speed shutdown processing in a data sharing environment. If you are shutting down multiple members of a data sharing group with CASTOUT(NO), some changed data might reside in the group buffer pools after the members have shut down. Therefore, if you want consistent data on disk, (for example, you are shutting down all members to create a copy of the database to send offsite) do not use CASTOUT(NO).

With CASTOUT(NO), the DB2 member shuts down with QC status, as displayed by the DISPLAY GROUP command, which indicates that the member quiesced with some castout processing not completed. A retained page set or partition P-lock is held in IX state for each object for which the DB2 member was the last updater. Also, group buffer pool connections enter failed-persistent state.

Example

Example 1: Stop the DB2 subsystem. Allow currently active programs to complete. Do not allow new programs to identify to DB2.

```
-STOP DB2 MODE (QUIESCE)
```

Example 2: Stop a member of a data sharing group for maintenance.

```
-STOP DB2 MODE (QUIESCE) CASTOUT(NO)
```

-STOP DDF (DB2)

-STOP DDF (DB2)

The DB2 command STOP DDF stops the distributed data facility (DDF) if it has already been started; use this command to terminate the DDF interface to VTAM or TCP/IP.

Abbreviation: -STO DDF

Environment

This command can be issued from an MVS console, a DSN session under TSO, a DB2I panel (DB2 COMMANDS), an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

Data sharing scope: Member


Authorization

To execute this command, the privilege set of the process must include one of the following authorities:

- SYSOPR
- SYSCTRL
- SYSADM

DB2 commands that are issued from an MVS console are not associated with any secondary authorization IDs.

Syntax



Option descriptions

MODE

Indicates whether currently executing active distributed threads are allowed to complete.

(QUIESCE)

Allows active distributed threads that are using DDF to complete normally and terminates only inactive distributed threads. If DDF THREADS ACTIVE was specified during DB2 installation, all DDF threads are active threads.

(FORCE)

Terminates all currently executing distributed threads.

Some tasks, such as stored procedures tasks and DB2 service tasks, terminate abnormally. When they terminate abnormally, you might see dumps and messages resulting from these failures.

(SUSPEND)

Suspends all DDF threads by:

-STOP DDF (DB2)

- Keeping inactive DDF threads inactive until a subsequent START DDF command is issued
- Terminating all DDF pool threads
- Preventing inbound DDF work from starting

MODE(SUSPEND) is intended to be used at a DB2 DRDA server when locking conflicts exist between CREATE, ALTER, DROP, GRANT, or REVOKE operations and client access to data. Requests that normally cause work to be dispatched (including requests for new connections) are queued. Outbound DDF processing is not affected by this command.

CANCEL (*n*)

Specifies to cancel all active DDF database access threads if suspend processing does not complete in *n* seconds. The range of *n* is 0 to 9999.

WAIT (*n*)

Specifies to resume DDF processing if suspend processing does not complete in *n* seconds. The range of *n* is 0 to 9999.

Usage notes

MODE(QUIESCE): If MODE(QUIESCE) is used, all distributed activity must complete before DDF stops. The operator can tell whether any distributed threads remain by using DISPLAY THREAD with the LOCATION option. To cancel distributed threads that are preventing DDF from stopping, see “Usage notes” on page 78 for CANCEL THREAD, or use STOP DDF MODE(FORCE).

MODE(QUIESCE) forces any inactive threads to terminate. A requesting system that is using two-phase commit on an inactive thread might report the terminated thread as indoubt at the system that issued STOP DDF. The thread is not actually indoubt (no commit or rollback is pending), and the condition is resolved when DDF is restarted.

MODE(FORCE): If MODE(FORCE) is used, the DB2 connection to VTAM or TCP/IP terminates. The termination forces all VTAM or TCP/IP requests to complete immediately, indicating that a communications error has occurred and DDF has stopped. A forced stop might take as long as three minutes to complete.

If any applications are updating remote servers that use two-phase commit, MODE(FORCE) might result in indoubt threads at each server.

MODE(SUSPEND): If MODE(SUSPEND) completes successfully, additional database resources, which are not inbound DDF work, might still be held. Cancel these additional resources with CANCEL THREAD as described in “-CANCEL THREAD (DB2)” on page 77.

Table 31 summarizes the actions that DB2 takes when START DDF or STOP DDF are issued with different DDF states.

Table 31. The result of commands on the DDF status

DDF status	Command issued			
	START DDF	STOP DB2 or STOP DDF without MODE(FORCE)	STOP DB2 or STOP DDF with MODE(FORCE)	STOP DDF MODE(SUSPEND)
Starting	DSNL003I	DSNL003I	DSNL003I	DSNL003I

-STOP DDF (DB2)

Table 31. The result of commands on the DDF status (continued)

Started	DSNL001I	DDF stops	DDF forced stop	DDF suspends
Stopping	DSNL005I	DSNL005I	DSNL005I	DSNL005I
Stopped	DDF starts	DSNL002I	DSNL002I	DSNL002I
Suspending	DDF resumes	DDF stops	DDF forced stop	DSNL069I
Suspended	DDF resumes	DDF stops	DDF forced stop	DSNL065I

Examples

Example 1: Stop the distributed data facility (MODE QUIESCE).

```
-STOP DDF
```

Example 2: Stop the distributed data facility (MODE FORCE).

```
-STOP DDF MODE(FORCE)
```

Example 3: Suspend distributed data facility activity (MODE SUSPEND). If command processing continues after 600 seconds, cancel any remaining DDF threads.

```
-STOP DDF MODE(SUSPEND) CANCEL(600)
```

-STOP FUNCTION SPECIFIC

The DB2 command STOP FUNCTION SPECIFIC prevents DB2 from accepting SQL statements with invocations of the specified functions. This command does not prevent SQL statements with invocations of the functions from running if they have already been queued or scheduled by DB2. You cannot use this command to stop built-in functions or user-defined functions that are sourced on another function.

DB2 implicitly issues the command STOP FUNCTION SPECIFIC ACTION(REJECT) for any function that exceeds the maximum abend count. That count is set by the MAX ABEND COUNT field of installation panel DSNTIPX.

Abbreviation: -STO FUNC SPEC

Environment

This command can be issued from an MVS console, a DSN session under TSO, a DB2I panel (DB2 COMMANDS), an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

#

Data sharing scope: Group or local, depending on the value of the SCOPE option.

Authorization

To execute this command, the privilege set of the process must include one of the following authorities for each function:


- Ownership of the function
- SYSOPR authority
- SYSCTRL authority
- SYSADM authority

If -STOP FUNCTION SPECIFIC *.* or schema.partial-name* is specified, the privilege set of the process must include one of the following authorities:

- SYSOPR authority
- SYSCTRL authority
- SYSADM authority

DB2 commands that are issued from an MVS console are not associated with any secondary authorization IDs.

Syntax



-STOP FUNCTION SPECIFIC

Option descriptions

(*.*)

Stops access to all functions, including functions that DB2 applications have not yet accessed.

If no functions are named, all functions are stopped.

schema.specific-function-name

Stops one specific function name. You cannot specify a function name as you can in SQL; you must use the specific name. If a specific name was not specified on the CREATE FUNCTION statement, query SYSIBM.SYSROUTINES for the correct specific name:

```
SELECT SPECIFICNAME, PARM_COUNT
FROM SYSIBM.SYSROUTINES
WHERE NAME='function_name'
AND SCHEMA='schema_name';
```

For overloaded functions, this query can return multiple rows.

*schema.partial-name**

Stops a set of functions in the specified schema. The specific names of all functions in the set begin with *partial-name* and can end with any string, including the empty string. For example, schema1.ABC* stops all functions with specific names that begin with ABC in schema1.

ACTION

Indicates what to do with an SQL statement that invokes the function while the function is stopped. If you issue STOP FUNCTION SPECIFIC more than once for a given function, the action that is taken is determined by the ACTION option on the most recent command.

(QUEUE)

Queues the request until either of the following conditions is true:

- The wait exceeds the installation timeout value.
- You issue START FUNCTION SPECIFIC command for the function.

(REJECT)

Rejects the request.

SCOPE

Specifies the scope of the command.

(LOCAL)

Specifies to stop the function on the local member only.

(GROUP)

Specifies to stop the function on all members of the data sharing group.

#

Usage notes

Limitations of STOP FUNCTION SPECIFIC: STOP FUNCTION SPECIFIC is only applicable to external functions that run in the WLM application environment. STOP FUNCTION SPECIFIC cannot stop a built-in function or a user-defined function sourced on another function.

Permanently disabling a function: A stopped function does not remain stopped if DB2 is stopped and restarted. To disable a function permanently, you can:

- Use ALTER FUNCTION to change the LOADMOD name to a nonexistent MVS load module

- Rename or delete the MVS load module

Examples

Example 1: Stop access to all functions. While the -STOP FUNCTION SPECIFIC command is in effect, DB2 queues all attempts to execute functions.

```
-STOP FUNCTION SPECIFIC ACTION(Queue)
```

This command produces output similar to the following output:

```
DSN9022I - DSNX9COM '-STOP FUNC' NORMAL COMPLETION
```

Example 2: Stop access to all functions. While the -STOP FUNCTION SPECIFIC command is in effect, DB2 rejects attempts to execute functions.

```
-STOP FUNCTION SPECIFIC ACTION(REJECT)
```

This command produces output similar to the following output:

```
DSN9022I - DSNX9COM '-STOP FUNC' NORMAL COMPLETION
```

Example 3: Stop functions PAYROLL.USERFN1 and PAYROLL.USERFN3. While the -STOP FUNCTION SPECIFIC command is in effect, DB2 queues all attempts to execute functions.

```
-STOP FUNCTION SPECIFIC(PAYROLL.USERFN1,PAYROLL.USERFN3)
```

This command produces output similar to the following output:

```
DSN9022I - DSNX9COM '-STOP FUNC' NORMAL COMPLETION
```

Example 4: Stop functions PAYROLL.USERFN1 and PAYROLL.USERFN3. While the -STOP FUNCTION SPECIFIC command is in effect, DB2 rejects attempts to execute either of these functions.

```
-STOP FUNCTION SPECIFIC(PAYROLL.USERFN1,PAYROLL.USERFN3) ACTION(REJECT)
```

This command produces output similar to the following output:

```
DSN9022I - DSNX9COM '-STOP FUNC' NORMAL COMPLETION
```

STOP ...(MVS IRLM)

STOP irlmproc (MVS IRLM)

The STOP *irlmproc* command shuts IRLM down normally. The command is rejected if any active DB2 subsystems are currently identified to IRLM.

Abbreviation: P

Environment

This command can be issued only from an MVS console.

Data sharing scope: Member

Authorization

The command requires an appropriate level of MVS authority, as described in *OS/390 MVS System Commands*.

Syntax

```
►►—STOP—irlmproc—◄◄
```

Option description

irlmproc

Identifies the procedure name for the IRLM to be stopped.

Usage note

Terminating the IRLM: If IRLM does not shut down normally, issue the MODIFY irlmproc,ABEND command to terminate the IRLM abnormally. If there are outstanding DB2 requests in process and IRLM will not terminate, use the MVS CANCEL command. If all other means of removing the subsystem fail, issue the MVS FORCE CANCEL command:

```
F irlmproc,ABEND,DUMP
```

Example

Enter on the MVS1 system console:

```
P KRLM1
```

IRLM responses on MVS1 system console:

```
DXR165I IR21 TERMINATED VIA IRLM MODIFY COMMAND  
DXR121I IR21 END-OF-TASK CLEANUP SUCCESSFUL - HI-CSA      325K
```

Response on MVS2 system console:

```
DXR025I JRLM SESSION LOST, SHARING STATE IS IRLM FAILED
```

The operator on system 1 has terminated the IRLM procedure named KRLM1. The operator on system 2 is informed that the IRLM in system 1 has terminated, but no operator action on system 2 is required.

STOP ...(MVS IRLM)

In a data sharing environment: You cannot issue the P command to IRLM in a data sharing group until there are no DB2s identified and the IRLM has issued the following messages:

```
DXR136I IR21 HAS DISCONNECTED FROM THE DATA SHARING GROUP
```

Any members that are still active in the group issue:

```
DXR137I JR21 GROUP STATUS CHANGED. IR21 233 HAS BEEN DISCONNECTED  
FROM THE DATA SHARING GROUP
```

-STOP PROCEDURE (DB2)

-STOP PROCEDURE (DB2)

The DB2 command STOP PROCEDURE prevents DB2 from accepting SQL CALL statements for one or more stored procedures. You can qualify stored procedure names with a schema name. This command does not prevent CALL statements from running if they have already been queued or scheduled by DB2.

If the DB2 established stored procedure address space is connected to DB2, MVS stops it based on the syntax of the STOP PROCEDURE command.

DB2 implicitly issues the command STOP PROCEDURE ACTION(REJECT) for any stored procedure that exceeds the maximum abend count. That count is set by the MAX ABEND COUNT field of installation panel DSNTIPX.

Abbreviation: -STO PROC

Environment

This command can be issued from an MVS console, a DSN session under TSO, a DB2I panel (DB2 COMMANDS), an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

Data sharing scope: Group or local, depending on the value of the SCOPE option.

Authorization

To execute this command, the privilege set of the process must include one of the following:


- SYSOPR authority
- SYSCTRL authority
- SYSADM authority
- Ownership of the stored procedure.

If you specify -STOP PROCEDURE *.* or schema.partial-name*, the privilege set of the process must include one of the following:

- SYSOPR authority
- SYSCTRL authority
- SYSADM authority

DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.

Syntax



Option descriptions

(*.*)

Stops access to all stored procedures in all schemas, including procedure definitions that have not yet been accessed by DB2 applications. The DB2-established stored procedures address space terminates after active work is complete.

(schema.procedure-name)

Identifies the fully-qualified procedure name that is to be stopped.

(schema.partial-name*)

Stops a set of stored procedures in the specified schema. The names of all procedures in the set begin with *partial-name* and can end with any string, including the empty string. For example, PAYROLL.* stops all stored procedures in the PAYROLL schema.

procedure-name

Identifies one or more specific stored procedure names to be stopped. The procedure name is implicitly qualified with the SYSPROC schema name.

partial-name*

Stops a set of stored procedures within the SYSPROC schema. The names of all procedures in the set begin with *partial-name* and can end with any string, including the empty string. For example, ABC* stops all stored procedures with names that begin with ABC.

ACTION

Indicates what to do with a CALL statement that is received while the procedure is stopped. If STOP PROCEDURE is issued more than once for a given procedure, the action taken is determined by the ACTION option on the most recent command.

(QUEUE)

Queues the request until either:

- The wait exceeds the installation timeout value, or
- The stored procedure is started by the command START PROCEDURE.

(REJECT)

Rejects the request

-STOP PROCEDURE (DB2)

SCOPE

Specifies the scope of the command.

(LOCAL)

Specifies to stop the procedure on the local member only.

(GROUP)

Specifies to stop the procedure on all members of the data sharing group.

Usage notes

Permanently disabling a stored procedure: A stopped procedure does not remain stopped if DB2 is stopped and restarted. To disable a stored procedure permanently, you can:

- Drop the procedure using the DROP PROCEDURE statement. See Chapter 5 of *DB2 SQL Reference* for more information.
- Use an ALTER PROCEDURE statement.
- Rename or delete the MVS load module.

Stored procedure address space management differences: The STOP PROCEDURE command operates differently depending upon how the DB2 stored procedures address spaces are established. For more information, see Part 4 (Volume 1) of *DB2 Administration Guide*.

Examples

Example 1: Stop access to all stored procedures, and terminate the DB2 stored procedures address space. While the -STOP PROCEDURE command is in effect, attempts to execute stored procedures are queued.

```
-STOP PROCEDURE ACTION(Queue)
```

```
DSNX947I - DSNX9SP2 STOP PROCEDURE SUCCESSFUL FOR *.*  
DSN9022I - DSNX9COM '-STOP PROC' NORMAL COMPLETION
```

Example 2: Stop access to all stored procedures, and terminate the DB2 stored procedures address space. While the -STOP PROCEDURE command is in effect, attempts to execute stored procedures are rejected.

```
-STOP PROCEDURE ACTION(REJECT)
```

```
DSNX947I - DSNX9SP2 STOP PROCEDURE SUCCESSFUL FOR *.*  
DSN9022I - DSNX9COM '-STOP PROC' NORMAL COMPLETION
```

Example 3: Stop stored procedures USERPRC1 and USERPRC3. While the -STOP PROCEDURE command is in effect, attempts to execute these stored procedure are queued.

```
-STOP PROCEDURE(USERPRC1,USERPRC3)
```

```
DSNX947I - DSNX9SP2 STOP PROCEDURE SUCCESSFUL FOR USERPRC1  
DSNX947I - DSNX9SP2 STOP PROCEDURE SUCCESSFUL FOR USERPRC3  
DSN9022I - DSNX9COM '-STOP PROC' NORMAL COMPLETION
```

Example 4: Stop stored procedures USERPRC1 and USERPRC3. While the -STOP PROCEDURE command is in effect, attempts to execute these stored procedure are rejected.

```
-STOP PROCEDURE(USERPRC1,USERPRC3) ACTION(REJECT)
```

```
DSNX947I - DSNX9SP2 STOP PROCEDURE SUCCESSFUL FOR USERPRC1  
DSNX947I - DSNX9SP2 STOP PROCEDURE SUCCESSFUL FOR USERPRC3  
DSN9022I - DSNX9COM '-STOP PROC' NORMAL COMPLETION
```

-STOP RLIMIT (DB2)

The DB2 command STOP RLIMIT stops the resource limit facility. -STOP RLIMIT resets all previously set limits to infinity and resets the accumulated time to zero. All previously limited SQL statements (SELECT, UPDATE, DELETE, and INSERT) executed through an SQL PREPARE or EXECUTE IMMEDIATE statement run with no limit.

Abbreviation: -STO RLIM

Environment

This command can be issued from an MVS console, a DSN session under TSO, a DB2I panel (DB2 COMMANDS), an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

Data sharing scope: Member

Authorization

To execute this command, the privilege set of the process must include one of the following:

- SYSOPR authority
- SYSCTRL authority
- SYSADM authority

DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.

Syntax

```
▶▶—STOP RLIMIT—▶▶
```

Example

Stop the resource limit facility.
-STOP RLIMIT

-STOP TRACE (DB2)

-STOP TRACE (DB2)

The DB2 command STOP TRACE stops tracing.

There is an additional option to this command and values for a few options that are not described here. They are intended for service and use under the direction of IBM support personnel. For details, see *DB2 Diagnosis Guide and Reference*.

Abbreviation: -STO TRA

Environment

This command can be issued from an MVS console, a DSN session, a DB2I panel (DB2 COMMANDS), an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

Data sharing scope: Group or local, depending on the value of the SCOPE option.


Authorization

To execute this command, the privilege set of the process must include one of the following:

- TRACE privilege
- SYSOPR, SYSCTRL, or SYSADM authority

DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.

Syntax



Option descriptions

Each option that you use, except TNO, limits the effect of the command to active traces that were started using the same option, either explicitly or by default, with exactly the same parameter values. For example, the following command stops only the active traces that were started using the options *PERFM* and *CLASS (1,2)*:

```
-STOP TRACE (PERFM) CLASS (1,2)
```

This command does *not* stop, for example, any trace started using *CLASS(1)*.

You must specify a trace type or an asterisk. For example, the following command stops all active traces:

```
-STOP TRACE (*)
```

When stopping trace classes, a special circumstance occurs if monitor trace class 6 is active. Monitor trace class 6 enables and disables data propagation. To avoid

-STOP TRACE (DB2)

accidentally stopping this trace class, the commands -STOP TRACE(*) and -STOP TRACE(MON) CLASS(*) fail if monitor trace class 6 is active.

To stop monitor trace class 6, you must explicitly specify it as one of the arguments of the CLASS option of the -STOP TRACE command, including any other monitor trace classes that were started with monitor trace class 6. For example, if monitor trace class 6 was started with the command -START TRACE(MON) CLASS(1,3,6), the following command stops it:

```
-STOP TRACE(MON) CLASS(1,3,6)
```

In the case where monitor trace class 6 was started with the command -START TRACE(MON) CLASS(*), you must explicitly specify all 32 monitor trace classes to have monitor trace class 6 stopped:

```
-STOP TRACE(MON) CLASS(1,2,3,4,5,6,...32)
```

However, if monitor trace class 6 is not active the -STOP TRACE(*) command stops all active traces.

Each of the following keywords limits the command to stopping traces of the corresponding type. For further descriptions of each type, see “-START TRACE (DB2)” on page 299.

Table 32. Trace types

Type	Description	Abbreviation
PERFM	Performance records of specific events	P
ACCTG	Accounting records for each transaction	A
STAT	Statistical data	S
AUDIT	Audit data	AU
MONITOR	Monitor data	MON

SCOPE

Specifies the scope of the command.

(LOCAL)

Stops the trace only on the local DB2 subsystem.

(GROUP)

Stops the trace on all members of a data sharing group.

COMMENT(string)

Gives a comment that is reproduced in the trace output record for the STOP TRACE command (except in the resident trace tables).

string is any SQL string; it must be enclosed between apostrophes if it includes a blank, comma, or special character.

DEST

Limits stopping to traces started for particular destinations. You can use more than one value, but do not use the same value twice. If you do not specify a value for DEST, DB2 does not use destination to limit which traces to stop.

Abbreviation: D

Possible values and their meanings are:

Value Trace destination

GTF The generalized trace facility

SMF The System Management Facility

SRV An exit to a user-written routine

OP n A specific destination. n can be a value from 1 to 8

See “-START TRACE (DB2)” on page 299 for a list of allowable destinations for each trace type.

PLAN(*plan-name*, ...)

Limits stopping to traces started for particular application plans. You can use up to eight plan names. If you use more than one name, you can use only one value for AUTHID, TNO, and LOCATION. Do not use this option with STAT.

The **default** is **PLAN(*)**, which does not limit the command.

AUTHID(*authorization-id*, ...)

Limits stopping to traces started for particular authorization identifiers. You can use up to eight identifiers. If you use more than one identifier, you can use only one value for PLAN, TNO, and LOCATION. Do not use this option with STAT.

The **default** is **AUTHID(*)**, which does not limit the command.

CLASS(*integer*, ...)

Limits stopping to traces started for particular classes. For descriptions of the allowable classes, see “-START TRACE (DB2)” on page 299. You cannot specify a class if you did not specify a trace type.

Abbreviation: C

The **default** is **CLASS(*)**, which does not limit the command.

TNO(*integer*, ...)

Limits stopping to particular traces, identified by their trace numbers (1 to 32, 01 to 09). You can use up to eight trace numbers. If you use more than one number, you can use only one value each for PLAN, AUTHID, and LOCATION.

The **default** is **TNO(*)**, which does not limit the command.

LOCATION(*location-name*, ...)

Introduces a list of specific location names for which traces are stopped. Limits the traces you can stop to those started for threads with connections to remote locations; the use of the LOCATION option precludes stopping traces of non-distributed threads.

You can specify up to eight location names. If you use more than one location name, you can only use one value for PLAN, AUTHID, and TNO. You cannot use this option with STAT.

The **default** is **LOCATION()**, which does not limit the command.

(*) LOCATION(*) limits the command to those traces that were started with the one or more location names specified on the LOCATION keyword of -START TRACE.

<luname>

Stops the DB2 trace for the remote clients that are connected to DDF through the remote SNA LU that you specify in <luname>.

ipaddr

Stops the DB2 trace for remote clients that are connected to DDF through the remote TCP/IP host. *nnn.nnn.nnn.nnn* is the dotted decimal IP address.

Requesters other than DB2 for OS/390 and z/OS: DB2 does not receive a location name from requesters that are not DB2. To display information about a requester that is not a DB2 for OS/390 and z/OS subsystem, enter its

-STOP TRACE (DB2)

LUNAME, enclosed by the less-than (<) and greater-than (>) symbols. For example, to display information about a requester with the LUNAME of LULA, enter the following command:

```
-STOP TRACE (*) LOCATION (<LULA>)
```

DB2 uses the <LUNAME> notation in messages displaying information about requesters that are not DB2 for OS/390 and z/OS.

Usage notes

Traces started by a IFI/IFC program: Before you stop an active trace, ensure that an IFI application program or the IFC Selective Dump utility (DSN1SDMP) did not start the trace. If you stop a trace started by DSN1SDMP, the DSN1SDMP utility abnormally terminates.

Examples

Example 1: Stop all traces that have the generalized trace facility as their only destination.

```
-STOP TRACE (*) DEST (GTF)
```

Example 2: Stop an accounting trace of all threads between the local and USIBMSTODB21 DB2 subsystems for plan DSN8BC71. Include a comment.

```
-STOP TRACE (ACCTG)
PLAN (DSN8BC71)
LOCATION (USIBMSTODB21)
COMMENT('ACCTG TRACE FOR DSN8BC71')
```

Example 3: Stop trace number 4.

```
-STOP TRACE (P) TNO(4)
```

Example 4: Stop all active traces of any type for USIBMSTODB22.

```
-STOP TRACE (*) LOCATION (USIBMSTODB22)
```

Example 5: Stop all performance traces.

```
-STOP TRACE=P
```

Example 6: Stop all monitor tracing.

```
-STOP TRACE(MON)
```

#

Example 7: Stop all monitor tracing in a data sharing group.

```
-STOP TRACE(MON) SCOPE(GROUP)
```

-TERM UTILITY (DB2)

The DB2 command TERM UTILITY terminates execution of a DB2 utility job step and releases all resources associated with the step. When executing, a utility does not terminate until it checks to see that -TERM was issued. Active utilities perform this check periodically. If the utility is stopped, all its resources are released by -TERM. An active utility can be terminated only from the DB2 on which it is running. A stopped utility can be terminated from any active member of the data sharing group.

Abbreviation: -TER UTIL

Environment

This command can be issued from an MVS console, a DSN session, DB2I panels DB2 COMMANDS and DB2 UTILITIES, an IMS or CICS terminal, or a program using the instrumentation facility interface (IFI).

Data sharing scope: Group or member. The utility is implicitly of group scope when the utility is stopped. For release dependency information, see *DB2 Data Sharing: Planning and Administration*.

Authorization

To execute this command, the primary or some secondary authorization ID of the process must be the ID that originally submitted the utility job, or the privilege set of the process must include one of the following:


- DBMAINT, DBCTRL, or DBADM authority
- SYSOPR, SYSCTRL, or SYSADM authority

DB2 commands issued from an MVS console are not associated with any secondary authorization IDs.

For users with DBMAINT, DBCTRL, or DBADM authority, the command takes effect only when it can be determined that the user has sufficient authority over each object that the utility job accesses.

Database DSNDB06 contains the table spaces and index spaces required to check authorization. If a table or index space required for authorization checking is affected by a utility which you need to terminate, then installation SYSADM authority is required to terminate that utility.

Syntax



Option descriptions

One of the following parameters must be specified.

-TERM UTILITY (DB2)

(*utility-id*)

Is the utility identifier, or the UID parameter used when creating the utility job step.

If *utility-id* was created by the DSNU CLIST by default, it has the form *tso-userid.control-file-name*. For the control file name that is associated with each utility, see the description of the DSNU utility in *DB2 Utility Guide and Reference*.

If *utility-id* was created by default by the EXEC statement invoking DSNUTILB, then the token has the form *userid.jobname*.

(*partial-utility-id**)

Terminates every utility job that begins with *partial-utility-id*. For example, -TERM UTILITY(ABCD*) terminates every utility job step whose utility identifier begins with the letters ABCD. If you have a two-part utility ID, such as ABCD.EFGH, -TERM UTILITY(ABCD*) also terminates that utility.

(*) Terminates every utility job step known to DB2 for which you are authorized.

Usage notes

Restarting utilities: A terminated utility job step cannot be restarted. You must resubmit the step as a new utility job.

What happens to particular utilities: In some cases, terminating a utility job can leave work in an undesirable state, requiring special processing before the job can be resubmitted. The following list describes the effects of -TERM on jobs for each of the utilities:

Utility	Special effects of -TERM
CATMAINT	Places indexes on REBUILD-pending status.
CHECK DATA	Table spaces remain in CHECK-pending status.
CHECK INDEX	None
CHECK LOB	Places LOB table spaces and indexes in the utility read-only (UTRO) state.
COPY	Inserts "T" record in SYSIBM.SYSCOPY. When you run COPY, it does not allow an incremental image copy if the "T" record exists.
DIAGNOSE	None
LOAD	See <i>DB2 Utility Guide and Reference</i> for the effect of -TERM on the LOAD utility phases
MERGECOPY	None
MODIFY RECOVERY	None
MODIFY STATISTICS	None
QUIESCE	None
REBUILD INDEX	Places the object being rebuilt in REBUILD-pending status
RECOVER	Places the object being recovered in RECOVER-pending status
REORG INDEX	See <i>DB2 Utility Guide and Reference</i> for the effect of -TERM on the REORG INDEX utility phases

-TERM UTILITY (DB2)

	REORG TABLESPACE	See <i>DB2 Utility Guide and Reference</i> for the effect of -TERM on the REORG TABLESPACE utility phases
	REPAIR	None
	REPORT	None
	RUNSTATS	None
	STOSPACE	None
	UNLOAD	The output data set remains incomplete until you restart the utility job or delete the data set.

Examples

Example 1: Terminate all utility jobs for which you are authorized.

```
-TERM UTILITY (*)
```

Example 2: Terminate all utility jobs whose utility ID begins with SMITH.

```
-TERM UTILITY  
  (SMITH*)
```

/TRACE (IMS)

The IMS /TRACE command directs and controls the IMS capabilities for tracing internal IMS events. It also starts, stops, and defines the activity to be monitored by the IMS Monitor. For more information about the IMS Monitor, see *IMS Utilities Reference: System*.

Abbreviation: /TRA

Environment

This command can be issued only from an IMS terminal.


Data sharing scope: Member

Authorization

To enter this command, users must have passed the IMS security check, as described in *IMS Administration Guide: System*.

The syntax diagram below includes only those parameters that DB2 users need to know. For a diagram with the complete syntax of this command, see *IMS Command Reference*.

Syntax



Option descriptions

The option descriptions for the /TRACE command are described in *IMS Command Reference*; however, this section provides information about the two parameters that are especially important for DB2 users.

SUBS

Indicates that the external subsystem trace table (containing information about every interaction with DB2) is to be enabled or disabled. SET ON TABLE SUBS enables the DB2 trace facility, and SET OFF TABLE SUBS disables it.

If nothing is specified with the TABLE keyword, then the default is ALL; ALL includes SUBS, as well as other trace tables.

LOG

Specifies that traced data is to be written to the IMS system log. Because IMS has a tracing mechanism that writes trace entries to the IMS system log, it is important that DB2 users specify SET ON and TABLE OPTION LOG.

Otherwise, the trace information that IMS provides will not be available unless a control region dump occurs.

Examples

Example 1: This command starts IMS tracing and:

- Enables the DB2 trace
- Writes IMS trace tables to the IMS log before they wrap.

```
/TRACE SET ON TABLE SUBS OPTION LOG
```

Example 2: This command starts IMS tracing and:

- Enables all trace tables (including DB2 trace tables); (ALL is the default parameter for the TABLE keyword)
- Writes IMS trace tables to the IMS log before they wrap.

```
/TRACE SET ON TABLE ALL OPTION LOG
```

TRACE CT (MVS IRLM)

The MVS command TRACE CT starts, stops, or modifies a diagnostic trace for the internal resource lock manager (IRLM) of DB2. IRLM does not support all the options available on the TRACE command as described in *OS/390 MVS System Commands*.

Environment

This command can be issued only from an MVS console.


Data sharing scope: Member

Authorization

This command requires an appropriate level of MVS authority, as described in *OS/390 MVS System Commands*.

The syntax diagram and option descriptions for this command are purposely incomplete. Options that are not shown are described in *OS/390 MVS System Commands*.

Syntax



Option descriptions

CT

Specifies the component trace. (Do not use other trace options available on the MVS TRACE command).

WTRSTART=parmlibmem

Identifies the member that contains source JCL. That JCL executes the CTRACE writer and defines the data set to which it writes the trace buffers. This member can be a procedure cataloged in SYS1.PROCLIB or a job.

WRAP

Specifies that when the system reaches the end of the group of data sets, it writes over the oldest data at the beginning of the first data set in the group. The system uses only the primary extents of the data sets.

NOWRAP

Specifies that the system stops writing to the data sets when they are all full. The system uses the primary and secondary extents of the data sets.

WTRSTOP=jobname

Stops the CTRACE writer for a trace that is running. The system also closes the data sets that the writer used.

jobname identifies the trace, either by:

- Member name, if the source JCL is a procedure
- Job name, if that appears on a JOB statement in the source JCL

ON

Turns on the trace.

COMP=irlmssnm

Gives the IRLM subsystem name.

SUB=subname

Specifies the type of sublevel trace. Traces INT, EXP, and XIT are ON by default. You cannot turn off traces INT and EXP. If you do not specify a subname on the TRACE command, the trace is performed on all subnames that you control. Specifying one subname restricts the traces to that trace plus the EXP and INT traces.

Use:	To trace:
DBM	Interactions with the identified DBMS
EXP	Any exception condition
INT	Member and group events outside normal locking activity
SLM	Interactions with the MVS locking component
XCF	All interactions with MVS cross-system coupling services
XIT	Only asynchronous interactions with the MVS locking component

OFF

Turns off the trace. If IRLM is connected to a CTRACE writer for the component trace, the system disconnects it.

Usage notes

Include the IRLM load module in the MVS link list: This command uses MVS component trace services. Include the IRLM load module DXRRL183, which contains a routine for stopping and starting, in the MVS link list.

Displaying a trace: To display a trace, use the MVS DISPLAY command:

```
D TRACE,COMP=IRLM001
```

Monitoring a trace: To monitor a trace, use the MVS MODIFY irlmproc,STATUS,TRACE command on page 232.

Setting the number of trace buffers: To set the number of trace buffers used by traces, use the MVS MODIFY irlmproc,SET command on page 228.

Sample procedure for the CTRACE writer: This procedure identifies the data set to which the next sample procedure writes data.

TRACE CT (MVS IRLM)

```
//CTWTR    PROC
//          EXEC PGM=ITTTTCWR
//TRCOUT01 DD    DSNAME=SYS1.WTR1,DISP=OLD
//TRCOUT02 DD    DSNAME=SYS1.WTR2,DISP=OLD
```

Sample procedure to start and stop a DBM trace to the CTRACE writer: After you enter the command TRACE CT,WTRSTART, turn the trace on and connect the writer, using the WTR parameter in the reply for the command TRACE CT.

```
TRACE CT,WTRSTART=CTWTR
TRACE CT,ON,COMP=IRLM001,SUB=(DBM)
:
```

```
      (MVS asks for a reply)
:
```

```
R 15,WTR=CTWTR,END
TRACE CT,OFF,COMP=IRLM001,SUB=(DBM)
:
```

```
      (Wait to make sure trace buffers are externalized.)
TRACE CT,WTRSTOP=CTWTR
```

Sample procedure to start and stop traces in wrap-around mode: Traces captured in this procedure are saved in a limited number of buffers that are provided by IRLM. Each buffer is reused when the previous buffer is filled. To start the trace in this wrap-around mode, enter the following commands:

```
TRACE CT,ON,COMP=IRLM001
:
```

```
      (MVS asks for a reply)
:
```

```
R 15,END
:
```

```
TRACE CT,OFF,COMP=IRLM001
```

Impact of setting TRACE CT ON: Each active subname type requires up to 0.7 MB of ECSA. Because IRLM initializes its own traces when it starts, the DISPLAY TRACE command shows that all traces are off. After you issue the TRACE ON command, the reports are accurate except for the two subname types, INT and EXT, which cannot be turned off.

Appendix A. Directory of subsystem parameters

Editing the subsystem parameters and DSNHDECP values

The subsystem parameter module is generated by job DSNTIJUZ each time you install, migrate, or update DB2. Seven macros expand to form this data-only subsystem parameter load module. It contains the DB2 execution-time parameters that you selected using the ISPF panels. These seven macros are DSN6ARVP, DSN6ENV, DSN6FAC, DSN6LOGP, DSN6SPRM, DSN6SYSP, and DSN6GRP.

The data-only load module DSNHDECP is also generated by job DSNTIJUZ. It contains the application programming defaults.

Directory of subsystem parameters and DSNHDECP values

Table 33 shows you each macro parameter, the macro where it is located, installation panel name, whether it can be updated online, and its corresponding page number. Online update capability does not apply to macro DSNHDECP so values are not listed for those parameters.

Table 33. Directory of subsystem parameters and DSNHDECP values

Parameter	Macro	Panel	Update Online
ABEXP	DSN6SPRM	DSNTIPO	Yes
ABIND	DSN6SPRM	DSNTIPO	Yes
AGCCSID	DSNHDECP	DSNTIPF	—
ALCUNIT	DSN6ARVP	DSNTIPA	Yes
ALL/dbname	DSN6SPRM	DSNTIPS	—
AMCCSID	DSNHDECP	DSNTIPF	—
APPENSCH	DSNHDECP	DSNTIPF	—
ARCPFX1	DSN6ARVP	DSNTIPH	Yes
ARCPFX2	DSN6ARVP	DSNTIPH	Yes
ARCRETN	DSN6ARVP	DSNTIPA	Yes
ARCWRTC	DSN6ARVP	DSNTIPA	Yes
ARCWTOR	DSN6ARVP	DSNTIPA	Yes
ARC2FRST	DSN6LOGP	DSNTIPO	Yes
ASCCSID	DSNHDECP	DSNTIPF	—
ASSIST	DSN6GRP	DSNTIPK	No
AUDITST	DSN6SYSP	DSNTIPN	No
AUTH	DSN6SPRM	DSNTIPP	No
AUTHCACH	DSN6SPRM	DSNTIPP	Yes
BACKODUR	DSN6SYSP	DSNTIPL	No
BINDNV	DSN6SPRM	DSNTIPP	Yes
BLKSIZE	DSN6ARVP	DSNTIPA	Yes
BMPTOUT	DSN6SPRM	DSNTIPI	Yes
CACHEDYN	DSN6SPRM	DSNTIP4	No
CACHEPAC	DSN6SPRM	DSNTIPP	No
CACHERAC	DSN6SPRM	DSNTIPP	No
CATALOG	DSN6ARVP	DSNTIPA	Yes
"	DSN6SPRM	DSNTIPA2	—
CDSSRDEF	DSN6SPRM	DSNTIP4	Yes
CHARSET	DSNHDECP	DSNTIPF	—
CHGDC	DSN6SPRM	DSNTIPO	No

Table 33. Directory of subsystem parameters and DSNHDECP values (continued)

Parameter	Macro	Panel	Update Online
CHKFREQ	DSN6SYSP	DSNTIPL	Yes
CMTSTAT	DSN6FAC	DSNTIPR	No
COMPACT	DSN6ARVP	DSNTIPA	Yes
COMPAT	DSNHDECP	—	—
CONDBAT	DSN6SYSP	DSNTIPE	Yes
CONTSTOR	DSN6SPRM	DSNTIPE	Yes
COORDNTR	DSN6GRP	DSNTIPK	No
CTHREAD	DSN6SYSP	DSNTIPE	Yes
DBACRVW	DSN6SPRM	DSNTIPP	Yes
DBPROTCL	DSN6SYSP	DSNTIP5	Yes
DATE	DSNHDECP	DSNTIP4	—
DATELEN	DSNHDECP	DSNTIP4	—
DDF	DSN6FAC	DSNTIPR	No
DEALLCT	DSN6LOGP	DSNTIPA	Yes
DECARTH	DSNHDECP	DSNTIPF	—
DECDIV3	DSN6SPRM	DSNTIPF	—
DECIMAL	DSNHDECP	DSNTIPF	—
DEFLANG	DSNHDECP	DSNTIPF	—
DEFLTID	DSN6SPRM	DSNTIPP	No
DELIM	DSNHDECP	DSNTIPF	—
DESCSTAT	DSN6SPRM	DSNTIPF	Yes
DLDFREQ	DSN6SYSP	DSNTIPL	Yes
DLITOUT	DSN6SPRM	DSNTIPI	Yes
DSHARE	DSN6GRP	DSNTIPA1	No
DSMAX	DSN6SPRM	DSNTIPC	Yes
DSQLDELI	DSNHDECP	DSNTIPF	—
DSSTIME	DSN6SYSP	DSNTIPN	Yes
DYNRULES	DSNHDECP	DSNTIPF	—
EDMBFIT	DSN6SPRM	DSNTIP4	—
EDMDSMAX	DSN6SPRM	DSNTIPC	No
EDMDSPAC	DSN6SPRM	DSNTIPC	Yes
EDMPOOL	DSN6SPRM	DSNTIPC	Yes
EDPROP	DSN6SPRM	DSNTIPO	No
ENSCHHEME	DSNHDECP	DSNTIPF	—
EVALUNC	DSN6SPRM	DSNTIP4	Yes
EXTRAREQ	DSN6SYSP	DSNTIP5	No
EXTRASRV	DSN6SYSP	DSNTIP5	No
EXTSEC	DSN6SYSP	DSNTIPR	No
GCCSID	DSNHDECP	DSNTIPF	—
GRPNAME	DSN6GRP	DSNTIPK	No
HOPAUTH	DSN6SPRM	DSNTIP5	No
IDBACK	DSN6SYSP	DSNTIPE	Yes
IDFORE	DSN6SYSP	DSNTIPE	Yes
IDTHTOIN	DSN6FAC	DSNTIPR	No
IDXBPOOL	DSN6SYSP	DSNTIP1	Yes
IMMEDWRI	DSN6GRP	DSNTIP4	No
IRLMAUT	DSN6SPRM	DSNTIPI	No
IRLMPRC	DSN6SPRM	DSNTIPI	No
IRLMRWT	DSN6SPRM	DSNTIPI	No

Table 33. Directory of subsystem parameters and DSNHDECP values (continued)

Parameter	Macro	Panel	Update Online
IRLMSID	DSN6SPRM	DSNTIPI	No
IRLMSWT	DSN6SPRM	DSNTIPI	Yes
LBACKOUT	DSN6SYSP	DSNTIPL	No
LC_CTYPE	DSNHDECP	DSNTIPF	—
LEMAX	DSN6SPRM	DSNTIP7	No
LOBVALA	DSN6SYSP	DSNTIP7	No
LOBVALS	DSN6SYSP	DSNTIP7	No
LOGAPSTG	DSN6SYSP	DSNTIPL	No
MAXARCH	DSN6LOGP	DSNTIPA	No
MAXDBAT	DSN6SYSP	DSNTIPE	Yes
MAXKEEPD	DSN6SPRM	DSNTIPE	No
MAXRBLK	DSN6SPRM	DSNTIPC	Yes
MAXRTU	DSN6LOGP	DSNTIPA	Yes
MAXTYPE1	DSN6FAC	DSNTIPR	No
MCCSID	DSNHDECP	DSNTIPF	—
MEMBNAME	DSN6GRP	DSNTIPK	No
MINSTOR	DSN6SPRM	DSNTIPE	Yes
MIXED	DSNHDECP	DSNTIPF	—
MON	DSN6SYSP	DSNTIPN	No
MONSIZE	DSN6SYSP	DSNTIPN	No
NPGTHRSH	DSN6SPRM	—	—
NUMLKTS	DSN6SPRM	DSNTIPJ	Yes
NUMLKUS	DSN6SPRM	DSNTIPJ	Yes
OJPERFEH	DSN6SPRM	—	No
OPTHINTS	DSN6SPRM	DSNTIP4	Yes
OPTOPSE	DSN6SPRM	—	No
OUTBUFF	DSN6LOGP	DSNTIPL	No
PARAMDEG	DSN6SPRM	DSNTIP4	—
PARTKEYU	DSN6SPRM	DSNTIP4	—
PCLOSEN	DSN6SYSP	DSNTIPL	Yes
PCLOSET	DSN6SYSP	DSNTIPL	Yes
POOLINAC	DSN6FAC	DSNTIP5	No
PRIQTY	DSN6ARVP	DSNTIPA	Yes
PROTECT	DSN6ARVP	DSNTIPP	Yes
PTASKROL	DSN6SYSP	—	Yes
QUIESCE	DSN6ARVP	DSNTIPA	Yes
RECALL	DSN6SPRM	DSNTIPO	No
RECALLD	DSN6SPRM	DSNTIPO	Yes
RELCURHL	DSN6SPRM	DSNTIP4	Yes
RESTART/DEFER	DSN6SPRM	DSNTIPS	—
RESYNC	DSN6FAC	DSNTIPR	No
RETLWAIT	DSN6SPRM	DSNTIPI	Yes
RETVLCFK	DSN6SPRM	DSNTIP4	Yes
RGFCOLID	DSN6SPRM	DSNTIPZ	No
RGFDBNAM	DSN6SPRM	DSNTIPZ	No
RGFDEDPL	DSN6SPRM	DSNTIPZ	No
RGFDEFLT	DSN6SPRM	DSNTIPZ	No
RGFESCP	DSN6SPRM	DSNTIPZ	No
RGFFULLQ	DSN6SPRM	DSNTIPZ	No

Table 33. Directory of subsystem parameters and DSNHDECP values (continued)

Parameter	Macro	Panel	Update Online
RGFINSTL	DSN6SPRM	DSNTIPZ	No
RGFNMORT	DSN6SPRM	DSNTIPZ	No
RGFNMPRT	DSN6SPRM	DSNTIPZ	No
RLF	DSN6SYSP	DSNTIPO	No
RLFAUTH	DSN6SYSP	DSNTIPP	Yes
RLFERR	DSN6SYSP	DSNTIPO	Yes
RLFERRD	DSN6FAC	DSNTIPR	Yes
RLFTBL	DSN6SYSP	DSNTIPO	Yes
ROUTCDE	DSN6SYSP	DSNTIPO	No
RRULOCK	DSN6SPRM	DSNTIPI	Yes
SCCSID	DSNHDECP	DSNTIPF	—
SECQTY	DSN6ARVP	DSNTIPA	Yes
SEQCACH	DSN6SPRM	DSNTIPE	Yes
SEQPRES	DSN6SPRM	DSNTIPE	Yes
SITETYP	DSN6SPRM	DSNTIPO	No
SMFACCT	DSN6SYSP	DSNTIPN	No
SMFSTAT	DSN6SYSP	DSNTIPN	No
SMSDCFL	DSN6SPRM	—	—
SMSDCIX	DSN6SPRM	—	—
SPRMLTD	DSN6SPRC	—	—
SQLDELI	DSNHDECP	DSNTIPF	—
SRTPOOL	DSN6SPRM	DSNTIPC	No
SSID	DSNHDECP	DSNTIPM	—
STARJOIN	DSN6SPRM	—	No
STATHIST	DSN6SPRM	DSNTIPO	No
STATIME	DSN6SYSP	DSNTIPN	Yes
STATROLL	DSN6SPRM	DSNTIPO	Yes
STATSINT	DSN6SPRM	DSNTIPO	Yes
STDSQL	DSNHDECP	DSNTIP4	—
STORMXAB	DSN6SYSP	DSNTIPX	Yes
STORPROC	DSN6SYSP	DSNTIPX	No
STORTIME	DSN6SYSP	DSNTIPX	Yes
SUPERRS	DSN6SPRM	DSNTIPM	Yes
SYNCVAL	DSN6SYSP	DSNTIPN	Yes
SYSADM	DSN6SPRM	DSNTIPP	No
SYSADM2	DSN6SPRM	DSNTIPP	No
SYSOPR1	DSN6SPRM	DSNTIPP	No
SYSOPR2	DSN6SPRM	DSNTIPP	No
TBSBPOOL	DSN6SYSP	DSNTIP1	Yes
TCPALVER	DSN6FAC	DSNTIP5	No
TCPKPALV	DSN6FAC	DSNTIP5	No
TIME	DSNHDECP	DSNTIP4	—
TIMELEN	DSNHDECP	DSNTIP4	—
TRACSTR	DSN6SYSP	DSNTIPN	No
TRACTBL	DSN6SYSP	DSNTIPN	No
TRKRSITE	DSN6SPRM	DSNTIPO	No
TSTAMP	DSN6ARVP	DSNTIPH	Yes
TWOACTV	DSN6LOGP	DSNTIPH	No
TWOARCH	DSN6LOGP	DSNTIPH	No

Table 33. Directory of subsystem parameters and DSNHDECP values (continued)

Parameter	Macro	Panel	Update Online
TWOBSDS	DSN6LOGP	—	No
UGCCSID	DSNHDECP	DSNTIPF	—
UMCCSID	DSNHDECP	DSNTIPF	—
UNIT	DSN6ARVP	DSNTIPA	Yes
UNIT2	DSN6ARVP	DSNTIPA	Yes
URCHKTH	DSN6SYSP	DSNTIPL	Yes
URLGWTH	DSN6SYSP	DSNTIPL	Yes
USCCSID	DSNHDECP	DSNTIPF	—
UTIMOUT	DSN6SPRM	DSNTIPI	Yes
WLMENV	DSN6SYSP	DSNTIPX	Yes
XLKUPDLT	DSN6SPRM	DSNTIPI	No

Note 1: Serviceability parameter

Note 2: SPRMLTD is introduced in macro member DSN6SPRC of the *prefix.SDSNMACS* data set. The default value is 10. The SPRMLTD value multiplied by 32K is used by DB2 to determine a size threshold for compression of the in-memory only copy of the Database Descriptor (DBD) for the new TEMP database when the database is no longer in use. This parameter has no effect on the actual size of the DB2 Directory copy of the DBD on DASD. You can use the new declared temporary tables without editing or changing the SPRMLTD value. You must reassemble and re-link the DB2 initialization parameter module, DSNZPARM, for each DB2 subsystem or Data Sharing member that will have the new TEMP database.

Appendix B. How to use the DB2 library

Titles of books in the library begin with DB2 Universal Database for OS/390 and z/OS Version 7. However, references from one book in the library to another are shortened and do not include the product name, version, and release. Instead, they point directly to the section that holds the information. For a complete list of books in the library, and the sections in each book, see the bibliography at the back of this book.

The most rewarding task associated with a database management system is asking questions of it and getting answers, the task called *end use*. Other tasks are also necessary—defining the parameters of the system, putting the data in place, and so on. The tasks that are associated with DB2 are grouped into the following major categories (but supplemental information relating to all of the following tasks for new releases of DB2 can be found in *DB2 Release Planning Guide*):

Installation: If you are involved with DB2 only to install the system, *DB2 Installation Guide* might be all you need.

If you will be using data sharing capabilities you also need *DB2 Data Sharing: Planning and Administration*, which describes installation considerations for data sharing.

End use: End users issue SQL statements to retrieve data. They can also insert, update, or delete data, with SQL statements. They might need an introduction to SQL, detailed instructions for using SPUFI, and an alphabetized reference to the types of SQL statements. This information is found in *An Introduction to DB2 for OS/390*, *DB2 Application Programming and SQL Guide*, and *DB2 SQL Reference*.

End users can also issue SQL statements through the Query Management Facility (QMF™) or some other program, and the library for that licensed program might provide all the instruction or reference material they need. For a list of the titles in the QMF library, see the bibliography at the end of this book.

Application Programming: Some users access DB2 without knowing it, using programs that contain SQL statements. DB2 application programmers write those programs. Because they write SQL statements, they need *DB2 Application Programming and SQL Guide*, *DB2 SQL Reference*, and *DB2 ODBC Guide and Reference*, just as end users do.

Application programmers also need instructions on many other topics:

- How to transfer data between DB2 and a host program—written in COBOL, C, or Fortran, for example
- How to prepare to compile a program that embeds SQL statements
- How to process data from two systems simultaneously, say DB2 and IMS™ or DB2 and CICS
- How to write distributed applications across operating systems
- How to write applications that use DB2 ODBC to access DB2 servers
- How to write applications that use Open Database Connectivity (ODBC) to access DB2 servers
- How to write applications in the Java programming language to access DB2 servers

The material needed for writing a host program containing SQL is in *DB2 Application Programming and SQL Guide* and in *DB2 Application Programming Guide and Reference for Java*. The material needed for writing applications that use DB2 ODBC or ODBC to access DB2 servers is in *DB2 ODBC Guide and Reference*. For handling errors, see *DB2 Messages and Codes*.

Information about writing applications across operating systems can be found in *Distributed Relational Database Architecture: Application Programming Guide*.

System and Database Administration: *Administration* covers almost everything else. *DB2 Administration Guide* divides those tasks among the following sections:

- Part 2 (Volume 1) of *DB2 Administration Guide* discusses the decisions that must be made when designing a database and tells how to bring the design into being by creating DB2 objects, loading data, and adjusting to changes.
- Part 3 (Volume 1) of *DB2 Administration Guide* describes ways of controlling access to the DB2 system and to data within DB2, to audit aspects of DB2 usage, and to answer other security and auditing concerns.
- Part 4 (Volume 1) of *DB2 Administration Guide* describes the steps in normal day-to-day operation and discusses the steps one should take to prepare for recovery in the event of some failure.
- Part 5 (Volume 2) of *DB2 Administration Guide* explains how to monitor the performance of the DB2 system and its parts. It also lists things that can be done to make some parts run faster.

In addition, the appendixes in *DB2 Administration Guide* contain valuable information on DB2 sample tables, National Language Support (NLS), writing exit routines, interpreting DB2 trace output, and character conversion for distributed data.

If you are involved with DB2 only to design the database, or plan operational procedures, you need *An Introduction to DB2 for OS/390* and *DB2 Administration Guide*. If you also want to carry out your own plans by creating DB2 objects, granting privileges, running utility jobs, and so on, you also need:

- *DB2 SQL Reference*, which describes the SQL statements you use to create, alter, and drop objects and grant and revoke privileges
- *DB2 Utility Guide and Reference*, which explains how to run utilities
- *DB2 Command Reference*, which explains how to run commands

If you will be using data sharing, you need *DB2 Data Sharing: Planning and Administration*, which describes how to plan for and implement data sharing.

Additional information about system and database administration can be found in *DB2 Messages and Codes*, which lists messages and codes issued by DB2, with explanations and suggested responses.

Diagnosis: Diagnosticians detect and describe errors in the DB2 program. They might also recommend or apply a remedy. The documentation for this task is in *DB2 Diagnosis Guide and Reference* and *DB2 Messages and Codes*.

Appendix C. How to obtain DB2 information

This section provides information that you can use to find valuable information about the DB2 product.

DB2 on the Web

Stay current with the latest information about DB2. View the DB2 home page on the Web. News items keep you informed about the latest enhancements to the product. Product announcements, press releases, fact sheets, and technical articles help you plan your database management strategy.

You can view and search DB2 publications on the Web, or you can download and print many of the most current DB2 books. Follow links to other Web sites with more information about DB2 family and OS/390 solutions. Access DB2 on the Web at the following address:

www.ibm.com/software/db2os390

DB2 publications

The publications for DB2 for OS/390 and z/OS are available in softcopy format and hardcopy. IBM provides mid-version updates in softcopy on the Web and on CD-ROM.

BookManager format

You can use online books on CD-ROM to read, search across books, print portions of the text, and make notes in these BookManager books. Using the IBM Softcopy Reader, appropriate IBM Library Readers, or the BookManager Read product, you can view these books in the OS/390, VM, and Windows environments. You can also view and search many of the DB2 BookManager books on the Web.

PDF format

Many of the DB2 books are available in Portable Document Format (PDF) for viewing or printing from CD-ROM or the Web. Download the PDF books to your intranet for distribution throughout your enterprise.

CD-ROMs and DVD

Books for Version 7 of DB2 Universal Database Server for OS/390 and z/OS are available on a CD-ROM that is included with your shipment of DB2 for OS/390:

- *DB2 UDB Server for OS/390 Version 7 Library Collection*, LK3T-6999, in English

The CD-ROM contains the collection of books for the DB2 server in BookManager and PDF formats. Periodically, IBM refreshes the books on subsequent editions of this CD-ROM.

The books for Version 7 of DB2 UDB Server for OS/390 and z/OS are also available on the following CD-ROM and DVD collection kits, which contain online books for many IBM products:

- *z/OS Software Collection*, SK3T-4270, in English
- *z/OS and Software Products DVD Collection*, SK3T-4271-00, in English
- *Online Library Omnibus Edition OS/390 Collection*, SK2T-6700, in English

DB2 education

IBM Education and Training offers a wide variety of classroom courses to help you quickly and efficiently gain DB2 expertise. IBM schedules classes in cities all over the world. You can find class information, by country, at the IBM Learning Services Web site:

www.ibm.com/services/learning/

For more information, including the current local schedule, please contact your IBM representative.

IBM also offers classes at your location, at a time that suits your needs. IBM can customize courses to meet your exact requirements. The *All-in-One Education and Training Catalog* describes the DB2 curriculum in the United States. You can inquire about or enroll in these courses by calling 1-800-IBM-TEACH (1-800-426-8322).

How to order the DB2 library

You can order DB2 publications and CD-ROMs through your IBM representative or the IBM branch office that serves your locality. If your location is within the United States or Canada, you can place your order by calling one of the toll-free numbers:

- In the U.S., call 1-800-879-2755.
- In Canada, call 1-800-565-1234.

To order additional copies of licensed publications, specify the SOFTWARE option. To order additional publications or CD-ROMs, specify the PUBLICATIONS option. Be prepared to give your customer number, the product number, and either the feature codes or order numbers that you want.

You can also order books from the IBM Publication Center on the Web:
www.elink.ibm.link.ibm.com

Subscription through the Publication Notification System (PNS)

IBM has replaced the System Library Subscription Service (SLSS) with an up-to-date notification application, the Publication Notification System (PNS). IBM migrated all active SLSS subscriptions to the new PNS application, which you can access from the Web.

PNS users receive electronic notifications of updated publications in their profiles. You have the option of ordering the updates by using the publications direct ordering application or any other IBM publication ordering channel. Unlike SLSS, the PNS application does not send automatic shipments of publications. You will receive updated publications and a bill for them if you respond to the electronic notification. To access the PNS application on the World Wide Web, enter the following address on your Web browser command line:

www.ibm.com/shop/publications/pns/elink.ibm.link.ibm.com

Appendix D. Summary of changes to DB2 for OS/390 and z/OS Version 7

DB2 for OS/390 and z/OS Version 7 delivers an enhanced relational database server solution for OS/390. This release focuses on greater ease and flexibility in managing your data, better reliability, scalability, and availability, and better integration with the DB2 family.

In Version 7, some utility functions are available as optional products; you must separately order and purchase a license to such utilities. Discussion of utility functions in this publication is not intended to otherwise imply that you have a license to them. See *DB2 Utility Guide and Reference* for more information about utilities products.

Enhancements for managing data

Version 7 delivers the following enhancements for managing data:

- DB2 now collects a comprehensive statistics history that:
 - Lets you track changes to the physical design of DB2 objects
 - Lets DB2 predict future space requirements for table spaces and indexes more accurately and run utilities to improve performance
- Database administrators can now manage DB2 objects more easily and no longer must maintain their utility jobs (even when new objects are added) by using enhancements that let them:
 - Dynamically create object lists from a pattern-matching expression
 - Dynamically allocate the data sets that are required to process those objects
- More flexible DBADM authority lets database administrators create views for other users.
- Enhancements to management of constraints let you specify a constraint at the time you create primary or unique keys. A new restriction on the DROP INDEX statement requires that you drop the primary key, unique key, or referential constraint before you drop the index that enforces a constraint.

Enhancements for reliability, scalability, and availability

Version 7 delivers the following enhancements for the reliability, scalability, and availability of your e-business:

- The DB2 Utilities Suite provides utilities for all of your data management tasks that are associated with the DB2 catalog.
- The new UNLOAD utility lets you unload data from a table space or an image copy data set. In most cases, the UNLOAD utility is faster than the DSNTIAUL sample program, especially when you activate partition parallelism for a large partitioned table space. UNLOAD is also easier to use than REORG UNLOAD EXTERNAL.
- The new COPYTOCOPY utility lets you make additional image copies from a primary image copy and registers those copies in the DB2 catalog. COPYTOCOPY leaves the target object in read/write access mode (UTRW), which allows Structured Query Language (SQL) statements and some utilities to run concurrently with the same target objects.

- Parallel LOAD with multiple inputs lets you easily load large amounts of data into partitioned table spaces for use in data warehouse applications or business intelligence applications. Parallel LOAD with multiple inputs runs in a single step, rather than in different jobs.
- A faster online REORG is achieved through the following enhancements:
 - Online REORG no longer renames data sets, which greatly reduces the time that data is unavailable during the SWITCH phase.
 - Additional parallel processing improves the elapsed time of the BUILD2 phase of REORG SHRLEVEL(CHANGE) or SHRLEVEL(REFERENCE).
- More concurrency with online LOAD RESUME is achieved by letting you give users read and write access to the data during LOAD processing so that you can load data concurrently with user transactions.
- More efficient processing for SQL queries:
 - More transformations of subqueries into a join for some UPDATE and DELETE statements
 - Fewer sort operations for queries that have an ORDER BY clause and WHERE clauses with predicates of the form *COL=constant*
 - More parallelism for IN-list index access, which can improve performance for queries involving IN-list index access
- The ability to change system parameters without stopping DB2 supports online transaction processing and e-business without interruption.
- Improved availability of user objects that are associated with failed or canceled transactions:
 - You can cancel a thread without performing rollback processing.
 - Some restrictions imposed by the restart function have been removed.
 - A NOBACKOUT option has been added to the CANCEL THREAD command.
- Improved availability of the DB2 subsystem when a log-read failure occurs: DB2 now provides a timely warning about failed log-read requests and the ability to retry the log read so that you can take corrective action and avoid a DB2 outage.
- Improved availability in the data sharing environment:
 - Group attachment enhancements let DB2 applications generically attach to a DB2 data sharing group.
 - A new LIGHT option of the START DB2 command lets you restart a DB2 data sharing member with a minimal storage footprint, and then terminate normally after DB2 frees the retained locks that it can.
 - You can let changes in structure size persist when you rebuild or reallocate a structure.
- Additional data sharing enhancements include:
 - Notification of incomplete units of recovery
 - Use of a new OS/390 and z/OS function to improve failure recovery of group buffer pools
- An additional enhancement for e-business provides improved performance with preformatting for INSERT operations.

Easier development and integration of e-business applications

Version 7 provides the following enhancements, which let you more easily develop and integrate applications that access data from various DB2 operating systems and distributed environments:

- DB2 XML Extender for OS/390 and z/OS, a new member of the DB2 Extender family, lets you store, retrieve, and search XML documents in a DB2 database.

- Improved support for UNION and UNION ALL operators in a view definition, a nested table expression, or a subquery predicate, improves DB2 family compatibility and is consistent with SQL99 standards.
- More flexibility with SQL gives you greater compatibility with DB2 on other operating systems:
 - Scrollable cursors let you move forward, backward, or randomly through a result table or a result set. You can use scrollable cursors in any DB2 applications that do not use DB2 private protocol access.
 - A search condition in the WHERE clause can include a subquery in which the base object of both the subquery and the searched UPDATE or DELETE statement are the same.
 - A new SQL clause, FETCH FIRST *n* ROWS, improves performance of applications in a distributed environment.
 - Fast implicit close in which the DB2 server, during a distributed query, automatically closes the cursor when the application attempts to fetch beyond the last row.
 - Support for options USER and USING in a new authorization clause for CONNECT statements lets you easily port applications that are developed on the workstation to DB2 for OS/390 and z/OS. These options also let applications that run under WebSphere to reuse DB2 connections for different users and to enable DB2 for OS/390 and z/OS to check passwords.
 - For positioned updates, you can specify the FOR UPDATE clause of the cursor SELECT statement without a list of columns. As a result, all updatable columns of the table or view that is identified in the first FROM clause of the fullselect are included.
 - A new option of the SELECT statement, ORDER BY *expression*, lets you specify operators as the sort key for the result table of the SELECT statement.
 - New datetime ISO functions return the day of the week with Monday as day 1 and every week with seven days.
- Enhancements to Open Database Connectivity (ODBC) provide partial ODBC 3.0 support, including many new application programming interfaces (APIs), which increase application portability and alignment with industry standards.
- Enhancements to the LOAD utility let you load the output of an SQL SELECT statement directly into a table.
- A new component called Precompiler Services lets compiler writers modify their compilers to invoke Precompiler Services and produce an *SQL statement coprocessor*. An SQL statement coprocessor performs the same functions as the DB2 precompiler, but it performs those functions at compile time. If your compiler has an SQL statement coprocessor, you can eliminate the precompile step in your batch program preparation jobs for COBOL and PL/I programs.
- Support for Unicode-encoded data lets you easily store multilingual data within the same table or on the same DB2 subsystem. The Unicode encoding scheme represents the code points of many different geographies and languages.

#

Improved connectivity

Version 7 offers improved connectivity:

- Support for COMMIT and ROLLBACK in stored procedures lets you commit or roll back an entire unit of work, including uncommitted changes that are made from the calling application before the stored procedure call is made.

- Support for Windows Kerberos security lets you more easily manage workstation clients who seek access to data and services from heterogeneous environments.
- Global transaction support for distributed applications lets independent DB2 agents participate in a global transaction that is coordinated by an XA-compliant transaction manager on a workstation or a gateway server (Microsoft Transaction Server or Encina, for example).
- Support for a DB2 Connect Version 7 enhancement lets remote workstation clients quickly determine the amount of time that DB2 takes to process a request (the server elapsed time).
- Additional enhancements include:
 - Support for connection pooling and transaction pooling for IBM DB2 Connect
 - Support for DB2 Call Level Interface (DB2 CLI) bookmarks on DB2 UDB for UNIX, Windows, OS/2

Features of DB2 for OS/390 and z/OS

Version 7 of DB2 UDB Server for OS/390 and z/OS offers several features that help you integrate, analyze, summarize, and share data across your enterprise:

- DB2 Warehouse Manager feature. The DB2 Warehouse Manager feature brings together the tools to build, manage, govern, and access DB2 for OS/390-based data warehouses. The DB2 Warehouse Manager feature uses proven technologies with new enhancements that are not available in previous releases, including:
 - DB2 Warehouse Center, which includes:
 - DB2 Universal Database Version 7 Release 1 Enterprise Edition
 - Warehouse agents for UNIX, Windows, and OS/390
 - Information Catalog
 - QMF Version 7
 - QMF High Performance Option
 - QMF for Windows
- DB2 Management Clients Package. The elements of the DB2 Management Clients Package are:
 - DB2 Control Center
 - DB2 Stored Procedure Builder
 - DB2 Installer
 - DB2 Visual Explain
 - DB2 Estimator
- Net Search Extender for in-memory text search for e-business applications
- Net.Data for secure Web applications

Migration considerations

Migration with full fallback protection is available when you have either DB2 for
 # OS/390 Version 5 or Version 6 installed. You should ensure that you are fully
 # operational on DB2 for OS/390 Version 5, or later, before migrating to DB2 for
 # OS/390 and z/OS Version 7.

To learn about all of the migration considerations from Version 5 to Version 7, read the *DB2 Release Planning Guide* for Version 6 and Version 7; to learn about content information, also read appendixes A through F in both books.

Notices

This information was developed for products and services offered in the U.S.A. IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing
IBM Corporation
North Castle Drive
Armonk, NY 10504-1785
U.S.A.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

IBM World Trade Asia Corporation
Licensing
2-31 Roppongi 3-chome, Minato-ku
Tokyo 106-0032, Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law:

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs

and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation
J74/G4
555 Bailey Avenue
P.O. Box 49023
San Jose, CA 95161-9023
U.S.A.

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this information and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement, or any equivalent agreement between us.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs.

Programming interface information

This book is intended to help you to use commands of IBM DATABASE 2 Universal Database Server for OS/390 and z/OS (DB2 for OS/390 and z/OS) and related subsystems. This book primarily documents General-use Programming Interface and Associated Guidance Information provided by DB2.

General-use programming interfaces allow the customer to write programs that obtain the services of DB2.

However, this book also documents Product-sensitive Programming Interface and Associated Guidance Information.

Product-sensitive programming interfaces allow the customer installation to perform tasks such as diagnosing, modifying, monitoring, repairing, tailoring, or tuning of this IBM software product. Use of such interfaces creates dependencies on the detailed design or implementation of the IBM software product. Product-sensitive programming interfaces should be used only for these specialized purposes. Because of their dependencies on detailed design and implementation, it is to be expected that programs written to such interfaces may need to be changed to run with new product releases or versions, or as a result of service.

Product-sensitive Programming Interface and Associated Guidance Information is identified where it occurs, by the following marking:

┌ **Product-sensitive Programming Interface** _____

Product-sensitive Programming Interface and Associated Guidance Information ...

└ **End of Product-sensitive Programming Interface** _____

Trademarks

The following terms are trademarks of the International Business Machines Corporation in the United States, or other countries, or both:

AD/Cycle	Enterprise System/9000
AIX	IBM
APL2	IMS
AS/400	IMS/ESA
BookManager	Language Environment
CICS	MVS/DFP
CICS/ESA	MVS/ESA
CICS/MVS	MVS/XA
CICS OS/2	Net.Data
COBOL/370	OS/2
C/370	OS/390
DATABASE 2	OS/400
DataPropagator	Parallel Sysplex
DB2	PR/SM
DB2 Connect	QMF
DB2 Universal Database	RACF
DFSMSdfp	RAMAC
DFSMSdss	SAA
DFSMSHsm	SecureWay
DFSMS/MVS	SQL/DS
DFSORT	System/370
Distributed Relational Database Architecture	System/390
DRDA	System Object Model
Enterprise Storage Server	VTAM
Enterprise System/3090	

Tivoli and NetView are trademarks of Tivoli Systems, Inc. in the United States, other countries, or both.

Java and all Java-based trademarks and logos are trademarks or registered trademarks of Sun Microsystems, Inc. in the United States and/or other countries.

Microsoft™, Windows™, Windows NT, and the Windows logo are trademarks or registered trademarks of Microsoft, Inc. in the United States and/or other countries.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Other company, product, and service names may be trademarks or service marks of others.

Glossary

The following terms and abbreviations are defined as they are used in the DB2 library.

A

abend. Abnormal end of task.

abend reason code. A 4-byte hexadecimal code that uniquely identifies a problem with DB2. A complete list of DB2 abend reason codes and their explanations is contained in *DB2 Messages and Codes*.

access method services. The facility that is used to define and reproduce VSAM key-sequenced data sets.

access path. The path that is used to locate data that is specified in SQL statements. An access path can be indexed or sequential.

active log. The portion of the DB2 log to which log records are written as they are generated. The active log always contains the most recent log records, whereas the archive log holds those records that are older and no longer fit on the active log.

active member state. A state of a member of a data sharing group. An active member is identified with a group by XCF, which associates the member with a particular task, address space, and MVS system. A member that is not active has either a failed member state or a quiesced member state.

address space. A range of virtual storage pages that is identified by a number (ASID) and a collection of segment and page tables that map the virtual pages to real pages of the computer's memory.

address space connection. The result of connecting an allied address space to DB2. Each address space that contains a task that is connected to DB2 has exactly one address space connection, even though more than one task control block (TCB) can be present. See also *allied address space* and *task control block*.

agent. As used in DB2, the structure that associates all processes that are involved in a DB2 unit of work. An *allied agent* is generally synonymous with an *allied thread*. *System agents* are units of work that process independently of the allied agent, such as prefetch processing, deferred writes, and service tasks.

alias. An alternative name that can be used in SQL statements to refer to a table or view in the same or a remote DB2 subsystem.

allied address space. An area of storage that is external to DB2 and that is connected to DB2. An allied address space is capable of requesting DB2 services.

allied thread. A thread that originates at the local DB2 subsystem and that can access data at a remote DB2 subsystem.

ambiguous cursor. A database cursor that is not defined with the FOR FETCH ONLY clause or the FOR UPDATE OF clause, is not defined on a read-only result table, is not the target of a WHERE CURRENT clause on an SQL UPDATE or DELETE statement, and is in a plan or package that contains either PREPARE or EXECUTE IMMEDIATE SQL statements.

American National Standards Institute (ANSI). An organization consisting of producers, consumers, and general interest groups, that establishes the procedures by which accredited organizations create and maintain voluntary industry standards in the United States.

ANSI. American National Standards Institute.

API. Application programming interface.

APPL. A VTAM® network definition statement that is used to define DB2 to VTAM as an application program that uses SNA LU 6.2 protocols.

application. A program or set of programs that performs a task; for example, a payroll application.

application plan. The control structure that is produced during the bind process. DB2 uses the application plan to process SQL statements that it encounters during statement execution.

application process. The unit to which resources and locks are allocated. An application process involves the execution of one or more programs.

application programming interface (API). A functional interface that is supplied by the operating system or by a separately orderable licensed program that allows an application program that is written in a high-level language to use specific data or functions of the operating system or licensed program.

| **application server.** The target of a request from a
| remote application. In the DB2 environment, the
| application server function is provided by the distributed
| data facility and is used to access DB2 data from
| remote applications.

archive log. The portion of the DB2 log that contains log records that have been copied from the active log.

| **ASCII.** An encoding scheme that is used to represent
| strings in many environments, typically on PCs and
| workstations. Contrast with *EBCDIC* and *Unicode*.

attachment facility • cast function

attachment facility. An interface between DB2 and TSO, IMS, CICS, or batch address spaces. An attachment facility allows application programs to access DB2.

attribute. A characteristic of an entity. For example, in database design, the phone number of an employee is one of that employee's attributes.

authorization ID. A string that can be verified for connection to DB2 and to which a set of privileges is allowed. It can represent an individual, an organizational group, or a function, but DB2 does not determine this representation.

auxiliary index. An index on an auxiliary table in which each index entry refers to a LOB.

auxiliary table. A table that stores columns outside the table in which they are defined. Contrast with *base table*.

B

backward log recovery. The fourth and final phase of restart processing during which DB2 scans the log in a backward direction to apply UNDO log records for all aborted changes.

base table. (1) A table that is created by the SQL CREATE TABLE statement and that holds persistent data. Contrast with *result table* and *temporary table*.

(2) A table containing a LOB column definition. The actual LOB column data is not stored with the base table. The base table contains a row identifier for each row and an indicator column for each of its LOB columns. Contrast with *auxiliary table*.

basic sequential access method (BSAM). An access method for storing or retrieving data blocks in a continuous sequence, using either a sequential access or a direct access device.

binary integer. A basic data type that can be further classified as small integer or large integer.

binary large object (BLOB). A sequence of bytes where the size of the value ranges from 0 bytes to 2 GB-1. Such a string does not have an associated CCSID.

bind. The process by which the output from the SQL precompiler is converted to a usable control structure, often called an access plan, application plan, or package. During this process, access paths to the data are selected and some authorization checking is performed. The types of bind are:

automatic bind. (More correctly, *automatic rebind*) A process by which SQL statements are bound automatically (without a user issuing a BIND command) when an application process begins

execution and the bound application plan or package it requires is not valid.

dynamic bind. A process by which SQL statements are bound as they are entered.

incremental bind. A process by which SQL statements are bound during the execution of an application process, because they could not be bound during the bind process, and VALIDATE(RUN) was specified.

static bind. A process by which SQL statements are bound after they have been precompiled. All static SQL statements are prepared for execution at the same time.

BLOB. Binary large object.

BMP. Batch Message Processing (IMS).

bootstrap data set (BSDS). A VSAM data set that contains name and status information for DB2, as well as RBA range specifications, for all active and archive log data sets. It also contains passwords for the DB2 directory and catalog, and lists of conditional restart and checkpoint records.

BSAM. Basic sequential access method.

BSDS. Bootstrap data set.

buffer pool. Main storage that is reserved to satisfy the buffering requirements for one or more table spaces or indexes.

built-in function. A function that DB2 supplies. Contrast with *user-defined function*.

C

cache structure. A coupling facility structure that stores data that can be available to all members of a Sysplex. A DB2 data sharing group uses cache structures as group buffer pools.

CAF. Call attachment facility.

call attachment facility (CAF). A DB2 attachment facility for application programs that run in TSO or MVS batch. The CAF is an alternative to the DSN command processor and provides greater control over the execution environment.

cascade delete. The way in which DB2 enforces referential constraints when it deletes all descendent rows of a deleted parent row.

cast function. A function that is used to convert instances of a (source) data type into instances of a different (target) data type. In general, a cast function has the name of the target data type. It has one single argument whose type is the source data type; its return type is the target data type.

castout. The DB2 process of writing changed pages from a group buffer pool to DASD.

catalog. In DB2, a collection of tables that contains descriptions of objects such as tables, views, and indexes.

catalog table. Any table in the DB2 catalog.

CCSID. Coded character set identifier.

CDB. Communications database.

CFRM policy. A declaration by an MVS administrator regarding the allocation rules for a coupling facility structure.

character large object (CLOB). A sequence of bytes representing single-byte characters or a mixture of single- and double-byte characters where the size of the value can be up to 2 GB–1. In general, character large object values are used whenever a character string might exceed the limits of the VARCHAR type.

character set. A defined set of characters.

| **character string.** A sequence of bytes that represent
| bit data, single-byte characters, or a mixture of
| single-byte and multibyte characters.

check constraint. See *table check constraint*.

check integrity. The condition that exists when each row in a table conforms to the table check constraints that are defined on that table. Maintaining check integrity requires DB2 to enforce table check constraints on operations that add or change data.

check pending. A state of a table space or partition that prevents its use by some utilities and some SQL statements because of rows that violate referential constraints, table check constraints, or both.

checkpoint. A point at which DB2 records internal status information on the DB2 log; the recovery process uses this information if DB2 abnormally terminates.

CI. Control interval.

CICS. Represents (in this publication) one of the following products:

CICS Transaction Server for OS/390: Customer Information Control System Transaction Server for OS/390

CICS/ESA: Customer Information Control System/Enterprise Systems Architecture

CICS/MVS: Customer Information Control System/Multiple Virtual Storage

CICS attachment facility. A DB2 subcomponent that uses the MVS subsystem interface (SSI) and cross storage linkage to process requests from CICS to DB2 and to coordinate resource commitment.

CIDF. Control interval definition field.

claim. A notification to DB2 that an object is being accessed. Claims prevent drains from occurring until the claim is released, which usually occurs at a commit point. Contrast with *drain*.

claim class. A specific type of object access that can be one of the following:
Cursor stability (CS)
Repeatable read (RR)
Write

claim count. A count of the number of agents that are accessing an object.

clause. In SQL, a distinct part of a statement, such as a SELECT clause or a WHERE clause.

CLIST. Command list. A language for performing TSO tasks.

CLOB. Character large object.

clustering index. An index that determines how rows are physically ordered in a table space.

coded character set. A set of unambiguous rules that establish a character set and the one-to-one relationships between the characters of the set and their coded representations.

coded character set identifier (CCSID). A 16-bit number that uniquely identifies a coded representation of graphic characters. It designates an encoding scheme identifier and one or more pairs consisting of a character set identifier and an associated code page identifier.

cold start. A process by which DB2 restarts without processing any log records. Contrast with *warm start*.

collection. A group of packages that have the same qualifier.

column. The vertical component of a table. A column has a name and a particular data type (for example, character, decimal, or integer).

column function. An operation that derives its result by using values from one or more rows. Contrast with *scalar function*.

command. A DB2 operator command or a DSN subcommand. A command is distinct from an SQL statement.

command prefix. A one- to eight-character command identifier. The command prefix distinguishes the command as belonging to an application or subsystem rather than to MVS.

command recognition character (CRC) • current data

command recognition character (CRC). A character that permits an MVS console operator or an IMS subsystem user to route DB2 commands to specific DB2 subsystems.

command scope. The scope of command operation in a data sharing group. If a command has *member scope*, the command displays information only from the one member or affects only non-shared resources that are owned locally by that member. If a command has *group scope*, the command displays information from all members, affects non-shared resources that are owned locally by all members, displays information on sharable resources, or affects sharable resources.

commit. The operation that ends a unit of work by releasing locks so that the database changes that are made by that unit of work can be perceived by other processes.

commit point. A point in time when data is considered consistent.

committed phase. The second phase of the multisite update process that requests all participants to commit the effects of the logical unit of work.

communications database (CDB). A set of tables in the DB2 catalog that are used to establish conversations with remote database management systems.

compression dictionary. The dictionary that controls the process of compression and decompression. This dictionary is created from the data in the table space or table space partition.

concurrency. The shared use of resources by more than one application process at the same time.

conditional restart. A DB2 restart that is directed by a user-defined conditional restart control record (CRCR).

connection. In SNA, the existence of a communication path between two partner LUs that allows information to be exchanged (for example, two DB2 subsystems that are connected and communicating by way of a conversation).

connection ID. An identifier that is supplied by the attachment facility and that is associated with a specific address space connection.

consistency token. A timestamp that is used to generate the version identifier for an application. See also *version*.

constant. A language element that specifies an unchanging value. Constants are classified as string constants or numeric constants. Contrast with *variable*.

constraint. A rule that limits the values that can be inserted, deleted, or updated in a table. See *referential constraint*, *table check constraint*, and *uniqueness constraint*.

control interval (CI). A fixed-length area or direct access storage in which VSAM stores records and creates distributed free space. Also, in a key-sequenced data set or file, the set of records pointed to by an entry in the sequence-set index record. The control interval is the unit of information that VSAM transmits to or from direct access storage. A control interval always includes an integral number of physical records.

control interval definition field (CIDF). In VSAM, a field located in the 4 bytes at the end of each control interval; it describes the free space, if any, in the control interval.

conversation. Communication, which is based on LU 6.2 or Advanced Program-to-Program Communication (APPC), between an application and a remote transaction program over an SNA logical unit-to-logical unit (LU-LU) session that allows communication while processing a transaction.

coordinator. The system component that coordinates the commit or rollback of a unit of work that includes work that is done on one or more other systems.

correlation ID. An identifier that is associated with a specific thread. In TSO, it is either an authorization ID or the job name.

coupling facility. A special PR/SM™ LPAR logical partition that runs the coupling facility control program and provides high-speed caching, list processing, and locking functions in a Sysplex.

CRC. Command recognition character.

CRCR. Conditional restart control record. See also *conditional restart*.

created temporary table. A table that holds temporary data and is defined with the SQL statement CREATE GLOBAL TEMPORARY TABLE. Information about created temporary tables is stored in the DB2 catalog, so this kind of table is persistent and can be shared across application processes. Contrast with *declared temporary table*. See also *temporary table*.

cross-system coupling facility (XCF). A component of MVS that provides functions to support cooperation between authorized programs that run within a Sysplex.

CS. Cursor stability.

current data. Data within a host structure that is current with (identical to) the data within the base table.

current status rebuild. The second phase of restart processing during which the status of the subsystem is reconstructed from information on the log.

cursor. A named control structure that an application program uses to point to a row of interest within some set of rows, and to retrieve rows from the set, possibly making updates or deletions.

cursor stability (CS). The isolation level that provides maximum concurrency without the ability to read uncommitted data. With cursor stability, a unit of work holds locks only on its uncommitted changes and on the current row of each of its cursors.

cycle. A set of tables that can be ordered so that each table is a descendent of the one before it, and the first table is a descendent of the last table. A self-referencing table is a cycle with a single member.

D

DASD. Direct access storage device.

database. A collection of tables, or a collection of table spaces and index spaces.

database access thread. A thread that accesses data at the local subsystem on behalf of a remote subsystem.

database administrator (DBA). An individual who is responsible for designing, developing, operating, safeguarding, maintaining, and using a database.

database descriptor (DBD). An internal representation of a DB2 database definition, which reflects the data definition that is in the DB2 catalog. The objects that are defined in a database descriptor are table spaces, tables, indexes, index spaces, and relationships.

database management system (DBMS). A software system that controls the creation, organization, and modification of a database and the access to the data stored within it.

database request module (DBRM). A data set member that is created by the DB2 precompiler and that contains information about SQL statements. DBRMs are used in the bind process.

| **database server.** The target of a request from a local
| application or an intermediate database server. In the
| DB2 environment, the database server function is
| provided by the distributed data facility to access DB2
| data from local applications, or from a remote database
| server that acts as an intermediate database server.

DATABASE 2 Interactive (DB2I). The DB2 facility that provides for the execution of SQL statements, DB2 (operator) commands, programmer commands, and utility invocation.

current status rebuild • DB2 command

data currency. The state in which data that is retrieved into a host variable in your program is a copy of data in the base table.

data definition name (ddname). The name of a data definition (DD) statement that corresponds to a data control block containing the same name.

Data Language/I (DL/I). The IMS data manipulation language; a common high-level interface between a user application and IMS.

data partition. A VSAM data set that is contained within a partitioned table space.

data sharing. The ability of two or more DB2 subsystems to directly access and change a single set of data.

data sharing group. A collection of one or more DB2 subsystems that directly access and change the same data while maintaining data integrity.

data sharing member. A DB2 subsystem that is assigned by XCF services to a data sharing group.

data space. A range of up to 2 GB of contiguous virtual storage addresses that a program can directly manipulate. Unlike an address space, a data space can hold only data; it does not contain common areas, system data, or programs.

data type. An attribute of columns, literals, host variables, special registers, and the results of functions and expressions.

date. A three-part value that designates a day, month, and year.

date duration. A decimal integer that represents a number of years, months, and days.

DBA. Database administrator.

DBCLOB. Double-byte character large object.

DBCS. Double-byte character set.

DBD. Database descriptor.

DBID. Database identifier.

DBMS. Database management system.

DBRM. Database request module.

DB2 catalog. Tables that are maintained by DB2 and contain descriptions of DB2 objects, such as tables, views, and indexes.

DB2 command. An instruction to the DB2 subsystem allowing a user to start or stop DB2, to display information on current users, to start or stop databases, to display information on the status of databases, and so on.

DB2 for VSE & VM • DRDA access

DB2 for VSE & VM. The IBM DB2 relational database management system for the VSE and VM operating systems.

DB2I. DATABASE 2 Interactive.

DCLGEN. Declarations generator.

DDF. Distributed data facility.

ddname. Data definition name.

deadlock. Unresolvable contention for the use of a resource such as a table or an index.

declarations generator (DCLGEN). A subcomponent of DB2 that generates SQL table declarations and COBOL, C, or PL/I data structure declarations that conform to the table. The declarations are generated from DB2 system catalog information. DCLGEN is also a DSN subcommand.

declared temporary table. A table that holds temporary data and is defined with the SQL statement DECLARE GLOBAL TEMPORARY TABLE. Information about declared temporary tables is not stored in the DB2 catalog, so this kind of table is not persistent and can only be used by the application process that issued the DECLARE statement. Contrast with *created temporary table*. See also *temporary table*.

default value. A predetermined value, attribute, or option that is assumed when no other is explicitly specified.

deferred write. The process of asynchronously writing changed data pages to disk.

delimited identifier. A sequence of characters that are enclosed within double quotation marks ("). The sequence must consist of a letter followed by zero or more characters, each of which is a letter, digit, or the underscore character (_).

dependent. An object (row, table, or table space) that has at least one parent. The object is also said to be a dependent (row, table, or table space) of its parent. See *parent row*, *parent table*, *parent table space*.

dependent row. A row that contains a foreign key that matches the value of a primary key in the parent row.

dependent table. A table that is a dependent in at least one referential constraint.

descendent. An object that is a dependent of an object or is the dependent of a descendent of an object.

descendent row. A row that is dependent on another row, or a row that is a descendent of a dependent row.

descendent table. A table that is a dependent of another table, or a table that is a descendent of a dependent table.

direct access storage device (DASD). A device in which access time is independent of the location of the data.

directory. The DB2 system database that contains internal objects such as database descriptors and skeleton cursor tables.

distinct type. A user-defined data type that is internally represented as an existing type (its source type), but is considered to be a separate and incompatible type for semantic purposes.

distributed data facility (DDF). A set of DB2 components through which DB2 communicates with another RDBMS.

Distributed Relational Database Architecture (DRDA). A connection protocol for distributed relational database processing that is used by IBM's relational database products. DRDA includes protocols for communication between an application and a remote relational database management system, and for communication between relational database management systems.

DL/I. Data Language/I.

double-byte character large object (DBCLOB). A sequence of bytes representing double-byte characters where the size of the values can be up to 2 GB. In general, double-byte character large object values are used whenever a double-byte character string might exceed the limits of the VARGRAPHIC type.

double-byte character set (DBCS). A set of characters, which are used by national languages such as Japanese and Chinese, that have more symbols than can be represented by a single byte. Each character is 2 bytes in length. Contrast with *single-byte character set* and *multibyte character set*.

double-precision floating point number. A 64-bit approximate representation of a real number.

drain. The act of acquiring a locked resource by quiescing access to that object.

drain lock. A lock on a claim class that prevents a claim from occurring.

DRDA. Distributed Relational Database Architecture.

DRDA access. An open method of accessing distributed data that you can use to connect to another database server to execute packages that were previously bound at the server location. You use the SQL CONNECT statement or an SQL statement with a three-part name to identify the server. Contrast with *private protocol access*.

DSN. (1) The default DB2 subsystem name. (2) The name of the TSO command processor of DB2. (3) The first three characters of DB2 module and macro names.

duration. A number that represents an interval of time. See *date duration*, *labeled duration*, and *time duration*.

dynamic SQL. SQL statements that are prepared and executed within an application program while the program is executing. In dynamic SQL, the SQL source is contained in host language variables rather than being coded into the application program. The SQL statement can change several times during the application program's execution.

E

EBCDIC. Extended binary coded decimal interchange code. An encoding scheme that is used to represent character data in the OS/390, MVS, VM, VSE, and OS/400® environments. Contrast with *ASCII* and *Unicode*.

EDM pool. A pool of main storage that is used for database descriptors, application plans, authorization cache, application packages, and dynamic statement caching.

embedded SQL. SQL statements that are coded within an application program. See *static SQL*.

escape character. The symbol that is used to enclose an SQL delimited identifier. The escape character is the double quotation mark ("), except in COBOL applications, where the user assigns the symbol, which is either a double quotation mark or an apostrophe (').

ESDS. Entry sequenced data set.

EUR. IBM European Standards.

exception table. A table that holds rows that violate referential constraints or table check constraints that the CHECK DATA utility finds.

exclusive lock. A lock that prevents concurrently executing application processes from reading or changing data. Contrast with *share lock*.

executable statement. An SQL statement that can be embedded in an application program, dynamically prepared and executed, or issued interactively.

exit routine. A user-written (or IBM-provided default) program that receives control from DB2 to perform specific functions. Exit routines run as extensions of DB2.

explicit hierarchical locking. Locking that is used to make the parent-child relationship between resources known to IRLM. This kind of locking avoids global locking overhead when no inter-DB2 interest exists on a resource.

external function. A function for which the body is written in a programming language that takes scalar argument values and produces a scalar result for each invocation. Contrast with *sourced function*, *built-in function*, and *SQL function*.

F

failed member state. A state of a member of a data sharing group. When a member fails, the XCF permanently records the failed member state. This state usually means that the member's task, address space, or MVS system terminated before the state changed from active to quiesced.

fallback. The process of returning to a previous release of DB2 after attempting or completing migration to a current release.

false global lock contention. A contention indication from the coupling facility when multiple lock names are hashed to the same indicator and when no real contention exists.

field procedure. A user-written exit routine that is designed to receive a single value and transform (encode or decode) it in any way the user can specify.

fixed-length string. A character or graphic string whose length is specified and cannot be changed. Contrast with *varying-length string*.

foreign key. A column or set of columns in a dependent table of a constraint relationship. The key must have the same number of columns, with the same descriptions, as the primary key of the parent table. Each foreign key value must either match a parent key value in the related parent table or be null.

forward log recovery. The third phase of restart processing during which DB2 processes the log in a forward direction to apply all REDO log records.

free space. The total amount of unused space in a page; that is, the space that is not used to store records or control information is free space.

function. A mapping, embodied as a program (the function body), invocable by means of zero or more input values (arguments), to a single value (the result). See also *column function* and *scalar function*.

Functions can be user-defined, built-in, or generated by DB2. (See *built-in function*, *cast function*, *external function*, *sourced function*, *SQL function*, and *user-defined function*.)

function package. A package that results from binding the DBRM for a function program.

function package owner. The authorization ID of the user who binds the function program's DBRM into a function package.

GB • in-commit

G

GB. Gigabyte (1 073 741 824 bytes).

GBP. Group buffer pool.

GBP-dependent. The status of a page set or page set partition that is dependent on the group buffer pool. Either read/write interest is active among DB2 subsystems for this page set, or the page set has changed pages in the group buffer pool that have not yet been cast out to DASD.

generalized trace facility (GTF). An MVS service program that records significant system events such as I/O interrupts, SVC interrupts, program interrupts, or external interrupts.

getpage. An operation in which DB2 accesses a data page.

global lock. A lock that provides concurrency control within and among DB2 subsystems. The scope of the lock is across all the DB2 subsystems of a data sharing group.

global lock contention. Conflicts on locking requests between different DB2 members of a data sharing group when those members are trying to serialize shared resources.

governor. See *resource limit facility*.

gross lock. The *shared*, *update*, or *exclusive* mode locks on a table, partition, or table space.

group buffer pool (GBP). A coupling facility cache structure that is used by a data sharing group to cache data and to ensure that the data is consistent for all members.

group buffer pool duplexing. The ability to write data to two instances of a group buffer pool structure: a *primary group buffer pool* and a *secondary group buffer pool*. OS/390 publications refer to these instances as the "old" (for primary) and "new" (for secondary) structures.

group name. The MVS XCF identifier for a data sharing group.

group restart. A restart of at least one member of a data sharing group after the loss of either locks or the shared communications area.

GTF. Generalized trace facility.

H

help panel. A screen of information presenting tutorial text to assist a user at the terminal.

hiperspace. A range of up to 2 GB of contiguous virtual storage addresses that a program can use as a buffer. Like a data space, a hiperspace can hold user data; it does not contain common areas or system data. Unlike an address space or a data space, data in a hiperspace is not directly addressable. To manipulate data in a hiperspace, bring the data into the address space in 4-KB blocks.

host language. A programming language in which you can embed SQL statements.

host program. An application program that is written in a host language and that contains embedded SQL statements.

HSM. Hierarchical storage manager.

I

IDCAMS. An IBM program that is used to process access method services commands. It can be invoked as a job or jobstep, from a TSO terminal, or from within a user's application program.

identify. A request that an attachment service program in an address space that is separate from DB2 issues via the MVS subsystem interface to inform DB2 of its existence and to initiate the process of becoming connected to DB2.

IFCID. Instrumentation facility component identifier.

IFI. Instrumentation facility interface.

IFI call. An invocation of the instrumentation facility interface (IFI) by means of one of its defined functions.

image copy. An exact reproduction of all or part of a table space. DB2 provides utility programs to make full image copies (to copy the entire table space) or incremental image copies (to copy only those pages that have been modified since the last image copy).

IMS. Information Management System.

IMS attachment facility. A DB2 subcomponent that uses MVS subsystem interface (SSI) protocols and cross-memory linkage to process requests from IMS to DB2 and to coordinate resource commitment.

in-abort. A status of a unit of recovery. If DB2 fails after a unit of recovery begins to be rolled back, but before the process is completed, DB2 continues to back out the changes during restart.

in-commit. A status of a unit of recovery. If DB2 fails after beginning its phase 2 commit processing, it "knows," when restarted, that changes made to data are consistent. Such units of recovery are termed *in-commit*.

index. A set of pointers that are logically ordered by the values of a key. Indexes can provide faster access to data and can enforce uniqueness on the rows in a table.

index key. The set of columns in a table that is used to determine the order of index entries.

index partition. A VSAM data set that is contained within a partitioning index space.

index space. A page set that is used to store the entries of one index.

indicator column. A 4-byte value that is stored in a base table in place of a LOB column.

indoubt. A status of a unit of recovery. If DB2 fails after it has finished its phase 1 commit processing and before it has started phase 2, only the commit coordinator knows if an individual unit of recovery is to be committed or rolled back. At emergency restart, if DB2 lacks the information it needs to make this decision, the status of the unit of recovery is *indoubt* until DB2 obtains this information from the coordinator. More than one unit of recovery can be indoubt at restart.

indoubt resolution. The process of resolving the status of an indoubt logical unit of work to either the committed or the rollback state.

inflight. A status of a unit of recovery. If DB2 fails before its unit of recovery completes phase 1 of the commit process, it merely backs out the updates of its unit of recovery at restart. These units of recovery are termed *inflight*.

inheritance. The passing of class resources or attributes from a parent class downstream in the class hierarchy to a child class.

instrumentation facility component identifier (IFCID). A value that names and identifies a trace record of an event that can be traced. As a parameter on the START TRACE and MODIFY TRACE commands, it specifies that the corresponding event is to be traced.

instrumentation facility interface (IFI). A programming interface that enables programs to obtain online trace data about DB2, to submit DB2 commands, and to pass data to DB2.

Interactive System Productivity Facility (ISPF). An IBM licensed program that provides interactive dialog services.

inter-DB2 R/W interest. A property of data in a table space, index, or partition that has been opened by more than one member of a data sharing group and that has been opened for writing by at least one of those members.

intermediate database server. The target of a request from a local application or a remote application requester that is forwarded to another database server. In the DB2 environment, the remote request is forwarded transparently to another database server if the object that is referenced by a three-part name does not reference the local location.

internal resource lock manager (IRLM). An MVS subsystem that DB2 uses to control communication and database locking.

IRLM. Internal resource lock manager.

ISO. International Standards Organization.

isolation level. The degree to which a unit of work is isolated from the updating operations of other units of work. See also *cursor stability*, *read stability*, *repeatable read*, and *uncommitted read*.

ISPF. Interactive System Productivity Facility.

ISPF/PDF. Interactive System Productivity Facility/Program Development Facility.

J

Japanese Industrial Standards Committee (JISC). An organization that issues standards for coding character sets.

JCL. Job control language.

JES. MVS Job Entry Subsystem.

JIS. Japanese Industrial Standard.

job control language (JCL). A control language that is used to identify a job to an operating system and to describe the job's requirements.

Job Entry Subsystem (JES). An IBM licensed program that receives jobs into the system and processes all output data that is produced by the jobs.

K

KB. Kilobyte (1024 bytes).

Kerberos. A network authentication protocol that is designed to provide strong authentication for client/server applications by using secret-key cryptography.

Kerberos ticket. A transparent application mechanism that transmits the identity of an initiating principal to its target. A simple ticket contains the principal's identity, a session key, a timestamp, and other information, which is sealed using the target's secret key.

key • logical page list (LPL)

key. A column or an ordered collection of columns identified in the description of a table, index, or referential constraint.

key-sequenced data set (KSDS). A VSAM file or data set whose records are loaded in key sequence and controlled by an index.

KSDS. Key-sequenced data set.

L

labeled duration. A number that represents a duration of years, months, days, hours, minutes, seconds, or microseconds.

large object (LOB). A sequence of bytes representing bit data, single-byte characters, double-byte characters, or a mixture of single- and double-byte characters. A LOB can be up to 2 GB–1 byte in length. See also *BLOB*, *CLOB*, and *DBCLOB*.

leaf page. A page that contains pairs of keys and RIDs and that points to actual data. Contrast with *nonleaf page*.

linkage editor. A computer program for creating load modules from one or more object modules or load modules by resolving cross references among the modules and, if necessary, adjusting addresses.

link-edit. The action of creating a loadable computer program using a linkage editor.

L-lock. Logical lock.

load module. A program unit that is suitable for loading into main storage for execution. The output of a linkage editor.

LOB. Large object.

LOB table space. A table space that contains all the data for a particular LOB column in the related base table.

local. A way of referring to any object that the local DB2 subsystem maintains. A *local table*, for example, is a table that is maintained by the local DB2 subsystem. Contrast with *remote*.

local lock. A lock that provides intra-DB2 concurrency control, but not inter-DB2 concurrency control; that is, its scope is a single DB2.

local subsystem. The unique RDBMS to which the user or application program is directly connected (in the case of DB2, by one of the DB2 attachment facilities).

| **location.** The unique name of a database server. An
| application uses the location name to access a DB2
| database server.

lock. A means of controlling concurrent events or access to data. DB2 locking is performed by the IRLM.

lock duration. The interval over which a DB2 lock is held.

lock escalation. The promotion of a lock from a row, page, or LOB lock to a table space lock because the number of page locks that are concurrently held on a given resource exceeds a preset limit.

locking. The process by which the integrity of data is ensured. Locking prevents concurrent users from accessing inconsistent data.

lock mode. A representation for the type of access that concurrently running programs can have to a resource that a DB2 lock is holding.

lock object. The resource that is controlled by a DB2 lock.

lock parent. For explicit hierarchical locking, a lock that is held on a resource that has child locks that are lower in the hierarchy; usually the table space or partition intent locks are the parent locks.

lock promotion. The process of changing the size or mode of a DB2 lock to a higher level.

lock size. The amount of data controlled by a DB2 lock on table data; the value can be a row, a page, a LOB, a partition, a table, or a table space.

lock structure. A coupling facility data structure that is composed of a series of lock entries to support shared and exclusive locking for logical resources.

log. A collection of records that describe the events that occur during DB2 execution and that indicate their sequence. The information thus recorded is used for recovery in the event of a failure during DB2 execution.

logical claim. A claim on a logical partition of a nonpartitioning index.

logical drain. A drain on a logical partition of a nonpartitioning index.

logical index partition. The set of all keys that reference the same data partition.

logical lock (L-lock). The lock type that transactions use to control intra- and inter-DB2 data concurrency between transactions. Contrast with *physical lock (P-lock)*.

logical page list (LPL). A list of pages that are in error and that cannot be referenced by applications until the pages are recovered. The page is in *logical error*, because the actual media (coupling facility or DASD) might not contain any errors. Usually a connection to the media has been lost.

logical partition. A set of key or RID pairs in a nonpartitioning index that are associated with a particular partition.

logical unit. An access point through which an application program accesses the SNA network in order to communicate with another application program.

logical unit of work (LUW). The processing that a program performs between synchronization points.

logical unit of work identifier (LUWID). A name that uniquely identifies a thread within a network. This name consists of a fully-qualified LU network name, an LUW instance number, and an LUW sequence number.

log initialization. The first phase of restart processing during which DB2 attempts to locate the current end of the log.

log record sequence number (LRSN). A number that DB2 generates and associates with each log record. DB2 also uses the LRSN for page versioning. The LRSNs that a particular DB2 data sharing group generates form a strictly increasing sequence for each DB2 log and a strictly increasing sequence for each page across the DB2 group.

log truncation. A process by which an explicit starting RBA is established. This RBA is the point at which the next byte of log data is to be written.

LPL. Logical page list.

LRH. Log record header.

LRSN. Log record sequence number.

LU name. Logical unit name, which is the name by which VTAM refers to a node in a network. Contrast with *location name*.

LUW. Logical unit of work.

LUWID. Logical unit of work identifier.

M

MB. Megabyte (1 048 576 bytes).

member name. The MVS XCF identifier for a particular DB2 subsystem in a data sharing group.

menu. A displayed list of available functions for selection by the operator. A menu is sometimes called a *menu panel*.

migration. The process of converting a DB2 subsystem with a previous release of DB2 to an updated or current release. In this process, you can acquire the functions of the updated or current release without losing the data you created on the previous release.

mixed data string. A character string that can contain both single-byte and double-byte characters.

modify locks. An L-lock or P-lock with a MODIFY attribute. A list of these active locks is kept at all times in the coupling facility lock structure. If the requesting DB2 fails, that DB2 subsystem's modify locks are converted to retained locks.

MPP. Message processing program (in IMS).

MTO. Master terminal operator.

multisite update. Distributed relational database processing in which data is updated in more than one location within a single unit of work.

MVS. Multiple Virtual Storage.

MVS/ESA™. Multiple Virtual Storage/Enterprise Systems Architecture.

MVS/XA™. Multiple Virtual Storage/Extended Architecture.

N

negotiable lock. A lock whose mode can be downgraded, by agreement among contending users, to be compatible to all. A physical lock is an example of a negotiable lock.

network identifier (NID). The network ID that is assigned by IMS or CICS, or if the connection type is RRS/AF, the OS/390 RRS unit of recovery ID (URID).

NID. Network ID.

nonleaf page. A page that contains keys and page numbers of other pages in the index (either leaf or nonleaf pages). Nonleaf pages never point to actual data.

nonpartitioning index. Any index that is not a partitioning index.

NUL. In C, a single character that denotes the end of the string.

null. A special value that indicates the absence of information.

NUL-terminated host variable. A varying-length host variable in which the end of the data is indicated by the presence of a NUL terminator.

NUL terminator. In C, the value that indicates the end of a string. For character strings, the NUL terminator is 'X'00'.

OASN (origin application schedule number) • precompilation

O

OASN (origin application schedule number). In IMS, a 4-byte number that is assigned sequentially to each IMS schedule since the last cold start of IMS. The OASN is used as an identifier for a unit of work. In an 8-byte format, the first 4 bytes contain the schedule number and the last 4 bytes contain the number of IMS sync points (*commit points*) during the current schedule. The OASN is part of the NID for an IMS connection.

OBID. Data object identifier.

OS/390. Operating System/390®.

P

package. An object containing a set of SQL statements that have been statically bound and that is available for processing. A package is sometimes also called an *application package*.

package list. An ordered list of package names that may be used to extend an application plan.

page. A unit of storage within a table space (4 KB, 8 KB, 16 KB, or 32 KB) or index space (4 KB). In a table space, a page contains one or more rows of a table. In a LOB table space, a LOB value can span more than one page, but no more than one LOB value is stored on a page.

page set. Another way to refer to a table space or index space. Each page set consists of a collection of VSAM data sets.

panel. A predefined display image that defines the locations and characteristics of display fields on a display surface (for example, a *menu panel*).

parallel I/O processing. A form of I/O processing in which DB2 initiates multiple concurrent requests for a single user query and performs I/O processing concurrently (in *parallel*) on multiple data partitions.

parent row. A row whose primary key value is the foreign key value of a dependent row.

parent table. A table whose primary key is referenced by the foreign key of a dependent table.

parent table space. A table space that contains a parent table. A table space containing a dependent of that table is a dependent table space.

participant. An entity other than the commit coordinator that takes part in the commit process. The term participant is synonymous with *agent* in SNA.

partition. A portion of a page set. Each partition corresponds to a single, independently extendable data set. Partitions can be extended to a maximum size of 1,

2, or 4 GB, depending on the number of partitions in the partitioned page set. All partitions of a given page set have the same maximum size.

partitioned page set. A partitioned table space or an index space. Header pages, space map pages, data pages, and index pages reference data only within the scope of the partition.

partitioned table space. A table space that is subdivided into parts (based on index key range), each of which can be processed independently by utilities.

partner logical unit. An access point in the SNA network that is connected to the local DB2 subsystem by way of a VTAM conversation.

path. See *SQL path*.

piece. A data set of a nonpartitioned page set.

physical claim. A claim on an entire nonpartitioning index.

physical drain. A drain on an entire nonpartitioning index.

physical lock (P-lock). A lock type that DB2 acquires to provide consistency of data that is cached in different DB2 subsystems. Physical locks are used only in data sharing environments. Contrast with *logical lock (L-lock)*.

physical lock contention. Conflicting states of the requesters for a physical lock. See *negotiable lock*.

plan. See *application plan*.

plan allocation. The process of allocating DB2 resources to a plan in preparation for execution.

plan name. The name of an application plan.

P-lock. Physical lock.

point of consistency. A time when all recoverable data that an application accesses is consistent with other data. The term point of consistency is synonymous with *sync point* or *commit point*.

policy. See *CFRM policy*.

postponed abort UR. A unit of recovery that was inflight or in-abort, was interrupted by system failure or cancellation, and did not complete backout during restart.

precompilation. A processing of application programs containing SQL statements that takes place before compilation. SQL statements are replaced with statements that are recognized by the host language compiler. Output from this precompilation includes source code that can be submitted to the compiler and the database request module (DBRM) that is input to the bind process.

prefix. A code at the beginning of a message or record.

prepare. The first phase of a two-phase commit process in which all participants are requested to prepare for commit.

primary authorization ID. The authorization ID used to identify the application process to DB2.

primary group buffer pool. For a duplexed group buffer pool, the structure used to maintain the coherency of cached data. This structure is used for page registration and cross-invalidation. The OS/390 equivalent is *old* structure. Compare with *secondary group buffer pool*.

primary index. An index that enforces the uniqueness of a primary key.

private connection. A communications connection that is specific to DB2.

private protocol access. A method of accessing distributed data by which you can direct a query to another DB2 system. Contrast with *DRDA access*.

private protocol connection. A DB2 private connection of the application process. See also *private connection*.

privilege. The capability of performing a specific function, sometimes on a specific object. The term includes:

explicit privileges, which have names and are held as the result of SQL GRANT and REVOKE statements. For example, the SELECT privilege.

implicit privileges, which accompany the ownership of an object, such as the privilege to drop a synonym one owns, or the holding of an authority, such as the privilege of SYSADM authority to terminate any utility job.

privilege set. For the installation SYSADM ID, the set of all possible privileges. For any other authorization ID, the set of all privileges that are recorded for that ID in the DB2 catalog.

process. In DB2, the unit to which DB2 allocates resources and locks. Sometimes called an *application process*, a process involves the execution of one or more programs. The execution of an SQL statement is always associated with some process. The means of initiating and terminating a process are dependent on the environment.

program. A single compilable collection of executable statements in a programming language.

protected conversation. A VTAM conversation that supports two-phase commit flows.

Q

QMF™. Query Management Facility.

query. A component of certain SQL statements that specifies a result table.

quiesced member state. A state of a member of a data sharing group. An active member becomes quiesced when a STOP DB2 command takes effect without a failure. If the member's task, address space, or MVS system fails before the command takes effect, the member state is failed.

R

RACF. Resource Access Control Facility, which is a component of the SecureWay Security Server for OS/390.

RBA. Relative byte address.

RCT. Resource control table (in CICS attachment facility).

read stability (RS). An isolation level that is similar to repeatable read but does not completely isolate an application process from all other concurrently executing application processes. Under level RS, an application that issues the same query more than once might read additional rows that were inserted and committed by a concurrently executing application process.

rebind. The creation of a new application plan for an application program that has been bound previously. If, for example, you have added an index for a table that your application accesses, you must rebind the application in order to take advantage of that index.

record. The storage representation of a row or other data.

record identifier (RID) pool. An area of main storage above the 16-MB line that is reserved for sorting record identifiers during list prefetch processing.

recovery. The process of rebuilding databases after a system failure.

recovery log. A collection of records that describes the events that occur during DB2 execution and indicates their sequence. The recorded information is used for recovery in the event of a failure during DB2 execution.

recovery pending (RECP). A condition that prevents SQL access to a table space that needs to be recovered.

RECP. Recovery pending.

redo • schema

redo. A state of a unit of recovery that indicates that changes are to be reapplied to the DASD media to ensure data integrity.

referential constraint. The requirement that nonnull values of a designated foreign key are valid only if they equal values of the primary key of a designated table.

referential integrity. The state of a database in which all values of all foreign keys are valid. Maintaining referential integrity requires the enforcement of referential constraints on all operations that change the data in a table upon which the referential constraints are defined.

relationship. A defined connection between the rows of a table or the rows of two tables. A relationship is the internal representation of a referential constraint.

relative byte address (RBA). The offset of a data record or control interval from the beginning of the storage space that is allocated to the data set or file to which it belongs.

remote. Any object that is maintained by a remote DB2 subsystem (that is, by a DB2 subsystem other than the local one). A *remote view*, for example, is a view that is maintained by a remote DB2 subsystem. Contrast with *local*.

remote subsystem. Any RDBMS, except the *local subsystem*, with which the user or application can communicate. The subsystem need not be remote in any physical sense, and might even operate on the same processor under the same MVS system.

REORG pending (REORP). A condition that restricts SQL access and most utility access to an object that must be reorganized.

REORP. REORG pending.

repeatable read (RR). The isolation level that provides maximum protection from other executing application programs. When an application program executes with repeatable read protection, rows referenced by the program cannot be changed by other programs until the program reaches a commit point.

request commit. The vote that is submitted to the prepare phase if the participant has modified data and is prepared to commit or roll back.

resource. The object of a lock or claim, which could be a table space, an index space, a data partition, an index partition, or a logical partition.

resource control table (RCT). A construct of the CICS attachment facility, created by site-provided macro parameters, that defines authorization and access attributes for transactions or transaction groups.

resource limit facility (RLF). A portion of DB2 code that prevents dynamic manipulative SQL statements from exceeding specified time limits. The resource limit facility is sometimes called the governor.

resource limit specification table. A site-defined table that specifies the limits to be enforced by the resource limit facility.

restart pending (RESTP). A restrictive state of a page set or partition that indicates that restart (backout) work needs to be performed on the object. All access to the page set or partition is denied except for access by the:

- RECOVER POSTPONED command
- Automatic online backout (which DB2 invokes after restart if the system parameter LBACKOUT=AUTO)

RESTP. Restart pending.

result table. The set of rows that are specified by a SELECT statement.

retained lock. A MODIFY lock that a DB2 subsystem was holding at the time of a subsystem failure. The lock is retained in the coupling facility lock structure across a DB2 failure.

RID pool. Record identifier pool.

RLF. Resource limit facility.

RMID. Resource manager identifier.

RO. Read-only access.

rollback. The process of restoring data changed by SQL statements to the state at its last commit point. All locks are freed. Contrast with *commit*.

ROWID. Row identifier.

row identifier (ROWID). A value that uniquely identifies a row. This value is stored with the row and never changes.

RS. Read stability.

S

SBCS. Single-byte character set.

SCA. Shared communications area.

scalar function. An SQL operation that produces a single value from another value and is expressed as a function name, followed by a list of arguments that are enclosed in parentheses. Contrast with *column function*.

schema. A logical grouping for user-defined functions, distinct types, triggers, and stored procedures. When an object of one of these types is created, it is assigned to

one schema, which is determined by the name of the object. For example, the following statement creates a distinct type T in schema C:

```
CREATE DISTINCT TYPE C.T ...
```

search condition. A criterion for selecting rows from a table. A search condition consists of one or more predicates.

secondary authorization ID. An authorization ID that has been associated with a primary authorization ID by an authorization exit routine.

secondary group buffer pool. For a duplexed group buffer pool, the structure that is used to back up changed pages that are written to the primary group buffer pool. No page registration or cross-invalidation occurs using the secondary group buffer pool. The OS/390 equivalent is *new* structure.

section. The segment of a plan or package that contains the executable structures for a single SQL statement. For most SQL statements, one section in the plan exists for each SQL statement in the source program. However, for cursor-related statements, the DECLARE, OPEN, FETCH, and CLOSE statements reference the same section because, they each refer to the SELECT statement that is named in the DECLARE CURSOR statement. SQL statements such as COMMIT, ROLLBACK, and some SET statements do not use a section.

segmented table space. A table space that is divided into equal-sized groups of pages called segments. Segments are assigned to tables so that rows of different tables are never stored in the same segment.

sequential data set. A non-DB2 data set whose records are organized on the basis of their successive physical positions, such as on magnetic tape. Several of the DB2 database utilities require sequential data sets.

sequential prefetch. A mechanism that triggers consecutive asynchronous I/O operations. Pages are fetched before they are required, and several pages are read with a single I/O operation.

| **server.** The target of a request from a remote
| requester. In the DB2 environment, the server function
| is provided by the distributed data facility, which is used
| to access DB2 data from remote applications.

session. A link between two nodes in a VTAM network.

shared communications area (SCA). A coupling facility list structure that a DB2 data sharing group uses for inter-DB2 communication.

share lock. A lock that prevents concurrently executing application processes from changing data, but not from reading data. Contrast with *exclusive lock*.

shift-in character. A special control character (X'0F') that is used in EBCDIC systems to denote that the subsequent bytes represent SBCS characters. See also *shift-out character*.

shift-out character. A special control character (X'0E') that is used in EBCDIC systems to denote that the subsequent bytes, up to the next shift-in control character, represent DBCS characters. See also *shift-in character*.

sign-on. A request that is made on behalf of an individual CICS or IMS application process by an attachment facility to enable DB2 to verify that it is authorized to use DB2 resources.

simple table space. A table space that is neither partitioned nor segmented.

| **single-byte character set (SBCS).** A set of characters
| in which each character is represented by a single byte.
| Contrast with *double-byte character set* or *multibyte*
| *character set*.

SMF. System management facility.

SMS. Storage Management Subsystem.

SNA. Systems Network Architecture.

sourced function. A function that is implemented by another built-in or user-defined function that is already known to the database manager. This function can be a scalar function or a column (aggregating) function; it returns a single value from a set of values (for example, MAX or AVG). Contrast with *built-in function*, *external function*, and *SQL function*.

source program. A set of host language statements and SQL statements that is processed by an SQL precompiler.

SPUFI. SQL Processor Using File Input.

SQL. Structured Query Language.

SQL authorization ID (SQL ID). The authorization ID that is used for checking dynamic SQL statements in some situations.

SQLCA. SQL communication area.

SQL communication area (SQLCA). A structure that is used to provide an application program with information about the execution of its SQL statements.

SQLDA. SQL descriptor area.

SQL descriptor area (SQLDA). A structure that describes input variables, output variables, or the columns of a result table.

SQL/DS™ • TCB

SQL/DS™. Structured Query Language/Data System. This product is now obsolete and has been replaced by DB2 for VSE & VM.

SQL escape character. The symbol that is used to enclose an SQL delimited identifier. This symbol is the double quotation mark ("). See also *escape character*.

SQL function. A user-defined function in which the CREATE FUNCTION statement contains the source code. The source code is a single SQL expression that evaluates to a single value. The SQL user-defined function can return only one parameter.

SQL path. An ordered list of schema names that are used in the resolution of unqualified references to user-defined functions, distinct types, and stored procedures. In dynamic SQL, the current path is found in the CURRENT PATH special register. In static SQL, it is defined in the PATH bind option.

SQL Processor Using File Input (SPUFI). SQL Processor Using File Input. A facility of the TSO attachment subcomponent that enables the DB2I user to execute SQL statements without embedding them in an application program.

SQL return code. Either SQLCODE or SQLSTATE.

SQL string delimiter. A symbol that is used to enclose an SQL string constant. The SQL string delimiter is the apostrophe ('), except in COBOL applications, where the user assigns the symbol, which is either an apostrophe or a double quotation mark (").

SSI. Subsystem interface (in MVS).

SSM. Subsystem member.

stand-alone. An attribute of a program that means it is capable of executing separately from DB2, without using DB2 services.

static SQL. SQL statements, embedded within a program, that are prepared during the program preparation process (before the program is executed). After being prepared, the SQL statement does not change (although values of host variables that are specified by the statement might change).

storage group. A named set of disks on which DB2 data can be stored.

stored procedure. A user-written application program that can be invoked through the use of the SQL CALL statement.

string. See *character string* or *graphic string*.

Structured Query Language (SQL). A standardized language for defining and manipulating data in a relational database.

subsystem. A distinct instance of a relational database management system (RDBMS).

sync point. See *commit point*.

synonym. In SQL, an alternative name for a table or view. Synonyms can be used only to refer to objects at the subsystem in which the synonym is defined.

system administrator. The person at a computer installation who designs, controls, and manages the use of the computer system.

system agent. A work request that DB2 creates internally such as prefetch processing, deferred writes, and service tasks.

system conversation. The conversation that two DB2 subsystems must establish to process system messages before any distributed processing can begin.

Systems Network Architecture (SNA). The description of the logical structure, formats, protocols, and operational sequences for transmitting information through and controlling the configuration and operation of networks.

T

table. A named data object consisting of a specific number of columns and some number of unordered rows. See also *base table* or *temporary table*.

table check constraint. A user-defined constraint that specifies the values that specific columns of a base table can contain.

table space. A page set that is used to store the records in one or more tables.

table space set. A set of table spaces and partitions that should be recovered together for one of these reasons:

- Each of them contains a table that is a parent or descendent of a table in one of the others.
- The set contains a base table and associated auxiliary tables.

A table space set can contain both types of relationships.

task control block (TCB). A control block that is used to communicate information about tasks within an address space that are connected to DB2. An address space can support many task connections (as many as one per task), but only one address space connection. See also *address space connection*.

TB. Terabyte (1 099 511 627 776 bytes).

TCB. Task control block (in MVS).

temporary table. A table that holds temporary data; for example, temporary tables are useful for holding or sorting intermediate results from queries that contain a large number of rows. The two kinds of temporary table, which are created by different SQL statements, are the created temporary table and the declared temporary table. Contrast with *result table*. See also *created temporary table* and *declared temporary table*.

thread. The DB2 structure that describes an application's connection, traces its progress, processes resource functions, and delimits its accessibility to DB2 resources and services. Most DB2 functions execute under a thread structure. See also *allied thread* and *database access thread*.

three-part name. The full name of a table, view, or alias. It consists of a location name, authorization ID, and an object name, separated by a period.

time. A three-part value that designates a time of day in hours, minutes, and seconds.

time duration. A decimal integer that represents a number of hours, minutes, and seconds.

Time-Sharing Option (TSO). An option in MVS that provides interactive time sharing from remote terminals.

timestamp. A seven-part value that consists of a date and time. The timestamp is expressed in years, months, days, hours, minutes, seconds, and microseconds.

TMP. Terminal Monitor Program.

trace. A DB2 facility that provides the ability to monitor and collect DB2 monitoring, auditing, performance, accounting, statistics, and serviceability (global) data.

transaction lock. A lock that is used to control concurrent execution of SQL statements.

TSO. Time-Sharing Option.

TSO attachment facility. A DB2 facility consisting of the DSN command processor and DB2I. Applications that are not written for the CICS or IMS environments can run under the TSO attachment facility.

type 1 indexes. Indexes that were created by a release of DB2 before DB2 Version 4 or that are specified as type 1 indexes in Version 4. Contrast with *type 2 indexes*. As of Version 7, type 1 indexes are no longer supported.

type 2 indexes. Indexes that are created on a release of DB2 after Version 6 or that are specified as type 2 indexes in Version 4 or later.

U

UDF. User-defined function.

UDT. User-defined data type. In DB2 for OS/390 and z/OS, the term *distinct type* is used instead of user-defined data type. See *distinct type*.

uncommitted read (UR). The isolation level that allows an application to read uncommitted data.

undo. A state of a unit of recovery that indicates that the changes the unit of recovery made to recoverable DB2 resources must be backed out.

unique constraint. An SQL rule that no two values in a primary key, or in the key of a unique index, can be the same.

unique index. An index which ensures that no identical key values are stored in a table.

unit of recovery. A recoverable sequence of operations within a single resource manager, such as an instance of DB2. Contrast with *unit of work*.

unit of work. A recoverable sequence of operations within an application process. At any time, an application process is a single unit of work, but the life of an application process can involve many units of work as a result of commit or rollback operations. In a *multisite update* operation, a single unit of work can include several *units of recovery*. Contrast with *unit of recovery*.

UR. Uncommitted read.

URID (unit of recovery ID). The LOGRBA of the first log record for a unit of recovery. The URID also appears in all subsequent log records for that unit of recovery.

user-defined data type (UDT). See *distinct type*.

user-defined function (UDF). A function that is defined to DB2 by using the CREATE FUNCTION statement and that can be referenced thereafter in SQL statements. A user-defined function can be an *external function*, a *sourced function*, or an *SQL function*. Contrast with *built-in function*.

UT. Utility-only access.

V

value. The smallest unit of data that is manipulated in SQL.

variable. A data element that specifies a value that can be changed. A COBOL elementary data item is an example of a variable. Contrast with *constant*.

varying-length string. A character or graphic string whose length varies within set limits. Contrast with *fixed-length string*.

version. A member of a set of similar programs, DBRMs, packages, or LOBs.

view • z/OS

A version of a program is the source code that is produced by precompiling the program. The program version is identified by the program name and a timestamp (consistency token).

A version of a DBRM is the DBRM that is produced by precompiling a program. The DBRM version is identified by the same program name and timestamp as a corresponding program version.

A version of a package is the result of binding a DBRM within a particular database system. The package version is identified by the same program name and consistency token as the DBRM.

A version of a LOB is a copy of a LOB value at a point in time. The version number for a LOB is stored in the auxiliary index entry for the LOB.

view. An alternative representation of data from one or more tables. A view can include all or some of the columns that are contained in tables on which it is defined.

Virtual Storage Access Method (VSAM). An access method for direct or sequential processing of fixed- and varying-length records on direct access devices. The records in a VSAM data set or file can be organized in logical sequence by a key field (key sequence), in the physical sequence in which they are written on the data set or file (entry-sequence), or by relative-record number.

Virtual Telecommunications Access Method (VTAM). An IBM licensed program that controls communication and the flow of data in an SNA network.

VSAM. Virtual storage access method.

VTAM. Virtual Telecommunication Access Method (in MVS).

W

warm start. The normal DB2 restart process, which involves reading and processing log records so that data under the control of DB2 is consistent. Contrast with *cold start*.

X

XCF. See *cross-system coupling facility*.

Z

z/OS. An operating system for the eServer product line that supports 64-bit real storage.

Bibliography

DB2 Universal Database Server for OS/390 and z/OS Version 7 product libraries:

DB2 for OS/390 and z/OS

- *DB2 Administration Guide*, SC26-9931
- *DB2 Application Programming and SQL Guide*, SC26-9933
- *DB2 Application Programming Guide and Reference for Java*, SC26-9932
- *DB2 Command Reference*, SC26-9934
- *DB2 Data Sharing: Planning and Administration*, SC26-9935
- *DB2 Data Sharing Quick Reference Card*, SX26-3846
- *DB2 Diagnosis Guide and Reference*, LY37-3740
- *DB2 Diagnostic Quick Reference Card*, LY37-3741
- *DB2 Image, Audio, and Video Extenders Administration and Programming*, SC26-9947
- *DB2 Installation Guide*, GC26-9936
- *DB2 Licensed Program Specifications*, GC26-9938
- *DB2 Master Index*, SC26-9939
- *DB2 Messages and Codes*, GC26-9940
- *DB2 ODBC Guide and Reference*, SC26-9941
- *DB2 Reference for Remote DRDA Requesters and Servers*, SC26-9942
- *DB2 Reference Summary*, SX26-3847
- *DB2 Release Planning Guide*, SC26-9943
- *DB2 SQL Reference*, SC26-9944
- *DB2 Text Extender Administration and Programming*, SC26-9948
- *DB2 Utility Guide and Reference*, SC26-9945
- *DB2 What's New?* GC26-9946
- *DB2 XML Extender for OS/390 and z/OS Administration and Programming*, SC27-9949
- *DB2 Program Directory*, GI10-8182

DB2 Administration Tool

- *DB2 Administration Tool for OS/390 and z/OS User's Guide*, SC26-9847

DB2 Buffer Pool Tool

- *DB2 Buffer Pool Tool for OS/390 and z/OS User's Guide and Reference*, SC26-9306

DB2 DataPropagator™

- *DB2 UDB Replication Guide and Reference*, SC26-9920

Net.Data®

The following books are available at this Web site:
<http://www.ibm.com/software/net.data/library.html>

- *Net.Data Library: Administration and Programming Guide for OS/390 and z/OS*
- *Net.Data Library: Language Environment Interface Reference*
- *Net.Data Library: Messages and Codes*
- *Net.Data Library: Reference*

DB2 PM for OS/390

- *DB2 PM for OS/390 Batch User's Guide*, SC27-0857
- *DB2 PM for OS/390 Command Reference*, SC27-0855
- *DB2 PM for OS/390 Data Collector Application Programming Interface Guide*, SC27-0861
- *DB2 PM for OS/390 General Information*, GC27-0852
- *DB2 PM for OS/390 Installation and Customization*, SC27-0860
- *DB2 PM for OS/390 Messages*, SC27-0856
- *DB2 PM for OS/390 Online Monitor User's Guide*, SC27-0858
- *DB2 PM for OS/390 Report Reference Volume 1*, SC27-0853
- *DB2 PM for OS/390 Report Reference Volume 2*, SC27-0854
- *DB2 PM for OS/390 Using the Workstation Online Monitor*, SC27-0859
- *DB2 PM for OS/390 Program Directory*, GI10-8223

Query Management Facility (QMF)

- *Query Management Facility: Developing QMF Applications*, SC26-9579
- *Query Management Facility: Getting Started with QMF on Windows*, SC26-9582
- *Query Management Facility: High Performance Option User's Guide for OS/390 and z/OS*, SC26-9581
- *Query Management Facility: Installing and Managing QMF on OS/390 and z/OS*, GC26-9575

- *Query Management Facility: Installing and Managing QMF on Windows, GC26-9583*
- *Query Management Facility: Introducing QMF, GC26-9576*
- *Query Management Facility: Messages and Codes, GC26-9580*
- *Query Management Facility: Reference, SC26-9577*
- *Query Management Facility: Using QMF, SC26-9578*

Ada/370

- *IBM Ada/370 Language Reference, SC09-1297*
- *IBM Ada/370 Programmer's Guide, SC09-1414*
- *IBM Ada/370 SQL Module Processor for DB2 Database Manager User's Guide, SC09-1450*

APL2®

- *APL2 Programming Guide, SH21-1072*
- *APL2 Programming: Language Reference, SH21-1061*
- *APL2 Programming: Using Structured Query Language (SQL), SH21-1057*

AS/400®

The following books are available at this Web site:
www.as400.ibm.com/infocenter

- *DB2 Universal Database for AS/400 Database Programming*
- *DB2 Universal Database for AS/400 Performance and Query Optimization*
- *DB2 Universal Database for AS/400 Distributed Data Management*
- *DB2 Universal Database for AS/400 Distributed Data Programming*
- *DB2 Universal Database for AS/400 SQL Programming Concepts*
- *DB2 Universal Database for AS/400 SQL Programming with Host Languages*
- *DB2 Universal Database for AS/400 SQL Reference*

BASIC

- *IBM BASIC/MVS Language Reference, GC26-4026*
- *IBM BASIC/MVS Programming Guide, SC26-4027*

BookManager® READ/MVS

- *BookManager READ/MVS V1R3: Installation Planning & Customization, SC38-2035*

SAA® AD/Cycle® C/370™

- *IBM SAA AD/Cycle C/370 Programming Guide, SC09-1841*

- *IBM SAA AD/Cycle C/370 Programming Guide for Language Environment/370, SC09-1840*
- *IBM SAA AD/Cycle C/370 User's Guide, SC09-1763*
- *SAA CPI C Reference, SC09-1308*

Character Data Representation Architecture

- *Character Data Representation Architecture Overview, GC09-2207*
- *Character Data Representation Architecture Reference and Registry, SC09-2190*

CICS/ESA

- *CICS/ESA Application Programming Guide, SC33-1169*
- *CICS External Interfaces Guide, SC33-1944*
- *CICS for MVS/ESA Application Programming Reference, SC33-1170*
- *CICS for MVS/ESA CICS-RACF Security Guide, SC33-1185*
- *CICS for MVS/ESA CICS-Supplied Transactions, SC33-1168*
- *CICS for MVS/ESA Customization Guide, SC33-1165*
- *CICS for MVS/ESA Data Areas, LY33-6083*
- *CICS for MVS/ESA Installation Guide, SC33-1163*
- *CICS for MVS/ESA Intercommunication Guide, SC33-1181*
- *CICS for MVS/ESA Messages and Codes, GC33-1177*
- *CICS for MVS/ESA Operations and Utilities Guide, SC33-1167*
- *CICS/ESA Performance Guide, SC33-1183*
- *CICS/ESA Problem Determination Guide, SC33-1176*
- *CICS for MVS/ESA Resource Definition Guide, SC33-1166*
- *CICS for MVS/ESA System Definition Guide, SC33-1164*
- *CICS for MVS/ESA System Programming Reference, GC33-1171*

CICS Transaction Server for OS/390

- *CICS Application Programming Guide, SC33-1687*
- *CICS External Interfaces Guide, SC33-1703*
- *CICS DB2 Guide, SC33-1939*
- *CICS Resource Definition Guide, SC33-1684*

IBM C/C++ for MVS/ESA

- *IBM C/C++ for MVS/ESA Library Reference, SC09-1995*
- *IBM C/C++ for MVS/ESA Programming Guide, SC09-1994*

IBM COBOL

- *IBM COBOL Language Reference, SC26-4769*
- *IBM COBOL for MVS & VM Programming Guide, SC26-4767*

IBM COBOL for OS/390 & VM Programming Guide, SC26-9049

Conversion Guide

- *IMS-DB and DB2 Migration and Coexistence Guide, GH21-1083*

Cooperative Development Environment

- *CoOperative Development Environment/370: Debug Tool, SC09-1623*

DataPropagator NonRelational

- *DataPropagator NonRelational MVS/ESA Administration Guide, SH19-5036*
- *DataPropagator NonRelational MVS/ESA Reference, SH19-5039*

Data Facility Data Set Services

- *Data Facility Data Set Services: User's Guide and Reference, SC26-4388*

Database Design

- *DB2 Design and Development Guide by Gabrielle Wiorkowski and David Kull, Addison Wesley, ISBN 0-20158-049-7*
- *Handbook of Relational Database Design by C. Fleming and B. Von Halle, Addison Wesley, ISBN 0-20111-434-8*

DataHub®

- *IBM DataHub General Information, GC26-4874*

Data Refresher

- *Data Refresher Relational Extract Manager for MVS GI10-9927*

DB2 Connect®

- *DB2 Connect Enterprise Edition for OS/2 and Windows: Quick Beginnings, GC09-2953*
- *DB2 Connect Enterprise Edition for UNIX: Quick Beginnings, GC09-2952*
- *DB2 Connect Personal Edition Quick Beginnings, GC09-2967*
- *DB2 Connect User's Guide, SC09-2954*

DB2 Red Books

- *DB2 UDB Server for OS/390 Version 6 Technical Update, SG24-6108-00*

DB2 Server for VSE & VM

- *DB2 Server for VM: DBS Utility, SC09-2394*

- *DB2 Server for VSE: DBS Utility, SC09-2395*

DB2 Universal Database for UNIX®, Windows®, OS/2®

- *DB2 UDB Administration Guide: Planning, SC09-2946*
- *DB2 UDB Administration Guide: Implementation, SC09-2944*
- *DB2 UDB Administration Guide: Performance, SC09-2945*
- *DB2 UDB Administrative API Reference, SC09-2947*
- *DB2 UDB Application Building Guide, SC09-2948*
- *DB2 UDB Application Development Guide, SC09-2949*
- *DB2 UDB CLI Guide and Reference, SC09-2950*
- *DB2 UDB SQL Getting Started, SC09-2973*
- *DB2 UDB SQL Reference Volume 1, SC09-2974*
- *DB2 UDB SQL Reference Volume 2, SC09-2975*

Device Support Facilities

- *Device Support Facilities User's Guide and Reference, GC35-0033*

DFSMS

These books provide information about a variety of components of DFSMS, including DFSMS/MVS®, DFSMSdftp™, DFSMSdss™, DFSMSShsm™, and MVS/DFP™.

- *DFSMS/MVS: Access Method Services for the Integrated Catalog, SC26-4906*
- *DFSMS/MVS: Access Method Services for VSAM Catalogs, SC26-4905*
- *DFSMS/MVS: Administration Reference for DFSMSdss, SC26-4929*
- *DFSMS/MVS: DFSMSShsm Managing Your Own Data, SH21-1077*
- *DFSMS/MVS: Diagnosis Reference for DFSMSdftp, LY27-9606*
- *DFSMS/MVS Storage Management Library: Implementing System-Managed Storage, SC26-3123*
- *DFSMS/MVS: Macro Instructions for Data Sets, SC26-4913*
- *DFSMS/MVS: Managing Catalogs, SC26-4914*
- *DFSMS/MVS: Program Management, SC26-4916*
- *DFSMS/MVS: Storage Administration Reference for DFSMSdftp, SC26-4920*
- *DFSMS/MVS: Using Advanced Services, SC26-4921*

- *DFSMS/MVS: Utilities*, SC26-4926
- *MVS/DFP: Using Data Sets*, SC26-4749

DFSORT™

- *DFSORT Application Programming: Guide*, SC33-4035

Distributed Relational Database Architecture™

- *Data Stream and OPA Reference*, SC31-6806
- *IBM SQL Reference*, SC26-8416
- *Open Group Technical Standard*

The Open Group presently makes the following DRDA® books available through its Web site at: www.opengroup.org

- *DRDA Version 2 Vol. 1: Distributed Relational Database Architecture (DRDA)*
- *DRDA Version 2 Vol. 2: Formatted Data Object Content Architecture*
- *DRDA Version 2 Vol. 3: Distributed Data Management Architecture*

Domain Name System

- *DNS and BIND, Third Edition*, Paul Albitz and Cricket Liu, O'Reilly, ISBN 1-56592-512-2

Education

- *IBM Dictionary of Computing*, McGraw-Hill, ISBN 0-07031-489-6
- *1999 IBM All-in-One Education and Training Catalog*, GR23-8105

Enterprise System/9000® and Enterprise System/3090™

- *Enterprise System/9000 and Enterprise System/3090 Processor Resource/System Manager Planning Guide*, GA22-7123

High Level Assembler

- *High Level Assembler for MVS and VM and VSE Language Reference*, SC26-4940
- *High Level Assembler for MVS and VM and VSE Programmer's Guide*, SC26-4941

Parallel Sysplex® Library

- *OS/390 Parallel Sysplex Application Migration*, GC28-1863
- *System/390 MVS Sysplex Hardware and Software Migration*, GC28-1862
- *OS/390 Parallel Sysplex Overview: An Introduction to Data Sharing and Parallelism*, GC28-1860
- *OS/390 Parallel Sysplex Systems Management*, GC28-1861
- *OS/390 Parallel Sysplex Test Report*, GC28-1963

- *System/390 9672/9674 System Overview*, GA22-7148

ICSF/MVS

- *ICSF/MVS General Information*, GC23-0093

IMS

- *IMS Batch Terminal Simulator General Information*, GH20-5522
- *IMS Administration Guide: System*, SC26-9420
- *IMS Administration Guide: Transaction Manager*, SC26-9421
- *IMS Application Programming: Database Manager*, SC26-9422
- *IMS Application Programming: Design Guide*, SC26-9423
- *IMS Application Programming: Transaction Manager*, SC26-9425
- *IMS Command Reference*, SC26-9436
- *IMS Customization Guide*, SC26-9427
- *IMS Install Volume 1: Installation and Verification*, GC26-9429
- *IMS Install Volume 2: System Definition and Tailoring*, GC26-9430
- *IMS Messages and Codes*, GC27-1120
- *IMS Utilities Reference: System*, SC26-9441

ISPF

- *ISPF V4 Dialog Developer's Guide and Reference*, SC34-4486
- *ISPF V4 Messages and Codes*, SC34-4450
- *ISPF V4 Planning and Customizing*, SC34-4443
- *ISPF V4 User's Guide*, SC34-4484

Language Environment®

- *Debug Tool User's Guide and Reference*, SC09-2137

National Language Support

- *IBM National Language Support Reference Manual Volume 2*, SE09-8002

NetView®

- *NetView Installation and Administration Guide*, SC31-8043
- *NetView User's Guide*, SC31-8056

Microsoft® ODBC

- *Microsoft ODBC 3.0 Software Development Kit and Programmer's Reference*, Microsoft Press, ISBN 1-57231-516-4

OS/390

- *OS/390 C/C++ Programming Guide*, SC09-2362
- *OS/390 C/C++ Run-Time Library Reference*, SC28-1663

- *OS/390 C/C++ User's Guide, SC09-2361*
- *OS/390 eNetwork Communications Server: IP Configuration, SC31-8513*
- *OS/390 Hardware Configuration Definition Planning, GC28-1750*
- *OS/390 Information Roadmap, GC28-1727*
- *OS/390 Introduction and Release Guide, GC28-1725*
- *OS/390 JES2 Initialization and Tuning Guide, SC28-1791*
- *OS/390 JES3 Initialization and Tuning Guide, SC28-1802*
- *OS/390 Language Environment for OS/390 & VM Concepts Guide, GC28-1945*
- *OS/390 Language Environment for OS/390 & VM Customization, SC28-1941*
- *OS/390 Language Environment for OS/390 & VM Debugging Guide, SC28-1942*
- *OS/390 Language Environment for OS/390 & VM Programming Guide, SC28-1939*
- *OS/390 Language Environment for OS/390 & VM Programming Reference, SC28-1940*
- *OS/390 MVS Diagnosis: Procedures, LY28-1082*
- *OS/390 MVS Diagnosis: Reference, SY28-1084*
- *OS/390 MVS Diagnosis: Tools and Service Aids, LY28-1085*
- *OS/390 MVS Initialization and Tuning Guide, SC28-1751*
- *OS/390 MVS Initialization and Tuning Reference, SC28-1752*
- *OS/390 MVS Installation Exits, SC28-1753*
- *OS/390 MVS JCL Reference, GC28-1757*
- *OS/390 MVS JCL User's Guide, GC28-1758*
- *OS/390 MVS Planning: Global Resource Serialization, GC28-1759*
- *OS/390 MVS Planning: Operations, GC28-1760*
- *OS/390 MVS Planning: Workload Management, GC28-1761*
- *OS/390 MVS Programming: Assembler Services Guide, GC28-1762*
- *OS/390 MVS Programming: Assembler Services Reference, GC28-1910*
- *OS/390 MVS Programming: Authorized Assembler Services Guide, GC28-1763*
- *OS/390 MVS Programming: Authorized Assembler Services Reference, Volumes 1-4, GC28-1764, GC28-1765, GC28-1766, GC28-1767*
- *OS/390 MVS Programming: Callable Services for High-Level Languages, GC28-1768*
- *OS/390 MVS Programming: Extended Addressability Guide, GC28-1769*
- *OS/390 MVS Programming: Sysplex Services Guide, GC28-1771*
- *OS/390 MVS Programming: Sysplex Services Reference, GC28-1772*
- *OS/390 MVS Programming: Workload Management Services, GC28-1773*
- *OS/390 MVS Routing and Descriptor Codes, GC28-1778*
- *OS/390 MVS Setting Up a Sysplex, GC28-1779*
- *OS/390 MVS System Codes, GC28-1780*
- *OS/390 MVS System Commands, GC28-1781*
- *OS/390 MVS System Messages Volume 1, GC28-1784*
- *OS/390 MVS System Messages Volume 2, GC28-1785*
- *OS/390 MVS System Messages Volume 3, GC28-1786*
- *OS/390 MVS System Messages Volume 4, GC28-1787*
- *OS/390 MVS System Messages Volume 5, GC28-1788*
- *OS/390 MVS Using the Subsystem Interface, SC28-1789*
- *OS/390 Security Server External Security Interface (RACROUTE) Macro Reference, GC28-1922*
- *OS/390 Security Server (RACF) Auditor's Guide, SC28-1916*
- *OS/390 Security Server (RACF) Command Language Reference, SC28-1919*
- *OS/390 Security Server (RACF) General User's Guide, SC28-1917*
- *OS/390 Security Server (RACF) Introduction, GC28-1912*
- *OS/390 Security Server (RACF) Macros and Interfaces, SK2T-6700 (OS/390 Collection Kit), SK27-2180 (OS/390 Security Server Information Package)*
- *OS/390 Security Server (RACF) Security Administrator's Guide, SC28-1915*
- *OS/390 Security Server (RACF) System Programmer's Guide, SC28-1913*
- *OS/390 SMP/E Reference, SC28-1806*
- *OS/390 SMP/E User's Guide, SC28-1740*
- *OS/390 Support for Unicode: Using Conversion Services, SC33-7050*
- *OS/390 RMF User's Guide, SC28-1949*
- *OS/390 TSO/E CLISTS, SC28-1973*
- *OS/390 TSO/E Command Reference, SC28-1969*
- *OS/390 TSO/E Customization, SC28-1965*
- *OS/390 TSO/E Messages, GC28-1978*
- *OS/390 TSO/E Programming Guide, SC28-1970*
- *OS/390 TSO/E Programming Services, SC28-1971*
- *OS/390 TSO/E REXX Reference, SC28-1975*
- *OS/390 TSO/E User's Guide, SC28-1968*

- *OS/390 DCE Administration Guide, SC28-1584*
- *OS/390 DCE Introduction, GC28-1581*
- *OS/390 DCE Messages and Codes, SC28-1591*
- *OS/390 UNIX System Services Command Reference, SC28-1892*
- *OS/390 UNIX System Services Messages and Codes, SC28-1908*
- *OS/390 UNIX System Services Planning, SC28-1890*
- *OS/390 UNIX System Services User's Guide, SC28-1891*
- *OS/390 UNIX System Services Programming: Assembler Callable Services Reference, SC28-1899*

IBM Enterprise PL/I for z/OS and OS/390

- *IBM Enterprise PL/I for z/OS and OS/390 Language Reference, SC26-9476*
- *IBM Enterprise PL/I for z/OS and OS/390 Programming Guide, SC26-9473*

OS PL/I

- *OS PL/I Programming Language Reference, SC26-4308*
- *OS PL/I Programming Guide, SC26-4307*

Prolog

- *IBM SAA AD/Cycle Prolog/MVS & VM Programmer's Guide, SH19-6892*

RAMAC® and Enterprise Storage Server™

- *IBM RAMAC Virtual Array, SG24-4951*
- *RAMAC Virtual Array: Implementing Peer-to-Peer Remote Copy, SG24-5338*
- *Enterprise Storage Server Introduction and Planning, GC26-7294*

Remote Recovery Data Facility

- *Remote Recovery Data Facility Program Description and Operations, LY37-3710*

Storage Management

- *DFSMS/MVS Storage Management Library: Implementing System-Managed Storage, SC26-3123*
- *MVS/ESA Storage Management Library: Leading a Storage Administration Group, SC26-3126*
- *MVS/ESA Storage Management Library: Managing Data, SC26-3124*
- *MVS/ESA Storage Management Library: Managing Storage Groups, SC26-3125*
- *MVS Storage Management Library: Storage Management Subsystem Migration Planning Guide, SC26-4659*

System/370™ and System/390

- *ESA/370 Principles of Operation, SA22-7200*
- *ESA/390 Principles of Operation, SA22-7201*
- *System/390 MVS Sysplex Hardware and Software Migration, GC28-1210*

System Network Architecture (SNA)

- *SNA Formats, GA27-3136*
- *SNA LU 6.2 Peer Protocols Reference, SC31-6808*
- *SNA Transaction Programmer's Reference Manual for LU Type 6.2, GC30-3084*
- *SNA/Management Services Alert Implementation Guide, GC31-6809*

TCP/IP

- *IBM TCP/IP for MVS: Customization & Administration Guide, SC31-7134*
- *IBM TCP/IP for MVS: Diagnosis Guide, LY43-0105*
- *IBM TCP/IP for MVS: Messages and Codes, SC31-7132*
- *IBM TCP/IP for MVS: Planning and Migration Guide, SC31-7189*

VS COBOL II

- *VS COBOL II Application Programming Guide for MVS and CMS, SC26-4045*
- *VS COBOL II Application Programming: Language Reference, GC26-4047*
- *VS COBOL II Installation and Customization for MVS, SC26-4048*

VS Fortran

- *VS Fortran Version 2: Language and Library Reference, SC26-4221*
- *VS Fortran Version 2: Programming Guide for CMS and MVS, SC26-4222*

VTAM

- *Planning for NetView, NCP, and VTAM, SC31-8063*
- *VTAM for MVS/ESA Diagnosis, LY43-0069*
- *VTAM for MVS/ESA Messages and Codes, SC31-6546*
- *VTAM for MVS/ESA Network Implementation Guide, SC31-6548*
- *VTAM for MVS/ESA Operation, SC31-6549*
- *VTAM for MVS/ESA Programming, SC31-6550*
- *VTAM for MVS/ESA Programming for LU 6.2, SC31-6551*
- *VTAM for MVS/ESA Resource Definition Reference, SC31-6552*

Index

Special Characters

- *. (asterisk)
 - DISPLAY PROCEDURE command 148
 - START PROCEDURE command 295
 - STOP FUNCTION SPECIFIC command 322
 - STOP PROCEDURE command 327
- () (parentheses) in DB2 commands 4
- ' (apostrophe) in DB2 commands 4
- * (asterisk)
 - DB2 commands 4
 - DISPLAY THREAD command 155
 - FREE PACKAGE command 219
 - REBIND PACKAGE command 68
- : (colon)
 - in DB2 commands 4
- , (comma) in DB2 commands 4
- = (equal sign) in DB2 commands 4
- " (quotation mark) in DB2 commands 4

A

- ABEND
 - subcommand of DSN 175
- ACCESS option
 - START DATABASE command 279
 - START DB2 command 283
- accounting
 - audit trace, class descriptions 303
 - trace
 - displaying 165
 - starting 299
 - stopping 330
- ACCTG option
 - DISPLAY TRACE command 167
 - MODIFY TRACE command 238
 - START TRACE command 301
 - STOP TRACE command 332
- ACQUIRE
 - option of BIND PLAN subcommand
 - description 44
 - option of DSNH command 207
 - option of REBIND PLAN subcommand 44
- ACTION
 - option of DSNH command 207
- ACTION option
 - BIND PACKAGE subcommand 45
 - BIND PLAN subcommand 45
 - DCLGEN subcommand 86
 - RECOVER INDOUBT command 253
 - STOP FUNCTION SPECIFIC command 322
 - STOP PROCEDURE command 327
- ACTIVE option
 - DISPLAY BUFFERPOOL command 97
 - DISPLAY DATABASE command 111
 - DISPLAY THREAD command 155
- ADD
 - option of DCLGEN subcommand 86
- ADD (*continued*)
 - option on DSNH command 210
- ADVISORY option of DISPLAY DATABASE command 112
- AFTER
 - option of DISPLAY DATABASE command 110
- ALL keyword of MODIFY irlmproc,DIAG command 225
- ALLD option of MODIFY irlmproc,STATUS command of MVS 232
- ALLI option of MODIFY irlmproc,STATUS command of MVS 233
- ALTER BUFFERPOOL command
 - description 12
 - example 18
 - option descriptions 12
- ALTER GROUPBUFFERPOOL command
 - description 19
 - example 22
 - option descriptions 19
- ALTER UTILITY command
 - description 23
 - example 25
- ambiguous cursor 48
- APOST option
 - DCLGEN subcommand 87
 - DSNH command 199
- APOSTSQL option
 - DSNH command 205
- application plan
 - binding 38
 - deleting 221
 - maximum size 2
 - rebinding
 - changing plans 244
- application program
 - preparation
 - DSNH CLIST processing 189
 - START command 275
 - testing 175
- ARCHIVE LOG command
 - description 26
 - example 30
 - option descriptions 27
- ASMLIB option of DSNH command 194
- ASMLOAD option of DSNH command 194
- asterisk (*)
 - DISPLAY THREAD command 155
 - FREE PACKAGE command 219
 - in DB2 commands 4
 - REBIND PACKAGE command 68
- asterisk (*.*)
 - DISPLAY PROCEDURE command 148
 - START PROCEDURE command 295
 - STOP FUNCTION SPECIFIC command 322
 - STOP PROCEDURE command 327
- AT(COMMIT) option of STOP DATABASE command 313
- AT option of DCLGEN subcommand 85

AUDIT
 option of DISPLAY TRACE command 167
 option of MODIFY TRACE command 238
 option of START TRACE command 301
 option of STOP TRACE command 332
 audit trace
 class descriptions 304
 displaying 165
 starting 299
 stopping 330
 AUTHID
 option of DISPLAY TRACE command 168
 option of START TRACE command 303
 option of STOP TRACE command 333
 authorization ID
 naming convention xv
 secondary
 privileges 1
 SQL
 privileges exercised by 1
 AUTOREC option of ALTER GROUPBUFFERPOOL
 command 20

B

BDBRMLIB option of DSNH command 208
 BDMEM option of DSNH command 207
 BIND PACKAGE subcommand of DSN
 description 32
 example 36
 option descriptions 44
 BIND PLAN subcommand of DSN
 description 38
 example 41
 option descriptions 44
 binding
 DSNH processing 189
 initiating 32, 38
 options for 44
 blank
 characters in DB2 command 4
 BLIB option of DSNH command 207
 BMEM option of DSNH command 208
 BnLIB option of DSNH command 208
 BSDS (bootstrap data set)
 recovery 251
 buffer pool
 active and inactive 12, 97
 altering attributes 12
 displaying current status 97
 BUFSIZE option of START TRACE command 306

C

C option, DCLGEN subcommand 86
 CACHESIZE
 option of BIND PLAN subcommand 46
 option of DSNH command 208
 option of REBIND PLAN subcommand 46
 CANCEL
 option of RECOVER POSTPONED command 255

CANCEL OFFLOAD option of ARCHIVE LOG
 command 28
 CANCEL THREAD command
 description 77
 example 81
 option descriptions 77
 cancelling threads, description 77
 CASTOUT option
 of ALTER BUFFERPOOL command 15
 STOP DB2 command 316
 CATMAINT utility
 effects of TERM command 336
 CCLINK option of DSNH command 194
 CCLLIB option of DSNH command 194
 CCLOAD option of DSNH command 194
 CCMSGGS option of DSNH command 194
 CCOLIB option of DSNH command 194
 CCPLIB option of DSNH command 194
 CCPMSGGS option of DSNH command 194
 CCSLIB option of DSNH command 194
 CD-ROM, books on 351
 CHANGE command of IMS
 description 82
 example 83
 character xv
 CHECK DATA utility
 effects of TERM command 336
 CHECK INDEX utility
 effects of TERM command 336
 CHECK LOB utility
 effects of TERM command 336
 CHKTIME option, SET LOG command 270
 CICS
 commands
 DSNC 178
 DSNC DISCONNECT 179, 180
 DSNC DISPLAY 180, 183
 DSNC MODIFY 184, 185
 DSNC STOP 186
 DSNC STRT 187
 option of DSNH command 208
 translation step in DSNH processing 189
 CICS option
 BIND and REBIND subcommands 57
 DSNH command 204
 CICSJOB option of DSNH command 195
 CICSLLIB option of DSNH command 195
 CICSOPT option of DSNH command 195
 CICSPLIB option of DSNH command 195
 CICSPRE option of DSNH command 195
 CICSVER option of DSNH command 195
 CICSXLAT option of DSNH command 195
 CLAIMERS option of DISPLAY DATABASE
 command 109
 CLASS option
 DISPLAY TRACE command 168
 IFCIDs activated by trace class 303
 MODIFY TRACE command 239
 START TRACE command 303
 STOP TRACE command 333

- CLASST option of ALTER GROUPBUFFERPOOL command 20
- CLIB option of DSNH command 195
- CnLIB option of DSNH command 195
- COB2 option, DCLGEN subcommand 86
- COB2CICS option of DSNH command 196
- COB2LIB option of DSNH command 196
- COB2LOAD option of DSNH command 196
- COBICOMP option of DSNH command 195
- COBILINK option of DSNH command 195
- COBIPLNK option of DSNH command 195
- COBIPMSG option of DSNH command 196
- COBLIB option of DSNH command 196
- COBLOAD option of DSNH command 196
- COBOL option, DCLGEN subcommand 86
- COBSOM option of DSNH command 196
- code, return 177
- collection, package
 - BIND PACKAGE subcommand 67
 - ID naming convention xv
 - REBIND PACKAGE subcommand 67
 - REBIND TRIGGER PACKAGE subcommand 249
- COLSUFFIX option of DCLGEN subcommand
 - description 88
- column
 - name
 - as a field name 88
- comma option, DSNH command 198
- command continuation character 7
- command prefix
 - description 3
 - multiple subsystems 284
 - part of a command 3
- command recognition character (CRC) 3
- commands
 - scope 5
- comment
 - DCLGEN subcommand output 88
 - DSN subcommands 175
- COMMENT option
 - DISPLAY TRACE command 167
 - MODIFY TRACE command 239
 - START TRACE command 301
 - STOP TRACE command 332
- commit point
 - terminating utility 335
- COMP option of TRACE CT command 341
- COMPILE option of DSNH command 196
- compiling 189
- conditional restart
 - control record
 - effect on restart 284
- CONNECT
 - option of DSN command 196
- connection
 - DB2
 - GROUP option of DSN command 176
 - RETRY option of DSN command 176
 - displaying
 - connection information 153
 - group buffer pool 137
 - connection (*continued*)
 - displaying (*continued*)
 - IRLM subsystem status 233
 - status 92
 - DSNC DISPLAY command 180
 - terminating 309
 - connection-name naming convention xvi
- CONNLIST option of DISPLAY GROUPBUFFERPOOL command 131
- CONTROL
 - option of DSNH command 196
- COPTION option of DSNH command 197
- COPY option
 - BIND PACKAGE subcommand 47
 - DSNH command 211
- COPY utility
 - effects of TERM command 336
- COPYVER option
 - BIND PACKAGE subcommand 47
 - DSNH command 211
- correlation ID
 - naming convention xvi
 - recovering threads 253
- CORRELATION option of START TRACE command 306
- COUNT option
 - SET ARCHIVE command 265
- CP option of RUN subcommand 262
- CPP option, DCLGEN subcommand 86
- CPPCLASS option of DSNH command 197
- CPPCLLIB option of DSNH command 197
- CPPCSLIB option of DSNH command 197
- CPPLINK option of DSNH command 197
- CPPLLIB option of DSNH command 197
- CPPPMMSG option of DSNH command 197
- CPPSLIB option of DSNH command 197
- CPPUTIL option of DSNH command 197
- CPU option of START TRACE command 306
- CRC (command recognition character)
 - description 3
- CSA option of MODIFY irlmproc,SET command of MVS 228
- CURRENTDATA option
 - BIND PACKAGE subcommand
 - description 48
 - BIND PLAN subcommand 48
 - DSNH command 208, 211
 - REBIND PACKAGE subcommand 48
 - REBIND PLAN subcommand 48
 - REBIND TRIGGER PACKAGE subcommand 48
 - description 48
- CURRENTSERVER
 - DSNH command 208
 - option of BIND PLAN subcommand 49
 - option of REBIND PLAN subcommand 49
- cursor
 - ambiguous 48
- CYLINDER option of DSNH command 205

D

- data set
 - naming convention xvi
- data sharing
 - delays, diagnosing 225
 - displaying
 - archive log information 95
 - information about groups 125
 - status of members 125
 - identifying members with utility jobs 172
 - scope of commands 5
 - starting members 285
- database
 - displaying status 106
 - reserved names 313
 - starting 276
 - stopping 310
- DATE
 - option of DSNH command 197
- DB2
 - precompiler 4
- DB2 books online 351
- DB2 commands
 - command names 4
 - commands
 - ALTER BUFFERPOOL 12, 18
 - ALTER GROUPBUFFERPOOL 19, 22
 - ALTER UTILITY 23
 - ARCHIVE LOG 26, 31
 - CANCEL THREAD 77, 81
 - DISPLAY ARCHIVE 95, 96
 - DISPLAY BUFFERPOOL 97
 - DISPLAY DATABASE 106
 - DISPLAY DDF 119
 - DISPLAY GROUP 125, 129
 - DISPLAY GROUPBUFFERPOOL 129
 - DISPLAY LOCATION 143, 145
 - DISPLAY LOG 146
 - DISPLAY PROCEDURE 148
 - DISPLAY RLIMIT 152
 - DISPLAY THREAD 153
 - DISPLAY TRACE 165, 170
 - DISPLAY UTILITY 171, 174
 - MODIFY TRACE 238, 240
 - RECOVER BSDS 251
 - RECOVER INDOUBT 252, 254
 - RECOVER POSTPONED 255
 - RESET INDOUBT 259
 - START DATABASE 276
 - START DB2 283, 285
 - START DDF 286
 - START FUNCTION SPECIFIC 287
 - START PROCEDURE 294
 - START RLIMIT 297, 298
 - START TRACE 299
 - STOP DATABASE 310
 - STOP DB2 316, 317
 - STOP DDF 318, 320
 - STOP PROCEDURE 326
 - STOP RLIMIT 329
 - STOP TRACE 330, 334
- DB2 commands (*continued*)
 - commands (*continued*)
 - TERM UTILITY 335, 337
 - completion messages 10
 - description 4
 - DISPLAY FUNCTION SPECIFIC 121
 - entering from
 - supported environments 8
 - scope 5
 - separator 4
 - STOP FUNCTION SPECIFIC command 321
- DBM1 option of START DB2 command 284
- DBPROTOCOL
 - option of BIND PACKAGE subcommand 49
 - option of BIND PLAN subcommand 49
 - option of REBIND PACKAGE subcommand 49
 - option of REBIND PLAN subcommand 49
- DBPROTOCOL option, DSNH command 208
- DBRM (database request module)
 - BIND PLAN subcommand 65
 - maximum number in plan 2
- DBRMLIB option of DSNH command 198
- DCLGEN subcommand of DSN
 - declaring an indicator variable array 88
 - description 84
 - example 90
 - forming field names 88
 - option descriptions 85
- DDF (distributed data facility)
 - displaying, DISPLAY DDF command 119
- DEADLINE option for ALTER UTILITY command 24
- DEADLOCK option of MODIFY irlmproc, SET command of MVS 229
- DEADLOCK option of START irlmproc command 290
- DECARTH option of DSNH command 198
- DECIMAL
 - option of DSNH command 198
- DEFAULT
 - option of SET ARCHIVE command 266
- DEFER
 - option of BIND PACKAGE subcommand 50
 - option of BIND PLAN subcommand 50, 51
 - option of DSNH command 208, 209
 - option of REBIND PACKAGE subcommand 50
 - option of REBIND PLAN subcommand 50
- DEGREE
 - option of BIND PACKAGE subcommand 51
 - option of BIND PLAN subcommand 51
 - option of DSNH command 208
 - option of REBIND PACKAGE subcommand 51
 - option of REBIND PLAN subcommand 51
- degree of parallel processing 51
- DELAY
 - keyword of MODIFY irlmproc, DIAG command 225
 - option of ALTER UTILITY command 24
- deleting
 - IMS units of recovery 82
- DELIMIT option of DSNH command 199
- deregistering IRLM 223
- DEST option
 - DISPLAY TRACE command 167

- DEST option *(continued)*
 - START TRACE command 301
 - STOP TRACE command 332
- DESTINATION option of DSNC MODIFY command 184
- DETAIL option
 - DISPLAY BUFFERPOOL command 98
 - DISPLAY GROUP command 125
 - DISPLAY LOCATION command 144
 - DISPLAY THREAD command 157
 - DISPLAY TRACE command 167
- detail report of DISPLAY BUFFERPOOL command 101
- DIAG
 - keyword of MODIFY irlmproc,DIAG command 225
- DIAGNOSE utility
 - TERM command effects 336
- diagnostic dumps, IRLM 225
- DISABLE option
 - BIND PACKAGE subcommand 56
 - BIND PLAN subcommand 56
 - DSNH command 209
 - REBIND PACKAGE subcommand 56
 - REBIND PLAN subcommand 56
- disabling a function permanently 322
- DISCONNECT
 - option of BIND PLAN subcommand 52
 - option of DSNH command 209
 - option of REBIND PLAN subcommand 52
- DISPLAY
 - command of IMS
 - description 92
 - example 94
 - option descriptions 92
 - DSNC DISPLAY command 180
- DISPLAY ARCHIVE command 95
- DISPLAY BUFFERPOOL command
 - description 97
 - option descriptions 97
 - output 99
- DISPLAY DATABASE command
 - description 106
 - example 115
 - option descriptions 108
- DISPLAY DDF command
 - description 119
 - example 120
 - option descriptions 119
 - output 119
- DISPLAY FUNCTION SPECIFIC command
 - description 121
 - examples 123
 - output 122
- DISPLAY GROUP command
 - description 125
 - examples 127
 - IRLM information 126
- DISPLAY GROUPBUFFERPOOL command
 - description 129
 - option descriptions 130
- DISPLAY GROUPBUFFERPOOL command *(continued)*
 - output
 - group detail report 132
 - member detail report 133
 - summary report 131
 - summary report example 137
- DISPLAY LOCATION command
 - description 143
 - example 144
 - option descriptions 143
- DISPLAY LOG command
 - description 146
 - example 146
- DISPLAY NET command of VTAM 79
- DISPLAY PROCEDURE command
 - description 148
 - example 150
 - option descriptions 148
 - output 149
- DISPLAY RLIMIT command 152
- DISPLAY THREAD command
 - description 153
 - example 160
 - option descriptions 154
 - output 158
- DISPLAY TRACE command
 - description 165
 - example 169
 - option descriptions 166
 - output 169
- DISPLAY UTILITY command
 - description 171
 - example 173
 - option descriptions 171
 - output 172
- displaying
 - information about
 - archive logs 95
 - data sharing group 125
 - DB2 functions 121
 - DB2 threads 153
 - DDF 119
 - resource limit facility (governor) 152
 - restricted objects 112
 - stored procedures 148
 - threads with remote locations 143
 - trace activity 165
 - log information 146
 - status of
 - buffer pools 97
 - DB2 databases 106
 - DB2 utilities 171
 - group buffer pools 129
- DIST option of START DB2 command 284
- DISTRIBUTED option of START TRACE command 306
- DLIBATCH option
 - BIND and REBIND subcommands 57
 - DSNH command 209
- DSN command of TSO
 - abbreviations 7

DSN command of TSO *(continued)*

- description 175
- example 177
- option descriptions 175
- return codes 177
- subcommands 7
 - ABEND 175
 - BIND PACKAGE 32, 37
 - BIND PLAN 38, 43
 - DCLGEN 84, 91
 - END 217
 - FREE PACKAGE 218, 220
 - FREE PLAN 221, 222
 - parsing 7
 - REBIND PACKAGE 240
 - REBIND PLAN 244
 - REBIND TRIGGER PACKAGE 248
 - return codes 177
 - RUN 262, 264
 - SPUFI 273

DSNC command of CICS

- description 178

DSNC DISCONNECT command of CICS

- description 179
- example 179

DSNC DISPLAY command of CICS

- description 180
- example 182
- option descriptions 180
- output 181

DSNC MODIFY command of CICS

- description 184
- example 185
- option descriptions 184

DSNC STOP command of CICS

- description 186
- example 186
- option descriptions 186

DSNC STRT command of CICS

- description 187
- example 187
- option descriptions 187

DSNDB01 database

- authority needed to start 276

DSNDB06 database

- authority needed to start 276

DSNH command of TSO

- data set names 193
- description 189
- example 214
- option descriptions 190

DSNHDECP

- list of parameters 343

DSNZPARM

- list of parameters 343
- option of START DB2 command 283

dump

- IRLM diagnostic 225

DUMP

- option of CANCEL THREAD command 78

DWQT option of ALTER BUFFERPOOL command 14

DYNAMICRULES

- option of BIND PACKAGE subcommand 52
- option of BIND PLAN subcommand 52
- option of REBIND PACKAGE subcommand 52
- option of REBIND PLAN subcommand 52

DYNAMICRULES option

- DSNH command 209

E

ENABLE

- option of BIND PACKAGE subcommand 56
- option of BIND PLAN subcommand 56
- option of REBIND PACKAGE subcommand 56
- option of REBIND PLAN subcommand 56

ENABLE option, DSNH command 209

ENCODING

- option of BIND PACKAGE subcommand 58
- option of BIND PLAN subcommand 58
- option of REBIND PACKAGE subcommand 58
- option of REBIND PLAN subcommand 58

END

- subcommand of DSN

- description 217

- example 217

ENTRY option of DSNH command 199

escape character

- APOST option of DCLGEN subcommand 87
- QUOTE option of DCLGEN subcommand 87

executing

- connections between IMS and a subsystem 275

EXPLAIN

- option of BIND PACKAGE subcommand 59
- option of BIND PLAN subcommand 59
- option of REBIND PACKAGE subcommand 59
- option of REBIND PLAN subcommand 59
- option of REBIND TRIGGER PACKAGE subcommand 59

EXPLAIN option, DSNH command 209, 212

extended MCS consoles, DB2 support of 8

F

F irlmproc, ABEND command of MVS 223

F irlmproc, DIAG command of MVS 225

F irlmproc, PURGE command of MVS IRLM 227

F irlmproc, SET command of MVS IRLM 228

F irlmproc, STATUS command of MVS IRLM 232

FLAG option

- BIND PACKAGE subcommand 60

- BIND PLAN subcommand 60

- DSNH command 209

- FREE PACKAGE subcommand 219

- FREE PLAN subcommand 221

- of DSNH command 199

- REBIND PACKAGE subcommand 60

- REBIND PLAN subcommand 60

- REBIND TRIGGER PACKAGE subcommand 60

FORCE option

- DSNC STOP command 186

- RESET INDOUBT command 260

- FORCE option (*continued*)
 - START DATABASE command 279
 - STOP DB2 command 316
 - STOP DDF command 318
- FORTLIB option of DSNH command 199
- FORTLOAD option of DSNH command 199
- FREE PACKAGE subcommand of DSN
 - description 218
 - example 220
 - option descriptions 219
- FREE PLAN subcommand of DSN
 - description 221
 - example 222
 - option descriptions 221
- functions
 - displaying
 - DISPLAY FUNCTION SPECIFIC command 121

G

- GBPCACHE option of ALTER GROUPBUFFERPOOL command 20
- GPCHKPT option of ALTER GROUPBUFFERPOOL command 21
- GBPOOLT option of ALTER GROUPBUFFERPOOL command 21
- GDETAIL option of DISPLAY GROUPBUFFERPOOL command 131
- GLOBAL option of START irlmproc command 293
- GRAPHIC option of DSNH command 199
- GRECP (group buffer pool RECOVER-pending) status
 - removing using START DATABASE command 280
- group, scope of command 5
- group buffer pool RECOVER-pending (GRECP) status
 - removing using START DATABASE command 280
- group detail report of DISPLAY GROUPBUFFERPOOL command 132
- GROUP option of DSN command 176
- GTF option
 - DISPLAY TRACE command 168
 - START TRACE command 302
 - STOP TRACE command 332

H

- HANG
 - keyword of MODIFY irlmproc,DIAG command 226
- HOST option of DSNH command 200
- HPSEQT option of ALTER BUFFERPOOL command 14
- HPSIZE option of ALTER BUFFERPOOL command 13

I

- I/O processing
 - parallel
 - DEGREE option of bind subcommands 51
- IBMCOB option, DCLGEN subcommand 86
- ID option
 - RECOVER INDOUBT command 253
 - START RLIMIT command 297

- IFCID (instrumentation facility component identifier)
 - identifiers by trace class 303
- IFCID option
 - MODIFY TRACE command 239
 - START TRACE command 305
- IMMEDWRITE option
 - BIND PACKAGE subcommand 61
 - BIND PLAN subcommand 61
 - REBIND PACKAGE subcommand 61
 - REBIND PLAN subcommand 61
- IMS
 - commands
 - CHANGE 82, 83
 - DISPLAY 92, 94
 - SSR 274
 - START 275
 - STOP 309
 - TRACE 338
 - facilities
 - events tracing 338
- IMSBMP option
 - BIND and REBIND subcommands 57
 - DSNH command 209
- IMSMPP option
 - BIND and REBIND subcommands 57
 - DSNH command 209
- IMSPRE option of DSNH command 200
- INACTIVE
 - option of DISPLAY THREAD command 156
- INCLUDE statement
 - DCLGEN subcommand output 88
- indicator variable
 - array declaration in DCLGEN 88
- INDOUBT option of DISPLAY THREAD command 155
- indoubt thread
 - recovering 252, 254
- INDVAR option of DCLGEN subcommand,
 - description 88
- INPUT option of DSNH command 200
- INTERVAL option of DISPLAY BUFFERPOOL command 98
- invalidated plans and packages 60
- IPADDR
 - DISPLAY LOCATION command 144
 - RESET INDOUBT command 261
- IRLM (internal resource lock manager)
 - commands
 - MODIFY irlmproc,ABEND 223
 - MODIFY irlmproc,DIAG 225
 - MODIFY irlmproc,PURGE option 227
 - MODIFY irlmproc,SET option 228
 - MODIFY irlmproc,STATUS option 232
 - overview 11
 - START irlmproc 290
 - STOP irlmproc 324
 - TRACE CT 340
- CSA
 - setting maximum amount of 228
- delays, diagnosing 225
- deregistering 223
- diagnostic dumps 225

IRLM (internal resource lock manager) *(continued)*
 DISPLAY GROUP command output 126
 locks
 releasing 227
 modifying, diagnostic trace 340
 restarting
 effect on CSA value 229
 effect on number of trace buffers 229
 starting
 an IRLM component 290
 starting, diagnostic trace 340
 status
 checking 228, 232
 stopping
 normal 324
 stopping, diagnostic trace 340
 terminating
 abnormal 223
 normal 324
 trace buffers, setting number of 228
 IRLMGRP option
 START irlmproc command 291
 IRLMID option of START irlmproc command 291
 IRLMMN option of START irlmproc command 291
 ISOLATION
 option of BIND PACKAGE subcommand 62
 option of BIND PLAN subcommand
 description 62
 option of REBIND PACKAGE subcommand 62
 option of REBIND PLAN subcommand 62
 option of REBIND TRIGGER PACKAGE
 subcommand 62
 ISOLATION option, DSNH command 209

K

KEEPDYNAMIC option
 BIND PACKAGE subcommand 63
 BIND PLAN subcommand 63
 DSNH command 209
 REBIND PACKAGE subcommand 63
 REBIND PLAN subcommand 63

L

LABEL
 option of DCLGEN subcommand 87
 LANGUAGE
 option of DCLGEN subcommand 86
 LEAVE option of DSNH command 206
 letter, description in DB2 xv
 library
 online 351
 LIBRARY option
 BIND PACKAGE subcommand 64
 BIND PLAN subcommand 64
 DCLGEN subcommand 86
 RUN subcommand 263
 LIGHT option, START DB2 command 284
 light restart
 with ARM 285

LIMIT
 option of DISPLAY DATABASE command 110
 LINECOUNT option
 DSNH command 200
 link-editing
 processing 189
 LINK option of DSNH command 200
 LIST
 option of DISPLAY BUFFERPOOL command 98
 LLIB option of DSNH command 200
 LnLIB option of DSNH command 200
 LOAD option
 of DSNH command 200
 SET SYSPARM command 268
 LOAD utility
 effects of TERM command 336
 LOCAL option of START irlmproc command 292
 LOCATION
 option of DISPLAY THREAD command 156
 option of DISPLAY TRACE command 168
 option of RESET INDOUBT command 260
 option of START TRACE command 306
 option of STOP TRACE command 333
 location name
 BIND PACKAGE subcommand 57, 67
 DISPLAY LOCATION command 143
 REBIND PACKAGE subcommand 57, 67
 REBIND TRIGGER PACKAGE subcommand 249
 LOCKS option of DISPLAY DATABASE command 109
 LOCKTABL option of START irlmproc command 291
 LOG
 option of TRACE command 338
 logical page list (LPL) 280
 LOGLOAD option, SET LOG command 270
 LONGLOG option of ALTER UTILITY option 24
 LOPTION option of DSNH command 200
 LPL
 option of DISPLAY DATABASE command 109
 LPL (logical page list)
 recovering pages
 using START DATABASE command 280
 LSTATS option of DISPLAY BUFFERPOOL
 command 98
 LTE option of MODIFY irlmproc,SET command of
 MVS 229
 LUNAME
 DISPLAY LOCATION command 144
 option of RESET INDOUBT command 260
 LUWID option
 DISPLAY THREAD command 157
 RECOVER INDOUBT command 253
 RESET INDOUBT command 261

M

MACRO option of DSNH command 201
 MAINT option of MODIFY irlmproc,STATUS command
 of MVS 233
 MAINT option of START DB2 command 284
 MAXCSA option of START irlmproc command 291

- MAXRO
 - option of ALTER UTILITY command 24
- MAXUSRS
 - option of START irlmproc command 292
- MCS consoles, scope of commands 5
- MDETAIL option of DISPLAY GROUPBUFFERPOOL command 130
- member, scope of command 5
- member detail report of DISPLAY
 - GROUPBUFFERPOOL command 133
- MEMBER option
 - BIND PACKAGE subcommand 65
 - BIND PLAN subcommand 65
 - DISPLAY UTILITY command 172
- MERGECOPY utility
 - effects of TERM command 336
- message
 - DB2 commands 10
 - DCLGEN subcommand 87
 - DISPLAY THREAD with ACTIVE 155
 - DISPLAY TRACE command 170
 - DISPLAY UTILITY command 171, 172
 - DSN command of TSO 176
 - DSNH command 199
 - FLAG option of bind subcommands 60
 - FREE PACKAGE subcommand 219
 - FREE PLAN subcommand 221
 - MODIFY irlmproc,STATUS command 233
 - RUN subcommand 264
- message by identifier
 - DSN7106I 125
 - DSN9022I 10
 - DSN9023I 10
 - DSNB411I 101
 - DSNB412I 101
 - DSNB413I 101
 - DSNB414I 101
 - DSNB415I 102
 - DSNB420I 102
 - DSNB421I 102
 - DSNB430I 102
 - DSNB431I 103
 - DSNI021I 282
 - DSNJ315I 29
 - DSNJ316I 29
 - DSNJ317I 29
 - DSNJ318I 29
 - DSNL440I to DSNL449I 261
 - DSNL448I 260
 - DSNL450I 78
 - DSNT392I 113
 - DSNT500I 114
 - DSNT501I 114
 - DSNT736I 313
 - DSNU100I 172
 - DSNU105I 172
 - DSNU106I 172
 - DSNV413I 158
 - DSNW133I 301
 - DSNX943I 150
 - DSNX950I 150

- MODE option
 - ARCHIVE LOG command 27
 - STOP DB2 command 316
 - STOP DDF command 318
- MODIFY irlmproc,ABEND command of MVS
 - description 223
 - example 223
- MODIFY irlmproc,DIAG command of MVS
 - description 225
 - example 226
- MODIFY irlmproc,PURGE command of MVS
 - description 227
 - example 227
- MODIFY irlmproc,SET command of MVS
 - description 228
 - example 230
 - option descriptions 227, 228
- MODIFY irlmproc,STATUS command of MVS
 - description 232
 - example 233
 - option descriptions 232
- MODIFY RECOVERY utility
 - effects of TERM command 336
- MODIFY STATISTICS utility
 - effects of TERM command 336
- MODIFY TRACE command
 - description 238
 - example 239
- MONITOR option
 - DISPLAY TRACE command 167
 - MODIFY TRACE command 238
 - START TRACE command 301
- monitor trace
 - displaying 165
 - starting 299
 - stopping 330
- monitor trace, class descriptions 305
- MSTR option of START DB2 command 284
- MVS
 - commands
 - MODIFY irlmproc,ABEND 223
 - MODIFY irlmproc,DIAG 225
 - MODIFY irlmproc,PURGE 227
 - MODIFY irlmproc,SET 228
 - MODIFY irlmproc,STATUS 232
 - START irlmproc 290
 - STOP irlmproc 324
 - TRACE CT 340

N

- NAMES
 - option of DCLGEN subcommand 86
- naming convention
 - variables in command syntax xv
- network ID (NID) 253
- NID (network ID)
 - option of RECOVER INDOUBT command 253
- NO LIMIT option of SET ARCHIVE command 266
- NO option of START DB2 command 284
- NO option of START irlmproc command 293

- NOBACKOUT
 - option of CANCEL THREAD command 78
- NODEFER option
 - BIND PACKAGE subcommand 50
 - BIND PLAN subcommand 50
 - DSNH command 209
 - REBIND PACKAGE subcommand 50
 - REBIND PLAN subcommand 50
- NODISCON option of START irlmproc command 293
- NODUMP option of MODIFY irlmproc,ABEND command 223
- NOFOR option
 - DSNH command 201
- NONE keyword of MODIFY irlmproc,DIAG command 226
- notices, legal 357
- NOWRAP option of TRACE CT command 341

O

- OASN option
 - CHANGE command 82
 - DISPLAY command 92
- online books 351
- ONLY option of DISPLAY DATABASE command 110
- OP option
 - START TRACE command 302
 - STOP TRACE command 332
- operands
 - DB2 command 4
- OPTHINT option
 - BIND PACKAGE subcommand 66
 - BIND PLAN subcommand 66
 - DSNH command 209
 - REBIND PACKAGE subcommand 66
 - REBIND PLAN subcommand 66
- OPTIONS option
 - BIND PACKAGE subcommand 66
- OPTIONS option of DSNH command 201
- OUTNAME option of DSNH command 201
- OWNER
 - option of BIND PACKAGE subcommand 67
 - option of BIND PLAN subcommand 67
 - option of DCLGEN subcommand 85
 - option of REBIND PACKAGE subcommand 67
 - option of REBIND PLAN subcommand 67
- OWNER option
 - DSNH command 210

P

- P irlmproc command 324
- package
 - binding, initiating 32
 - identifier
 - BIND PACKAGE subcommand 67
 - REBIND PACKAGE subcommand 67
 - REBIND TRIGGER PACKAGE subcommand 249
 - rebinding 240
 - rebinding trigger 248

- package (*continued*)
 - replacing version of 46
- PACKAGE option, DSNH command 212
- PACTION option, DSNH command 210
- parallel processing
 - DEGREE option of bind subcommands 51
 - VPPSEQT option of ALTER BUFFERPOOL command 14
- parameter
 - passing to application program 263
- PARM option of START DB2 command 283
- PARMS option
 - DSNH command 201
 - RUN subcommand 263
- parsing rules
 - commands 3
- PART
 - option of DISPLAY DATABASE command 110
 - option of START DATABASE command 279
 - option of STOP DATABASE command 312
- partial-location name, DISPLAY LOCATION command 144
- PASS option of DSNH command 201
- PATH option
 - BIND PACKAGE subcommand 69
 - BIND PLAN subcommand 69
 - DSNH command 210
 - REBIND PACKAGE subcommand 69
 - REBIND PLAN subcommand 69
- PATHDEFAULT option
 - REBIND PACKAGE subcommand 70
 - REBIND PLAN subcommand 70
- PBIND option, DSNH command 210
- PC option of START irlmproc command 292
- PCICS option, DSNH command 211
- PCLOAD option of DSNH command 201
- PDBPROTOCOL option, DSNH command 211
- PDBRMLIB option, DSNH command 211
- PDEFER option, DSNH command 211
- PDEGREE option, DSNH command 211
- PDISABLE option, DSNH command 211
- PDLIBATCH option, DSNH command 211
- PDMEM option, DSNH command 211
- PDYNAMICRULES option, DSNH command 212
- PENABLE option, DSNH command 212
- PERFM option
 - DISPLAY TRACE command 167
 - MODIFY TRACE command 238
 - START TRACE command 301
 - STOP TRACE command 332
- performance
 - trace
 - class descriptions 304
 - displaying 165
 - starting 299
 - stopping 330
- PFLAG option, DSNH command 212
- PGPROT option of START irlmproc command 292
- PGSTEAL option of ALTER BUFFERPOOL command 15

- phases of execution
 - DSNH processing 189
- PIMSBMP option
 - DSNH command 212
- PIMSMPP option, DSNH command 212
- PISOLATION option, DSNH command 212
- PKEEPDYNAMIC option, DSNH command 212
- PKLIST option
 - BIND PLAN subcommand 70
 - DSNH command 210
 - REBIND PLAN subcommand 70
- PL/I application program
 - macro processing step for DSNH 189
- PLAN
 - option of DSNH command 201, 210
- PLAN
 - BIND PLAN subcommand 71
 - option of DISPLAY TRACE command 168
 - option of DSNH DISPLAY command 180
 - option of RUN subcommand 263
 - option of START TRACE command 303
 - option of STOP TRACE command 333
 - REBIND PLAN subcommand 71
- plan-name naming convention xvii
- PLI option, DCLGEN subcommand 86
- PLI2LIB option of DSNH command 202
- PLIB option of DSNH command 202
- PLILIB option of DSNH command 202
- PLILOAD option of DSNH command 202
- PLOCK keyword of MODIFY irlmproc,DIAG
 - command 225
- PnLIB option of DSNH command 202
- PNODEFER option, DSNH command 212
- POPTHINT option, DSNH command 212
- POPTION option of DSNH command 202
- POSTPONED option of DISPLAY THREAD
 - command 156
- postponed units of recovery
 - recovering 255
- POWNER option, DSNH command 212
- PPATH option, DSNH command 212
- PQUALIFIER option, DSNH command 213
- PRECOMP option of DSNH command 202
- precompiler
 - DSNH command options 201
 - invoking DSNH 189
 - producing members for 65
- PRELEASE option, DSNH command 213
- PRELINK option of DSNH command 202
- PREOPT option, DSNH command 213
- PRINT
 - option of DSNH command 203
- privilege set of a process 1
- process
 - privilege set of 1
- processing
 - parallel, VPPSEQT option of ALTER BUFFERPOOL
 - command 14
- PROGRAM option of RUN subcommand 262
- PSECSPAC option of DSNH command 203
- PSPACE option of DSNH command 203

- PVALIDATE option, DSNH command 213

Q

- QUALIFIER
 - option of BIND PACKAGE subcommand 72
 - option of BIND PLAN subcommand 72
 - option of REBIND PACKAGE subcommand 72
 - option of REBIND PLAN subcommand 72
- qualifier-name naming convention xviii
- QUALIFIER option
 - DSNH command 210
- QUEUE option of STOP FUNCTION SPECIFIC 322
- QUIESCE option
 - DSNC STOP command 186
 - STOP DB2 command 316
 - STOP DDF command 318
- QUIESCE utility
 - effects of TERM command 336
- QUOTE
 - option of DCLGEN subcommand 87
- QUOTE option, DSNH command 199

R

- RATIO option of ALTER GROUPBUFFERPOOL
 - command 20
- RCTERM option of DSNH command 203
- REBIND PACKAGE subcommand of DSN
 - description 240
 - example 243
 - option descriptions 44
- REBIND PLAN subcommand of DSN
 - description 244
 - example 247
 - option descriptions 44
- REBIND TRIGGER PACKAGE subcommand of DSN
 - description 248
 - example 250
 - option descriptions 44
- rebinding
 - initiating 240, 244
 - options for 44
- REBUILD INDEX utility
 - TERM command effects 336
- recognition character 3
- RECOVER BSDS command
 - description 251
 - example 251
- RECOVER INDOUBT command
 - description 252
 - example 254
 - option descriptions 252
- RECOVER POSTPONED command
 - description 255
 - example 256
- RECOVER utility
 - TERM command effects 336
- recovery
 - BSDS 251
 - indoubt threads 252, 254

- recovery (*continued*)
 - postponed units of recovery 255
- REJECT option of STOP FUNCTION SPECIFIC 322
- RELEASE
 - option of BIND PACKAGE subcommand 72
 - option of BIND PLAN subcommand
 - description 72
 - option of DSNH command 210
 - option of REBIND PACKAGE subcommand 72
 - option of REBIND PLAN subcommand 72
 - option of REBIND TRIGGER PACKAGE subcommand 72
- RELOAD option, SET SYSPARM command 268
- REMOTE option, DSNH command 213
- REOPT option
 - BIND PACKAGE subcommand 73
 - BIND PLAN subcommand 73
 - DSNH command 210
 - REBIND PACKAGE subcommand 73
 - REBIND PLAN subcommand 73
- REORG INDEX utility
 - effects of TERM command 336
- REORG TABLESPACE utility
 - effects of TERM command 337
- REPAIR utility
 - effects of TERM command 337
- REPLACE
 - option of DCLGEN subcommand 86
 - option of DSNH command 207
- REPLACE option
 - DSNH command 210
- replacing
 - version of a package 46
- REPLVER option
 - BIND PACKAGE subcommand 45
 - DSNH command 213
 - effect of 46
- REPORT utility
 - effects of TERM command 337
- reports
 - detail report 101
 - group detail report 132
 - member detail report 133
 - summary report
 - DISPLAY BUFFERPOOL command 100
 - DISPLAY GROUPBUFFERPOOL command 131, 137
- RES option of STOP TRACE command 332
- RESET
 - option of CHANGE command 82
- RESET GENERICLU command
 - description 257
 - example 258
 - option descriptions 257
- RESET INDOUBT command
 - description 259
 - option descriptions 260
- restarting
 - CICS attachment facility 186
 - connections between IMS and a subsystem 275
 - status of DB2 resources 283

- restarting (*continued*)
 - utilities
 - terminated job steps 336
- RESTRICT
 - option of DISPLAY DATABASE command 111
- RESUME option
 - SET LOG command 271
- RETAIN option
 - BIND PLAN subcommand 45
 - DSNH command 210
- retained lock 109
- RETRY
 - option of DSN command 176
- return code
 - CURRENTSERVER option of bind and rebind subcommands 49
 - DSN command 177
 - RUN subcommand of DSN 177
- RO option of START DATABASE command 279
- RRSURID option, DISPLAY THREAD command 157
- RUN
 - option of DSNH command parameters 204
 - subcommand of DSN
 - description 262
 - example 264
 - option descriptions 262
 - return codes 177
- RUNIN option of DSNH command 204
- running DSNH processing 189
- RUNOUT option of DSNH command 204
- RUNSTATS utility
 - effects of TERM command 337
- RW option of START DATABASE command 279

S

- scanning rules
 - commands 3
- schema.partial-name* option of DISPLAY FUNCTION SPECIFIC command 122
- schema.partial-name option of START FUNCTION SPECIFIC command 288
- schema.partial-name option of STOP FUNCTION SPECIFIC command 322
- schema.specific-function-name
 - option of DISPLAY FUNCTION SPECIFIC command 122
- schema.specific-function-name option of DISPLAY FUNCTION SPECIFIC command 121
- schema.specific-function-name option of START FUNCTION SPECIFIC command 288
- schema.specific-function-name option of STOP FUNCTION SPECIFIC command 322
- scope of commands 5
- SCOPE option
 - ARCHIVE LOG command 27
 - DISPLAY THREAD command 155
 - of DISPLAY FUNCTION SPECIFIC command 122
 - of DISPLAY PROCEDURE command 149
 - of STOP FUNCTION SPECIFIC command 322
 - of STOP PROCEDURE command 328

SCOPE option (*continued*)
 START FUNCTION SPECIFIC command 288
 START irlmproc command 292
 START PROCEDURE command 295
 START TRACE command 167, 301
 STOP TRACE command 332
secondary authorization ID 1
SET ARCHIVE command
 description 265
 example 266
 option descriptions 265
SET LOG command
 description 270
 example 271
 option descriptions 270
SET SYSPARM command
 description 268
 example 268
 option descriptions 268
SMF option
 DISPLAY TRACE command 168
 START TRACE command 302
 STOP TRACE command 332
softcopy publications 351
SOURCE
 option of DSNH command 204
SPACENAM option
 DISPLAY DATABASE command 108
 START DATABASE command 278
 STOP DATABASE command 312
SPACEUN option of DSNH command 205
special character xv
SPUFI
 description 273
SQL
 option of DSNH command 205
SQLDELIM option of DSNH command 205
SQLERROR
 option of BIND PACKAGE subcommand 74
 option of DSNH command 213
SQLFLAG option
 DSNH command 205
SQLRULES
 option of BIND PLAN subcommand 74
 option of DSNH command 210
 option of REBIND PLAN subcommand 74
SRC (subsystem recognition character) 3
SRV option
 DISPLAY TRACE command 168
 START TRACE command 302
 STOP TRACE command 332
SSR command of IMS
 description 274
START command of IMS 275
START DATABASE command
 description 276
 example 282
 option descriptions 277
 recovering object in group buffer pool 280
 recovering pages on logical page list 280
START DB2 command
 description 283
 example 285
 option descriptions 283
START DDF command 286
START FUNCTION SPECIFIC command
 description 287
 example 289
 option descriptions 288
START irlmproc command of MVS
 description 290
 example 293
 option descriptions 290
START PROCEDURE command
 description 294
 example 296
 option descriptions 295
START RLIMIT command
 description 297
 example 298
START TRACE command
 description 299
 example 308
 option descriptions 300
STARTUP option, SET SYSPARM command 268
STAT option
 DISPLAY TRACE command 167
 MODIFY TRACE command 238
 START TRACE command 301
 STOP TRACE command 332
statistics
 trace
 class descriptions 304
 displaying 165
 starting 299
 stopping 330
STATISTICS option of DSNH DISPLAY command 180
status
 checking, IRLM 232
 cross-system coupling facility (XCF) status of
 members 125
 shown by DISPLAY DATABASE 113
STDSQL option
 DSNH command 206
STOP command of IMS 309
STOP DATABASE command
 description 310
 example 315
 option descriptions 311
STOP DB2 command
 description 316
 example 317
STOP DDF command
 description 318
 example 320
STOP FUNCTION SPECIFIC command
 description 321
 examples 323
 limitations of 322
 option descriptions 322
STOP irlmproc command of MVS 324

- STOP PROCEDURE command
 - description 326
 - example 328
 - option descriptions 327
- STOP RLIMIT command 329
- STOP TRACE command
 - description 330
 - example 334
 - option descriptions 332
- STOR option of MODIFY irlmproc,STATUS command of MVS 233
- stored procedure
 - displaying status 148
 - starting 294
 - stopping 326
- STOSPACE utility
 - effects of TERM command 337
- string
 - delimiter
 - COBOL 87
 - SQL 87
- string option naming convention xviii
- STRUCTURE option of DCLGEN subcommand 87
- SUB option of TRACE CT command 341
- SUBS option of TRACE command 338
- SUBSYS option
 - CHANGE command 82
 - DISPLAY command 92
 - START command 275
 - STOP command 309
- subsystem
 - name
 - naming convention xviii
 - naming convention xviii
- subsystem parameters
 - list 343
 - NPGTHRSH 345
 - PTASKROL 345
- SUFFIX option, DSNH command 206
- summary report
 - DISPLAY BUFFERPOOL command 100
 - DISPLAY GROUPBUFFERPOOL command 131, 137
- SUSPEND option
 - SET LOG command 270
 - STOP DDF command 318
- syntax diagrams, how to read xix
- SYSTEM option
 - DSN command 175
 - DSNH command 206

T

- TABLE
 - option of DCLGEN subcommand 85
- table name
 - naming convention xviii
- table space
 - naming convention xviii
- TDATA option of START TRACE command 306

- TERM option
 - DSNH command 206
- TERM UTILITY command
 - description 335
 - example 337
- terminating
 - connections between IMS and a subsystem 309
 - databases 310
 - DB2
 - description 316
 - IRLM
 - abnormal 223
 - normal 324
 - stored procedures 326
 - trace activity 330
 - utilities
 - description 335
- TEST option
 - DSN command 176
- thread
 - canceling 77
 - displaying
 - DISPLAY THREAD command 153
- TIME option
 - ARCHIVE LOG command 28
 - DSNH command 206
 - SET ARCHIVE command 266
- TIMEOUT option of MODIFY irlmproc,SET command of MVS 229
- TNO option
 - DISPLAY TRACE command 168
 - MODIFY TRACE command 239
- trace
 - changing active traces 238
 - displaying 165
 - events 338
 - IFCIDs activated by trace class 303
 - starting 299
 - stopping 330
- TRACE CT command of MVS
 - description 340
 - example 342
 - option descriptions 340
- TRACE
 - command of IMS
 - description 338
 - example 338
 - option of START TRACE command 306
- TRACE option, START irlmproc command 293
- TRACE option of MODIFY irlmproc,SET command of MVS 229
- TRACE option of MODIFY irlmproc,STATUS command of MVS 233
- TRACK option of DSNH 205
- TRANSACTION option
 - DSNC DISPLAY command 180
 - DSNC MODIFY command 184
- TSO
 - CLISTs
 - DSNH 189, 216
 - TSO option of DSNH command 204

TYPE

- option of DISPLAY GROUPBUFFERPOOL command 130
- option of DISPLAY THREAD command 155

U

- unit of recovery
 - IMS 93
- unit of work
 - displaying an outstanding 92
 - IMS
 - resetting by CHANGE 82
 - indoubt
 - resetting by CHANGE 82
- UNLOAD utility
 - effects of TERM command 337
- USE option of DISPLAY DATABASE command 109
- UT option of START DATABASE command 279
- utilities
 - displaying status 171
 - identifier 336
 - terminating 335
- utility-id naming convention xviii

V

- VALIDATE
 - option of BIND PACKAGE subcommand 75
 - option of BIND PLAN subcommand 75
 - option of REBIND PACKAGE subcommand 75
 - option of REBIND PLAN subcommand 75
- VALIDATE option, DSNH command 210
- VDWQT option of ALTER BUFFERPOOL command 15
- VERSION
 - option of DSNH command 206
- version-id naming convention xviii
- version of a package
 - BIND PACKAGE subcommand 67
 - REBIND PACKAGE subcommand 67
- virtual buffer pool parallel sequential steal threshold (VPSEQT) 14
- virtual buffer pool sequential steal threshold (VPSEQT) 13
- VPPSEQT option of ALTER BUFFERPOOL command 14
- VPSEQT option of ALTER BUFFERPOOL command 13
- VPSIZE option of ALTER BUFFERPOOL command 12
- VPTYPE option of ALTER BUFFERPOOL command 13
- VPXPSEQT
 - option of ALTER BUFFERPOOL command 14
- VSAM (virtual storage access method)
 - password, DCLGEN subcommand 86
- VTAM (Virtual Telecommunications Access Method) commands
 - DISPLAY NET 79

W

- WAIT option
 - ARCHIVE LOG command 28
- WEPR option of DISPLAY DATABASE command 110
- WORKUNIT option of DSNH command 206
- WRAP option of TRACE CT command 340
- WSECPAC option of DSNH command 206
- WSPACE option of DSNH command 206
- WTRSTART option of TRACE CT command 340
- WTRSTOP option of TRACE CT command 341

X

- XCF (cross-system coupling facility) component of MVS
 - status of members 125
- XLIB option of DSNH command 207
- XREF option
 - DSNH command 207

Y

- YES option of START DB2 command 284
- YES option of START irlmproc command 293

Z

- ZPARM 343

Readers' Comments — We'd Like to Hear from You

DB2 Universal Database for OS/390 and z/OS
Command Reference
Version 7

Publication No. SC26-9934-01

Overall, how satisfied are you with the information in this book?

	Very Satisfied	Satisfied	Neutral	Dissatisfied	Very Dissatisfied
Overall satisfaction	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>

How satisfied are you that the information in this book is:

	Very Satisfied	Satisfied	Neutral	Dissatisfied	Very Dissatisfied
Accurate	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Complete	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Easy to find	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Easy to understand	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Well organized	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Applicable to your tasks	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>

Please tell us how we can improve this book:

Thank you for your responses. May we contact you? ☐ Yes ☐ No

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate without incurring any obligation to you.

Name

Address

Company or Organization

Phone No.



Cut or Fold
Along Line

Fold and Tape

Please do not staple

Fold and Tape




NO POSTAGE
NECESSARY
IF MAILED IN THE
UNITED STATES

BUSINESS REPLY MAIL

FIRST-CLASS MAIL PERMIT NO. 40 ARMONK, NEW YORK

POSTAGE WILL BE PAID BY ADDRESSEE

International Business Machines Corporation
Department HHX/H3
PO BOX 49023
SAN JOSE CA
U. S. A.
95161-9023



Fold and Tape

Please do not staple

Fold and Tape

Cut or Fold
Along Line



Program Number: 5675-DB2



Printed in the United States of America
on recycled paper containing 10%
recovered post-consumer fiber.

SC26-9934-01

