

IBM[®] Net.Data



Reference

IBM[®] Net.Data



Reference

Note

Be sure to read the information in "Notices" on page 331 before using this information and the product it supports.

March 2001 Edition

This edition applies to IBM Net.Data for OS/390, a feature of Version 7 of DB2 Universal Database Server for OS/390 (DB2 UDB for OS/390), and to all subsequent releases and modifications until otherwise indicated in new editions.

© **Copyright International Business Machines Corporation 1997, 2001. All rights reserved.**

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

Preface	vii
About Net.Data	vii
About This Book	vii
Who Should Read This Book	viii
About Examples in This Book	viii
How to Read the Syntax Diagrams	viii
How to send your comments	x

Chapter 1. Net.Data Macro Language

Constructs	1
Net.Data Macro Syntax	1
Common Syntax Elements	4
Variable Name	4
Variable Reference	4
Strings	5
Macro Language Constructs	6
Comment Block	8
DEFINE Block or Statement	10
ENVVAR Statement	14
EXEC Block or Statement	15
FUNCTION Block	17
Function Call (@)	24
HTML Block	27
IF Block	29
INCLUDE Statement	35
LIST Statement	37
MACRO_FUNCTION Block	39
MESSAGE Block	43
REPORT Block	47
ROW Block	49
TABLE Statement	51
WHILE Block	53
XML Block	56

Chapter 2. Variables 59

User-defined Variables	60
Conditional Variables	60
Environment Variables	61
Executable Variables	61
Hidden Variables	62
List Variables	63
Table Variables	64
Net.Data Table Processing Variables	65
Nn	66
NLIST	67
NUM_COLUMNS	68
NUM_ROWS	69
ROW_NUM	70
TOTAL_ROWS	71
V_columnName	72
VLIST	73
Vn	74
Net.Data Report Variables	74
ALIGN	75
DTW_DEFAULT_REPORT	76

DTW_HTML_TABLE	77
RPT_MAX_ROWS	78
START_ROW_NUM	79
Net.Data Language Environment Variables	80
DATABASE	81
DB_CASE	83
DB2PLAN	84
DB2SSID	85
DTW_APPLET_ALTTEXT	86
DTW_EDIT_CODES	87
DTW_PAD_PGM_PARMS	88
DTW_SAVE_TABLE_IN	89
DTW_SET_TOTAL_ROWS	90
LOCATION	91
LOGIN	92
NULL_RPT_FIELD	93
PASSWORD	94
SHOWSQL	95
SQL_STATE	96
TRANSACTION_SCOPE	97
Net.Data Miscellaneous Variables	98
DTW_CURRENT_FILENAME	99
DTW_CURRENT_LAST_MODIFIED	100
DTW_DEFAULT_MESSAGE	101
DTW_LOG_LEVEL	102
DTW_MACRO_FILENAME	103
DTW_MACRO_LAST_MODIFIED	104
DTW_MBMODE	105
DTW_MP_PATH	106
DTW_MP_VERSION	107
DTW_PRINT_HEADER	108
DTW_REMOVE_WS	109
DTW_USE_DB2_PREPARE_CACHE	110
RETURN_CODE	112

Chapter 3. Net.Data Built-in Functions 113

Function Names	113
Input and Output Parameters	113
Function Result Formatting	114
Function Parameter Rules	114
General Functions	114
DTW_ADDQUOTE	116
DTW_CACHE_PAGE	118
DTW_DATE	122
DTW_EXIT	124
DTW_GETCOOKIE	125
DTW_GETENV	127
DTW_GETINIDATA	128
DTW_HTMLLENCODE	129
DTW_LOG_ERRORMSG	131
DTW_LOG_TRACEMSG	132
DTW_QHTMLLENCODE	133
DTW_SENMAIL	134
DTW_SETCOOKIE	139
DTW_SETENV	143

DTW_TIME	145
DTW_URLESCSEQ	147
Math Functions.	148
DTW_ADD	150
DTW_DIVIDE	152
DTW_DIVREM	154
DTW_FORMAT	156
DTW_INTDIV	159
DTW_MULTIPLY	161
DTW_POWER	163
DTW_SUBTRACT	165
String Functions	166
DTW_ASSIGN	168
DTW_CHARTOHEX	169
DTW_CONCAT	170
DTW_DELSTR	171
DTW_HEXTOCHAR	173
DTW_INSERT	174
DTW_LASTPOS	176
DTW_LENGTH	178
DTW_LOWERCASE	179
DTW_POS	181
DTW_REPLACE	183
DTW_REVERSE	185
DTW_STRIP	186
DTW_SUBSTR	188
DTW_TRANSLATE	190
DTW_UPPERCASE	192
Word Functions	193
DTW_DELWORD	194
DTW_SUBWORD	196
DTW_WORD	198
DTW_WORDINDEX	199
DTW_WORDLENGTH	200
DTW_WORDPOS	201
DTW_WORDS	203
Table Functions.	203
DTW_TB_APPENDROW	205
DTW_TB_COLS	207
DTW_TB_DELETECOL	208
DTW_TB_DELETEROW	209
DTW_TB_DLIST	211
DTW_TB_DUMP	213
DTW_TB_DUMPV	214
DTW_TB_GETN	216
DTW_TB_GETV	218
DTW_TB_HTMLLENCODE	220
DTW_TB_INPUT_CHECKBOX	222
DTW_TB_INPUT_RADIO	224
DTW_TB_INPUT_TEXT	226
DTW_TB_INSERTCOL	228
DTW_TB_INSERTROW	229
DTW_TB_LIST	231
DTW_TB_QUERYCOLNONJ	233
DTW_TB_ROWS	235
DTW_TB_SELECT	236
DTW_TB_SETCOLS	238
DTW_TB_SETN	239
DTW_TB_SETV	241
DTW_TB_TABLE	243
DTW_TB_TEXTAREA	245

Flat File Interface Functions	246
Access to Flat File Data Sources	246
Flat File Interface Delimiters	248
Locking Files	249
DTWF_APPEND	250
DTWF_CLOSE	253
DTWF_COPY	254
DTWF_DELETE	255
DTWF_EXISTS	257
DTWF_INSERT	258
DTWF_OPEN	261
DTWF_READ	263
DTWF_READFILE	266
DTWF_REMOVE	268
DTWF_SEARCH	270
DTWF_UPDATE	273
DTWF_WRITE	276
DTWF_WRITEFILE	279
Web Registry Functions	280
DTWR_ADDENTRY	281
DTWR_CLEARREG	283
DTWR_CLOSEREG	284
DTWR_CREATEREG	285
DTWR_DELENTY	287
DTWR_DELREG	289
DTWR_LISTREG	290
DTWR_LISTSUB	292
DTWR_OPENREG	294
DTWR_RTVENTRY	295
DTWR_UPDATEENTRY	297
Persistent Macro Functions	298
DTW_ACCEPT	299
DTW_COMMIT	301
DTW_ROLLBACK	302
DTW_RTVHANDLE	303
DTW_STATIC	304
DTW_TERMINATE	306
Java Applet Functions	306
Configuring the Java Applet Language Environment	307
Creating Java Applets	307
Generating the Applet Tags.	307
Java Applet Example	310
Using the Net.Data Java Applet Interface	311

Appendix A. Net.Data Technical Library 315

Appendix B. Deprecated Features . . 317

EXEC_SQL	317
HTML_INPUT	317
HTML_REPORT	317
INCLUDE_URL	317
SQL	317
SQL_MESSAGE	318
SQL_REPORT	318
SQL_CODE	318

Appendix C. Net.Data Operating System Reference 319

Notices	331
Trademarks	332

Index	335
------------------------	------------

Preface

Thank you for selecting Net.Data®, the IBM® development tool for creating dynamic Web pages! With Net.Data you can rapidly develop Web pages with a dynamic content by incorporating data from a variety of data sources and by using the power of programming languages you already know.

About Net.Data

With IBM's Net.Data product, you can create dynamic Web pages using data from both relational and non-relational database management systems (DBMSs), including DB2, IMS, ODBC-enabled databases, and databases that can be accessed through DRDA, and using applications written in programming languages such as Java, JavaScript, Perl, C, C++, and REXX. The Net.Data family of products provides similar capabilities on machines executing the Windows NT, AIX, OS/2, OS/390, OS/400, HP-UX, PTX, Linux, and Sun Solaris operating systems.

Net.Data is a macro processor that executes as middleware on a Web server machine. You can write Net.Data application programs, called *macros*, that Net.Data interprets to create dynamic Web pages with customized content based on input from the user, the current state of your databases, other data sources, existing business logic, and other factors that you design into your macro.

A request, in the form of a URL (uniform resource locator), flows from a browser, such as Netscape Navigator or Internet Explorer, to a Web server that forwards the request to Net.Data for execution. Net.Data locates and executes the macro, and builds a Web page that it customizes based on functions that you write. These functions can:

- Encapsulate business logic within applications written in, but not limited to, C, C++, RPG, COBOL, Java, Perl, or REXX programming languages
- Access databases such as DB2
- Access other data sources such as flat files

Net.Data passes this Web page to the Web server, which in turn forwards the page over the network for display at the browser.

Net.Data can be used in server environments that are configured to use interfaces such as HyperText Transfer Protocol (HTTP) and Common Gateway Interface (CGI). HTTP is an industry-standard interface for interaction between a browser and Web server, and CGI is an industry-standard interface for Web server invocation of gateway applications like Net.Data. These interfaces allow you to select your favorite browser or Web server for use with Net.Data.

For improved performance, Net.Data supports a variety of Web server Application Programming Interfaces (APIs). In addition, Net.Data can be launched as a Java servlet.

About This Book

This book explains the syntax and usage of Net.Data language constructs, variables, and functions.

This book might refer to products or features that are announced, but not yet available.

More information, sample Net.Data macros, demos, and the latest copy of this book, is available from the following World Wide Web sites:

- <http://www.ibm.com/software/data/net.data>
- <http://www.as400.ibm.com/netdata>

Throughout this book, there are tables containing 'X's to indicate on which operating system a particular feature of Net.Data is available.

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X			X	X	X	

The abbreviations in the table represent the following operating systems.

AIX	IBM Advanced Interactive Executive
HP-UX	Hewlett Packard UNIX
Linux	Open Source Linux
OS/2	IBM OS/2
OS/390	IBM OS/390
OS/400	IBM OS/400
PTX	IBM/Sequent DYNIX/ptx
SUN	Sun Solaris
Win NT	Microsoft Windows NT

See “Appendix C. Net.Data Operating System Reference” on page 319 for an overview of what is supported on each platform.

Who Should Read This Book

People involved in planning and writing Net.Data applications can use the information in this book to understand what language constructs, variables, and functions Net.Data provides.

To understand the concepts discussed in this book, you should be familiar with Web servers, simple SQL statements, and HTML (including using HTML forms), and the information in *Net.Data Administration and Programming Guide*.

About Examples in This Book

Examples used in this book are kept simple to illustrate specific concepts. The examples are not intended to show all of the ways in which Net.Data constructs can be used. Likewise, some of the examples are fragments of code that cannot be executed by themselves.

How to Read the Syntax Diagrams

The following rules apply to the syntax diagrams used in this book:

- Read the syntax diagrams from left to right, from top to bottom, following the path of the line.

The ►— symbol indicates the beginning of a statement.


The \longrightarrow symbol indicates that the statement syntax is continued on the next line.

The \blacktriangleright — symbol indicates that a statement is continued from the previous line.

The $\longrightarrow\blacktriangleleft$ symbol indicates the end of a statement.

Diagrams of syntactical units other than complete statements start with the \blacktriangleright — symbol and end with the \longrightarrow symbol.


- Required items appear on the horizontal line (the main path).




- Optional items appear below the main path.




If an optional item appears above the main path, that item has no effect on the execution of the statement and is used only for readability.




- If you can choose from two or more items, they appear vertically, in a stack. If you *must* choose one of the items, one item of the stack appears on the main path.




If choosing one of the items is optional, the entire stack appears below the main path.




If one of the items is the default, it appears above the main path and the remaining choices are shown below.



- An arrow returning to the left, above the main line, indicates an item that can be repeated.



If the repeat arrow contains punctuation, you must separate repeated items with the specified punctuation.



A repeat arrow above a stack indicates that you can repeat the items in the stack.

- Keywords appear in uppercase (for example, FROM). In Net.Data, keywords can be in any case. Terms that are not keywords appear in lowercase letters (for example, *column-name*). They represent user-supplied names or values.
- If punctuation marks, parentheses, arithmetic operators, or other such symbols are shown, you must enter them as part of the syntax.

How to send your comments

Your feedback helps IBM to provide quality information. Please send any comments that you have about this book or other DB2 documentation. You can use any of the following methods to provide comments:

- Send your comments by e-mail to db2pubs@vnet.ibm.com and include the name of the product, the version number of the product, and the number of the book. If you are commenting on specific text, please list the location of the text (for example, a chapter and section title, page number, or a help topic title).
- Send your comments from the Web. Visit the Web site at:

<http://www.ibm.com/software/db2os390>

The Web site has a feedback page that you can use to send comments.

- Complete the readers' comment form at the back of the book and return it by mail, by fax (800-426-7773 for the United States and Canada), or by giving it to an IBM representative.

Chapter 1. Net.Data Macro Language Constructs

This chapter describes the Net.Data macro syntax and the language constructs used in the Net.Data macro. The language constructs consist of a keyword and a statement or block in the Net.Data macro, specify different variable types, and perform other special tasks such as including files.

This chapter describes:

- “Net.Data Macro Syntax”
- “Common Syntax Elements” on page 4
- “Macro Language Constructs” on page 6


Net.Data Macro Syntax

A Net.Data macro is a text file consisting of a series of Net.Data macro language constructs that:

- Specify the layout of Web pages
- Define variables and functions
- Call functions that are defined in the macro or that Net.Data passes to language environments for processing

Each statement is composed of one or more language constructs, which in turn are composed of keywords, special characters, strings, names, and variables. The following diagram depicts the global structure of a syntactically valid Net.Data macro. See “Macro Language Constructs” on page 6 for detailed syntax of each element in the global structure.

The Net.Data macro contains two parts: declaration and presentation part. You can



use these parts multiple times and in any order.

- *Declaration part* contains the definitions of variables and functions in the macro.
- *Presentation part* contains HTML or XML blocks that contain statements that specify the layout of the generated document. This part includes the report section.

Figure 1 shows the declaration and presentation parts of the macro.




Figure 1. Sample macro structure

Variables and functions that are used in the declaration or generation part must be defined before being used by a variable reference or a function call.

Figure 2 on page 3 demonstrates the parts of a macro. The declaration part contains the DEFINE and FUNCTION definition blocks. The HTML and XML blocks act as entry points.

```

%{ ***** Define block *****}
%DEFINE {
    page_title="Net.Data macro Template"
%}

%{ ***** Function Definition block *****}
%FUNCTION(DTW_REXX) rexx1 (IN input) returns(result)
    { %EXEC{ompsamp.cmd %}
%}

%FUNCTION(DTW_REXX) today () RETURNS(result)
    {
        result = date();
%}

%{ ***** HTML Block: Input *****}
%HTML (Input) {
<HTML>
<head>
<title>$(page_title)<title>
</head><body>
<h1>Input Form</h1>
Today is @today()

<form method="post" action="output">
Type some data to pass to a REXX program:<br />
<input name="input_data" type="text" size="30" /><br />
<input type="submit" value="enter" /><br />
<hr />
<p>[<a href="/">Home page </a>] </p>
</form>
</body></HTML>
%}

%{ ***** HTML Block: Output *****}
%HTML (Output) {
<HTML>
<head>
<title>$(page_title)</title>
</head><body>
<h1>Output Page</h1>
<p>@rexx1(input_data)</p>
<hr />
<p>[<a href="/">Home page</a> |
<a href="input">Previous page</a>]</p>
</body></HTML>
%}

```

Figure 2. The Macro Template Format

The Net.Data macro language is a free-form language, giving you flexibility for writing your macros. Unless specifically noted, extra white space characters are ignored. Each of the Net.Data macro language constructs is described in the following section, along with several other elements that are used to define the constructs. The Net.Data macro language supports DB2 WWW Connection language elements for backward compatibility. Although these language elements are described in “Appendix B. Deprecated Features” on page 317, it is recommended that you use the Net.Data language constructs.

The examples show some of the ways you can use the language constructs, variables, functions, and other elements in your macros. You can download the samples and demos from the Net.Data Web pages for more extensive examples:

- <http://www.ibm.com/software/data/net.data/>
- <http://www.as400.ibm.com/netdata>

Common Syntax Elements

The following syntax elements are used frequently in the language construct descriptions:

- “Variable Name”
- “Variable Reference”
- “Strings” on page 5

Variable Name

Purpose:

Identifies a variable. A variable is an object whose value can change during the execution of a macro.

Variable names must begin with a letter or underscore (`_`) and contain any alphanumeric characters, underscores, hash marks (`#`), or periods (`.`). All variable names are case sensitive except `V_columnName` (See “Net.Data Table Processing Variables” on page 65 for more information about these two exceptions.).

Variable Reference

Purpose:


Returns the value of a variable and is specified with `$` and `()`. For example: if `VAR = 'front'`, `$(VAR)` returns the value 'front'. Variable references are evaluated during run time. When a variable is defined for an EXEC statement or block, Net.Data runs the specified action when it reads the variable reference.

You can dynamically generate a variable reference by including variable references, strings, and function calls within a variable reference. For example: if `frontside = 'blue'`, `$($(VAR)side)` returns the value 'blue'. If you reference a dynamically-generated variable that does not follow the variable name rules, Net.Data resolves the reference to an empty string.

Restrictions::

- Net.Data strings are terminated by NULL characters (binary zeroes). If your data source returns data containing the NULL character, Net.Data will terminate the string stored in the variable at that point in the data stream.
- Variable references cannot be used as an OUT parameter to a function call.
- Leading and trailing whitespace is ignored.
- Whitespace (including a newline character) is not allowed between function calls, strings, and variable references.
- A variable reference returns an empty string if any whitespace exists within the name of the variable.

Syntax:



Notes:

- 1 String can contain only the characters that are allowed in variable names: alphanumeric characters, underscores (`_`), hash marks (`#`), or periods (`.`).

Example 1: Variable reference

If you have defined a variable `homeURL`:

```
%DEFINE homeURL="http://www.ibm.com/"
```

You can refer to the homepage as `$(homeURL)` and create a link:

```
<a href="$(homeURL)">Home page</a>
```

Example 2: Dynamically-generated variable reference

You can dynamically generate variable references that in turn dynamically reference a field value in a row:

```
%define{
var1="value1"
var2="value2"
var3="value3"
@DTW_ASSIGN (INDEX, "1")
%}
%WHILE (INDEX < 3) {
$(var$(INDEX))
@DTW_ADD(INDEX, "1", INDEX)
%}
```

Returns:

```
value1
value2
value3
```

Example 3: A dynamic variable reference with nested variable references and a function call

```
%define my = "my"
%define u = "lower"
%define myLOWERvar = "hey"

$($(my)@dtw_ruppercase(u)var)
```

The variable reference returns the value of `hey`.

Strings

Any sequence of alphabetic and numeric characters and punctuation. If the string appears within double quotes, the new-line character is not allowed. See the string parameter description in each language construct for restrictions when used with the language construct.

Strings in quotes (""), can contain any character except the new-line character. If the string is in brackets, ({ %}), it can contain any character including the new-line character. For example,

```
%define multiline = {  
first line  
second line  
%}
```

To specify double quotes inside a quoted string, use two pairs of double quotes. A string used as function argument or as term in a comparison expression can contain double quotes. For example, if you define a string value as:

```
%DEFINE result = " ""Hello world!"" "
```

The value of *result* is:

```
"Hello world!"
```

A presentation statement is a string.

Strings used as function arguments, terms, and variable values can contain variable references and function calls. In the following example, the function call `myfunc2` has a string parameter that contains a variable reference and a function call.

```
%HTML(report) {  
  @myfunc2("abc$(var1)@myfunc()")  
%}
```

Net.Data resolves the variable reference `$(var1)` and the function call `@myfunc()`, rather than interpreting them literally as part of the string, before passing the string to the function `myfunc2`.

Macro Language Constructs

This section describes the language constructs used in the Net.Data macro.

Each language construct description can contain the following information:

Purpose

Defines why you use the language construct in the Net.Data macro.

Syntax

Provides a diagram of the language construct's logical structure.

Parameters

Defines all the elements in the syntax diagram and provides cross references to other language constructs' syntax and examples.

Context

Explains where in the Net.Data macro structure the language construct can be used.

Restrictions

Defines which elements it can contain and specifies any usage restrictions.

Examples

Provides simple examples and explanations for using the keyword statement or block within the Net.Data macro.

The following constructs are used in the macro; please refer to each constructs description for syntax and examples.

- "Comment Block" on page 8

- “DEFINE Block or Statement” on page 10
- “ENVVAR Statement” on page 14
- “EXEC Block or Statement” on page 15
- “FUNCTION Block” on page 17
- “Function Call (@)” on page 24
- “HTML Block” on page 27
- “IF Block” on page 29
- “INCLUDE Statement” on page 35
- “LIST Statement” on page 37
- “MACRO_FUNCTION Block” on page 39
- “MESSAGE Block” on page 43
- “REPORT Block” on page 47
- “ROW Block” on page 49
- “TABLE Statement” on page 51
- “WHILE Block” on page 53
- “XML Block” on page 56

Comment Block

Purpose

Documents the functions of the Net.Data macro. Because the COMMENT block can be used anywhere in the macro, it is not documented in the other syntax diagrams.

The COMMENT block can also be used in the Net.Data initialization file.

Syntax

►► `%{—text—%}` 

Values

text Any string on one or more lines. Net.Data ignores the contents of all comments.

Context

Comments can be placed anywhere between Net.Data language constructs in a Net.Data macro or the Net.Data initialization file

Restrictions

Any text or characters are allowed; however, comment blocks cannot be nested.

Examples

Example 1: A basic comment block

```
%{  
This is a comment block. It can contain any number of lines  
and contain any characters. Its contents are ignored by Net.Data.  
%}
```

Example 2: Comments in a FUNCTION block

```
%function(DTW_REXX) getAddress(IN name,  %{ customer name %}  
                                IN phone, %{ customer phone number %}  
                                OUT address %{ customer address %}  
                                )  
  
{  
    ....  
%}
```

Example 3: Comments in an HTML block

```
%HTML(report) {  
  
    %{ run the query and save results in a table %}  
    @myQuery(resultTable)  
  
    %{ build a form to display a page of data %}  
    <form method="POST" action="report">  
  
    %{ send the table to a REXX function to send the data output %}  
    @displayRows(START_ROW_NUM, submit, resultTable, RPT_MAX_ROWS)  
  
    %{ pass START_ROW_NUM as a hidden variable to the next invocation %}  
    <input name="START_ROW_NUM" type="hidden" value="$(START_ROW_NUM)" />  
  
    %{ build the next and previous buttons %}  
    %if (submit == "both" || submit == "next_only")  
        <input name="submit" type="submit" value="next" />
```

```

    %endif
    %if (submit == "both" || submit == "prev_only")
        <input name="submit" type="submit" value="previous" />
    %endif
</form>
%}

```

Example 4: Comments in a DEFINE block

```

%define {
    START_ROW_NUM = "1"           %{ starting row number for output table %}
    RPT_MAX_ROWS = "25"          %{ maximum number of rows in the table %}
    resultTable = %table          %{ table to hold query results %}
%}

```

Example 5: Comments in the Net.Data initialization file

```

...
%{ restrict for general use %}
    DTW_DIRECT_REQUEST no
...

```

DEFINE Block or Statement


Purpose

The DEFINE section defines variables names in the declaration part of the macro and can be either a statement or a block.


- Use statements to define one variable at a time
- Use blocks to define several variables

The variable definition can be on a single line, using double quotes (""), or can span multiple lines, using brackets and a percent sign ({ %}). After the variable is defined, you can reference it anywhere in the macro.



Syntax




define entry:



conditional variable:



abbreviated conditional variable:



Notes:

- 1 **STATIC** and **TRANSIENT** are keywords for persistent macros, which are currently available on the OS/400 operating system, only.

Values

%DEFINE

A keyword that defines variables.

STATIC

A keyword that specifies that the variable retains its value across macro invocations within a persistent transaction. This is the default for persistent macros.

TRANSIENT

A keyword that specifies that this variable does not retain its value across macro invocations. This is the default for non-persistent macros.

define entry:

variable name

A name that identifies a variable. See “Variable Name” on page 4 for syntax information.

string

Any sequence of alphabetic and numeric characters and punctuation. If the string appears within double quotes, the new-line character is not allowed.

variable reference

Returns the value of a variable and is specified with \$ and (). For example: if VAR='abc', then \$(VAR) returns the value 'abc'. See “Variable Reference” on page 4 for syntax information.

function call

Invokes one or more FUNCTION or MACRO_FUNCTION blocks, or a Net.Data built-in function with specified arguments. See “Function Call (@)” on page 24 for syntax and examples.

exec statement

The EXEC statement. The name of an external program that executes when a variable is referenced or a function is called. See “EXEC Block or Statement” on page 15 for syntax and examples.

table statement

The TABLE statement. Defines a collection of related data containing an array of identical records, or rows, and an array of column names describing the fields in each row. See “TABLE Statement” on page 51 for syntax and examples.

envvar statement

The ENVVAR statement. Refers to environment variables. See “ENVVAR Statement” on page 14 for syntax and examples.

conditional variable

Sets the value of a variable based on whether another variable or string is empty.

abbreviated conditional variable

Sets the value of a variable based on whether another variable or string is empty. A shorter form of the conditional variable.

list statement

The LIST statement. Defines variables that are used to build a delimited list of values. See “LIST Statement” on page 37 for syntax and examples.

include statement

The INCLUDE statement. Reads and incorporates a file into the Net.Data macro. See “INCLUDE Statement” on page 35 for syntax and examples.

Context

The DEFINE block or statement must be in an IF block or outside all other blocks in the declaration part of the Net.Data macro.

Restrictions

- Can contain the following elements:
 - Comment block

- Conditional variables
 - LIST statement
 - TABLE statement
 - Variable references
 - INCLUDE statement
 - EXEC statement
 - Function calls
 - ENVVAR statement
- You cannot use a variable in its own definition. For example, the following variable definition is not allowed:

```
%DEFINE var = "The value is $(var)."
```

Examples

Example 1: Simple variable definitions

```
%DEFINE var1 = "orders"
%DEFINE var2 = "${var1}.html"
```

During run time, the variable reference `$(var2)` is evaluated as `orders.html`.

Example 2: Quotes inside a string

```
%DEFINE hi = "say "hello""
%DEFINE empty = ""
```

When displayed, the variable `hi` has the value `say "hello"`. The variable `empty` contains the empty string.

Example 3: Definition of multiple variables

```
%DEFINE{ DATABASE = "testdb"
         home = "http://www.ibm.com/software"
         SHOWSQL = "YES"
         PI = "3.14150"
}%
```

Example 4: Multiple-line definition of a variable

```
%DEFINE text = {This variable definition
               spans two lines
}%
```

Example 5: This example of a conditional variable demonstrates how the variable `var` takes the resulting value inside the quotations marks (") if the resulting value does not contain any NULL values.

```
%DEFINE var = ? "Hello! $(V)@MyFunc()"
%}
```

ENVVAR Statement

Purpose

Defines a variable as an environment variable in the DEFINE block. When the ENVVAR variable is referenced, Net.Data returns the current value of the environment variable by the same name.

Syntax

►►—%ENVVAR—◄◄

Context

The ENVVAR statement can be in the DEFINE block or statement.

Values

%ENVVAR

The keyword for defining a variable as an environment variable in a DEFINE block. This variable gets the value of an environment variable anywhere in the macro.

Restrictions

The ENVVAR statement can contain no other elements.

Examples

Example 1: In this example, ENVVAR defines a variable, which when referenced, returns the current value for the environment variable SERVER_SOFTWARE, the name of the Web server.

```
%DEFINE SERVER_SOFTWARE = %ENVVAR

%HTML (Report){
The server is $(SERVER_SOFTWARE).
%}
```

EXEC Block or Statement

Purpose

Specifies an external program to execute when a variable is referenced or a function is called.

When Net.Data encounters an executable variable in a macro, it looks for the referenced executable program using the following method:


1. It searches the EXEC_PATH in the Net.Data initialization file. See the configuration chapter in *Net.Data Administration and Programming Guide* for your operating system for more information about EXEC_PATH.
2. If Net.Data does not locate the program, it searches the directories defined by the system. If it locates the executable program, Net.Data runs the program.

Authorization Tip: Ensure that the user ID under which Net.Data executes has access rights to any files referenced by the EXEC statement or block. See the section on specifying Web server access rights to Net.Data files in the configuration chapter of *Net.Data Administration and Programming Guide* for your operating system for more information.


The EXEC statement and block are used in two different contexts and have different syntax, depending where they are used. Use the EXEC statement in the DEFINE block, and use the EXEC block in the FUNCTION block.

Syntax

The EXEC statement syntax when used in the DEFINE block:



The EXEC block syntax when used in the FUNCTION block:



Values

`%EXEC`

The keyword that specifies the name of an external program to be executed when a variable is referenced or when a function is called. When Net.Data encounters a variable reference that is defined in an EXEC statement, it processes what the EXEC statement declares for the variable.

`string`

Any sequence of alphabetic and numeric characters and punctuation. If the string appears within double quotes, the new-line character is not allowed.

variable reference

Returns the value of a variable and is specified with \$ and (). For example: if VAR='abc', then \$(VAR) returns the value 'abc'. See “Variable Reference” on page 4 for syntax information.

function call

Invokes one or more FUNCTION or MACRO_FUNCTION blocks, or a Net.Data built-in function with specified arguments. See “Function Call (@)” on page 24 for syntax and examples.

Context

The EXEC block or statement can be found in these contexts:

- DEFINE block
- FUNCTION block

Restrictions

The EXEC block or statement can contain these elements:

- Comment block
- String
- Variable references
- Function call

The following Net.Data-provided language environments support the EXEC statement:

- REXX
- System
- Perl

Examples**Example 1:** Executable file referenced by a variable

```
%DEFINE mycall = %EXEC "MYEXEC.EXE $(empno)"
```

```
%HTML (Report) {
  <p>Here is the report you requested:</p>
  <hr />$(mycall)
%}
```

This example executes MYEXEC.EXE on every reference to the variable, mycall.

Example 2: Executable file referenced by a function

```
%FUNCTION(DTW_REXX) my_rexx_pgm(INOUT a, b, IN c, INOUT d){
  %EXEC{ mypgm.cmd this is a test %}
%}
```

This example executes mypgm.cmd when the function my_rexx_pgm is called.

FUNCTION Block

Purpose

Defines a subroutine that Net.Data invokes from the macro. The executable statements in a FUNCTION block can be inline statements directly interpreted by a language environment, or they can be a call to an external program.

EXEC Blocks in Function Blocks: If you use the EXEC block within the FUNCTION block, it must be the only executable statement in the FUNCTION block. Before passing the executable statement to the language environment, Net.Data appends the file name of the program in the EXEC block to a path name determined by the EXEC_PATH path configuration statement in the initialization file. The resulting string is passed to the language environment to be executed.

The method that the language environment uses to process the EXEC block depends on the particular language environment; the REXX, System, and Perl Net.Data-provided language environments support the EXEC block.

Using Special Characters in Language Statements: When characters that match Net.Data language constructs syntax are used in the language statements section of a function block as part of syntactically valid embedded program code (such as REXX or Perl), they can be misinterpreted as Net.Data language constructs, causing errors or unpredictable results in a macro.

For example, a Perl function might use the COMMENT block delimiter characters, `%{`. When the macro is run, the `%{` characters are interpreted as the beginning of a COMMENT block. Net.Data then looks for the end of the COMMENT block, which it thinks it finds when it reads the end of the function block. Net.Data then proceeds to look for the end of the function block, and when it can't be found, issues an error.

Use one of the following methods to use Net.Data special characters as part of your embedded program code, without having them interpreted by Net.Data as special characters:

- Use the EXEC statement to call the program code, rather than putting the code inline.
- Use a variable reference to specify the special characters.

For example, the following Perl function contains characters representing a COMMENT block delimiter, `%{`, as part of its Perl language statements:

```
%function(DTW_PERL) func() {  
    ...  
    for $num_words (sort bynumber keys %{ $Rtitles{$num} }) {  
        &make_links($Rtitles{$num}{$num_words});  
    }  
    ...  
    %}
```

To ensure that Net.Data interprets the `%{` characters as Perl source code rather than as a Net.Data COMMENT block delimiter, rewrite the function in either of the following ways:

- Use the %EXEC statement:

```
%function(DTW_PERL) func() {  
    %EXEC{ func.pr1 %}  
    %}
```
- Use a variable reference to specify the `%{` characters:


```

%define percent_openbrace = "%{"


%function(DTW_PERL) func() {
...
  for $num_words (sort bynumber keys $(percent_openbrace) $Rtitles{$num} }) {
    &make_links($Rtitles{$num}{$num_words});
  }
...
%}

```


Syntax



parm passing spec:




returns spec:



function body:





Notes:

- 1 The default parameter type of IN applies when no parameter type is specified at the beginning of the parameter list. A parameter without a parameter type uses the type most recently specified in the parameter list, or type IN if no type has been specified. For example, in the parameter list (*parm1*, INOUT *parm2*, *parm3*, OUT *parm4*, *parm5*), parameters *parm1*, *parm3*, and *parm5* do not have parameter types. The parameter *parm1* has a type of IN because no initial parameter type has been specified. The parameter *parm3* has a type of INOUT because it is the most recently specified parameter type. Similarly, the parameter *parm5* has a type of OUT because it is the most recently specified type in the parameter list.
- 2 The repeated report block is valid for:
 - SQL and ODBC language environments when processing stored procedures that return multiple result sets for the OS/390 operating systems.
 - Functions calling any language environment for the OS/400, OS/2, Windows NT, and UNIX operating systems.

Values

%FUNCTION

The keyword that specifies a subroutine that Net.Data invokes from the macro.

lang_env

The language environment that processes the function body. See the *Net.Data Administration and Programming Guide* for more information.

function_name

The name of the function being defined that can be an alphabetic or numeric string that begins with an alphabetic character or underscore and contains any combination of alphabetic, numeric, underscore, or period characters.

parm passing spec:

IN Specifies that Net.Data passes input data to the language environment. IN is the default.

OUT

Specifies that the language environment returns output data to Net.Data.

INOUT

Specifies that Net.Data passes input data to the language environment and the language environment returns output data to Net.Data.

datatype

Specifies the datatype of the parameter. For a list of supported datatypes for stored procedures, see the operating system appendix of *Net.Data Reference*.

name

An alphabetic or numeric string beginning with an alphabetic character or underscore and containing any combination of alphabetic, numeric, underscore, or period characters.

returns spec:**RETURNS**

Declares the variable that contains the function value assigned by the language environment, after the function completes.

function body:**inline statement block**

Syntactically valid statements from the language environment specified in the function definition, for example; REXX, SQL, or Perl. See *Net.Data Administration and Programming Guide* for a description of the language environment you are using. See the programming language's programming reference for syntax and usage. The string representing the inline statement block can contain Net.Data variable references and function calls, which get evaluated before execution of the inline statement block (program).

exec block

The EXEC block. The name of an external program that executes when the function is called. See "EXEC Block or Statement" on page 15 for syntax and examples.

report block

The REPORT block. Formatting instructions for the output of a function call. You can use header and footer information for the report. See "REPORT Block" on page 47 for syntax and examples.

message block

The MESSAGE block. A set of return codes, the associated messages, and the actions Net.Data takes when a function call is returned. See "MESSAGE Block" on page 43 for syntax and examples.

Context

The FUNCTION block can be found in these contexts:

- IF block
- Outside of any block or statement in the declaration part of the Net.Data macro.

Restrictions

- The FUNCTION block can contain these elements:
 - Comment block
 - EXEC block
 - MESSAGE block
 - REPORT block
 - Inline statement blocks
- SQL statements in the inline statement block can have the following lengths. Your database might have different restrictions; refer to your database documentation to determine if your database has a smaller restriction. IBM DB2 database restrictions are listed below, if they are different from the Net.Data limits:

- For OS/2, Windows NT, and UNIX: 64 KB
DB2 has the following restrictions:
 - DB2 Universal Database V6 or higher: 64 KB
 - DB2 Universal Database V5.2 or lower: 32 KB
- For OS/390: 32 KB
- For OS/400: 32 KB

Examples

The following examples are general and do not cover all language environments. See *Net.Data Language Environment Reference* for more information about using FUNCTION blocks with a specific language environment.

Example 1: A REXX substring function

```
%DEFINE lstring = "longstring"
%FUNCTION(DTW_REXX) substring(IN x, y, z) RETURNS(s) {
  s = substr("$x", $(y), $(z));
}%
%DEFINE a = {@substring(lstring, "1", "4")%} %{ assigns "long" to a %}
```

When *a* is evaluated, the @substring function call is found and the substring FUNCTION block is executed. Variables are substituted in the executable statements in the FUNCTION block, then the text string *s* = substr("longstring", 1, 4) is passed to the REXX interpreter to execute. Because the RETURNS clause is specified, the value of the @substring function call in the evaluation of *a* is replaced with "long", the value of *s*.

Example 2: Invoking an external REXX program

- Net.Data macro:

```
%FUNCTION(DTW_REXX) my_rexx_pgm(INOUT a, b, IN c, OUT d) {
  %EXEC{ mypgm.cmd this is a test %}
}%
%HTML(INPUT) {
  <p> Original variable values: $(w) $(x) $(z) </p>
  <p> @my_rexx_pgm(w, x, y, z) </p>
  <p> Modified variable values: $(w) $(x) $(z) </p>
}%
```

Variables *w* and *x* correspond to the INOUT parameters *a* and *b* in the function. Their values and the value of *y*, which corresponds to the IN parameter *c*, should already be defined from HTML form input or from a DEFINE statement. Variables *a* and *b* are assigned new values when parameters *a* and *b* return values. The variable *z* is defined when the OUT parameter *d* returns a value.

- REXX program mypgm.cmd:

```
/* Sample REXX Program for Example 2 */
/* Test arguments */
num_args = arg();
say 'There are' num_args 'arguments';
do i = 1 to num_args;
  say 'arg' i 'is "'arg(i)'"
end;
/* Set variables passed from Net.Data */
d = a || b || c; /* concatenate a, b, and c forming d */
a = ''; /* reset a to null string */
b = ''; /* reset b to null string */
return;
```

- Output from mypgm.cmd:

```

There are 1 arguments
arg 1 is "this is a test"

```

The EXEC statement tells the REXX language environment to tell the REXX interpreter to execute the external REXX program mypgm.cmd. Because the REXX language environment can directly share Net.Data variables with the REXX program, it assigns the REXX variables *a*, *b*, and *c* the values of the Net.Data variables *w*, *x* and *y* before executing mypgm.cmd. mypgm.cmd can directly use the variables *a*, *b*, and *c* in REXX statements. When the program ends, the REXX variables *a*, *b*, and *d* are retrieved from the REXX program, and their values are assigned to the Net.Data variables *w*, *x*, and *z*. Because the RETURNS clause is not used in the definition of the my_rexx_pgm FUNCTION block, the value of the @my_rexx_pgm function call is the null string, "", (if the return code is 0) or the value of the REXX program return code (if the return code is nonzero).

Example 3: An SQL query and report

```

%DEFINE customer_name="IBM"
%DEFINE customer_order="12345"

%FUNCTION(DTW_SQL) query_1(IN x, IN y) {
  SELECT customer.num, order.num, part.num, status
  FROM customer, order, shippingpart
  WHERE customer.num = '$(x)'
    AND customer.ordernumber = order.num
    AND order.num = '$(y)'
    AND order.partnumber = part.num
  %REPORT{
    <p>Here is the status of your order: </p>
    <p>$(NLIST) </p>
    <ul>
    %ROW{
      <li>$(V1) $(V2) $(V3) $(V4) </li>
    %}
    </ul>
    %}
  %}

%HTML(REPORT) {
  @query_1(customer_name, customer_order)
  %}

```

The @query_1 function call substitutes IBM for \$(x) and 12345 for \$(y) in the SELECT statement. Because the definition of the SQL function query_1 does not identify an output table variable, the default table is used (see the TABLE variables block for details). The NLIST and Vn variables referenced in the REPORT block are defined by the default table definition. The report produced by the REPORT block is placed in the output HTML where the query_1 function is invoked.

Example 4: A system call to execute a Perl script

- Net.Data macro:

```

%FUNCTION(DTW_SYSTEM) today() RETURNS(result) {
  %exec{ perl "today.pr1" %}
  %}
%HTML(INPUT) {
  @today()
  %}

```

- Perl program today.pr1:

```

$date = 'date';
chop $date;
open(DTW, "> $ENV{DTWPIPE}") || die "Could not open: $!";
print DTW "result = \"$date\"\n";

```

The System language environment interprets the executable statements in a FUNCTION block by passing them to the operating system through the C language system() function call. This method does not allow Net.Data variables to be directly passed or retrieved to the executable statements, as the REXX language environment does, so the System language environment passes and retrieves variables as described here:

- Input parameters are passed as system environment variables through the putenv() function and can be retrieved by the executing program. Different languages reference the variables differently. A UNIX cshell script refers to environment variables by preceding the environment variable name with a '\$', such as \$x. A Perl language script refers to them by referencing the associative array %ENV, such as %ENV{'x'}. A DOS batch (.BAT) file refers to the variable name enclosed in percent signs, such as %x%.
- Output parameters are passed back to the language environment by writing to a pipe whose name is passed in the environment variable DTWPIPE, except on the OS/400 platform, where output parameters are passed back to the language environment as system environment variables. The data that is written to the named pipe has the form name="value". If a variable name corresponding to an output parameter is written this way, the new value replaces the current value. If a variable name is written that does not correspond to an output parameter, it is ignored.

When the @today function call is encountered, Net.Data performs variable substitution on the executable statements. In this example, there are no Net.Data variables in the executable statements, so no variable substitution is performed. The executable statements and parameters are passed to the System language environment, which creates a named pipe and sets the environment variable DTWPIPE to the name of the pipe.

Then the external program is called with the C system() function call. The external program opens the pipe as write-only and writes the values of output parameters to the pipe as if it were a standard stream file. The external program generates output by writing to STDOUT. In this example, the output of the system date program is assigned to the variable result, which is the variable identified in the RETURNS clause of the FUNCTION block. This value of the result variable replaces the @today() function call in the HTML block.

Example 5: Perl language environment

```
%FUNCTION(DTW_PERL) today() RETURNS(result) {
    $date = 'date';
    chop $date;
    open(DTW, "> $ENV{DTWPIPE}") || die "Could not open: $!";
    print DTW "result = \"$date\"\n";
}%
%HTML(INPUT) {
    @today()
}%
```


Compare this example with Example 4 to see how the EXEC block is used. In Example 4, the System language environment does not understand how to interpret Perl programs, but the language environment does know how to call external programs. The EXEC block tells it to call a program called perl as an external program. The actual Perl language statements are interpreted by the external Perl program. Example 5 has no EXEC block, because the Perl language environment is able to directly interpret Perl language statements.

Function Call (@)

Purpose

Invokes a FUNCTION block, MACRO_FUNCTION block, or built-in function with specified arguments. If the function is not a built-in function, you must define it in the Net.Data macro before you specify a function call.

Syntax



Values

@function_name

The name of any existing function. An alphabetic or numeric string that begins with an alphabetic character or underscore and contains any combination of alphabetic, numeric, underscore, or period characters.

variable name

A name that identifies a variable. See "Variable Name" on page 4 for syntax information.

string

Any sequence of alphabetic and numeric characters and punctuation, except the new-line character.

variable reference

Returns the value of a variable and is specified with `$` and `()`. For example: if `VAR='abc'`, then `$(VAR)` returns the value `'abc'`. See "Variable Reference" on page 4 for syntax information.

function call

Invokes one or more FUNCTION or MACRO_FUNCTION blocks, or a Net.Data built-in function with specified arguments.

Context

Function calls can be found in these contexts:

- HTML block
- XML block
- REPORT block
- ROW block
- DEFINE block
- IF block
- WHILE block
- MESSAGE block
- MACRO_FUNCTION block
- Function call statement
- Outside of any block in the declaration part of the Net.Data macro

Restrictions

- Function calls can contain these elements:
 - Comment block
 - Strings
 - Function calls
 - Variable References
- OUT or INOUT parameter values cannot contain variable references, function calls, or literal strings.

Examples

Example 1: A call to the SQL function formQuery

```
%FUNCTION(DTW_SQL) formQuery(){
SELECT $(queryVal) from $(tableName)
}%

%HTML (Input){
<p>Which columns of $(tableName) do you want to see?</p>
<form method="post" action="report">
<input name="queryval" type="checkbox" value="name" /> Name
<input name="queryval" type="checkbox" value="mail" /> E-mail
<input name="queryval" type="checkbox" value="fax" /> FAX
<input type="submit" value="submit request" />
</form>
}%

%HTML (Report){
<p>Here are the columns you selected:</p>
<hr />
@formQuery()
}%
```

Example 2: A call to a REXX function with input and output parameters

```
%FUNCTION(DTW_REXX) my_rexx_pgm(INOUT a, b, IN c, OUT d) {
%EXEC{ mypgm.cmd this is a test %}
}%

%HTML (INPUT) {
<p> Original variable values: $(w) $(x) $(z) </p>
<p> @my_rexx_pgm(w, x, y, z) </p>
<p> Modified variable values: $(w) $(x) $(z) </p>
}%
```

Example 3: A call to a REXX function, with input parameters, that uses variable references and function calls

```
%FUNCTION(DTW_REXX) my_rexx_pgm(IN a, b, c, d, OUT e) {
...
}%

%HTML (INPUT) {
<p> @my_rexx_pgm$(myA), @getB(), @retrieveC(), $(myD), myE)</p>
}%
```

Example 4: A macro that illustrates the use of the INOUT parameter.

```
%DEFINE a = "initial value of a"

%FUNCTION(DTW_REXX) func1(INOUT x) {
Say 'value at start of function:<br />'
Say 'x =' x
Say '<p>'
x = "new value of a"
Say '<p>'
%REPORT {
```

```

        <p>value at start of report block:<p>
        x = $(x)<br />
        @dtw_assign(x, "newest value of a")
        value at end of report block:<br />
        x = $(x)<br />
    %}
%}

%HTML (Report) {
    initial values:<br />
    a = $(a)<br />
    @func1(a)
    value after function call:<br />
    a = $(a)<br />
%}

```

Resulting output:

```

initial values:
a = initial value of a

value at start of function:
x = initial value of a

value at start of report block:
x = new value of a

value at end of report block:
x = newest value of a

value after function call:
a = newest value of a


```

HTML Block

Purpose

Defines how a Web page is to be presented. The name of the HTML block to be executed is specified on the URL when Net.Data is invoked. The HTML block can contain most Net.Data macro language statements and any valid presentation statements, such as HTML and Javascript.

Syntax



Values

%HTML

The keyword that specifies that the block is a presentation block that contains HTML rather than XML tags.

name

An alphabetic or numeric string that begins with an alphabetic character or underscore and contains any combination of alphabetic, numeric, or underscore characters, including periods.

variable reference

Returns the value of a variable and is specified with `$` and `()`. For example: if `VAR='abc'`, then `$(VAR)` returns the value `'abc'`. See “Variable Reference” on page 4 for syntax information.

if block

The IF block. Performs conditional string processing. String values in the condition list are treated as numeric for comparisons if they are strings that represent integers and have no leading or trailing white space. They can have a single leading plus (+) or minus (-) sign. See “IF Block” on page 29 for syntax and examples.

function call

Invokes one or more `FUNCTION` or `MACRO_FUNCTION` blocks, or a Net.Data built-in function with specified arguments. See “Function Call (@)” on page 24 for syntax and examples.

presentation statements

Includes any alphabetic or numeric characters, as well as HTML tags to be formatted for the client’s browser.

include statement

The `INCLUDE` statement. Reads and incorporates a file into the Net.Data macro. See “INCLUDE Statement” on page 35 for syntax and examples.

while block

The WHILE block. Performs looping with conditional string processing. See “WHILE Block” on page 53 for syntax and examples.

Context

The HTML block can be found in these contexts:

- IF block
- Outside of any block in the declaration part of the Net.Data macro

Restrictions

The HTML block can contain these elements:

- Comment block
- IF block
- presentation statements
- INCLUDE statement
- WHILE block
- Variable references
- Function calls

Examples

Example 1: HTML block with include files for headings and footings

```
%HTML(my.report){  
%INCLUDE "header.html"  
<p>You can put <em>any</em> HTML in an HTML block.  
An SQL function call is made like this:</p>  
@xmpl()  
%INCLUDE "footer.html"  
%}
```


IF Block

Purpose

Performs conditional string processing. The IF block provides the ability to test one or more conditions, and then to perform a block of statements based on the outcome of the condition test. You can use the IF block in the declaration part of a Net.Data macro, the HTML block, the MACRO_FUNCTION block, the REPORT block, the WHILE block, and the ROW block, as well as nest it inside another IF block.

String values in the condition list are treated as numeric for comparisons if they are strings that represent integers and have no leading or trailing white space. They can have a single leading plus (+) or minus (-) sign.

Restriction: Net.Data does not support numerical comparison of non-integer numbers; for example, floating point numbers.

Nested IF blocks: The rules for IF block syntax are determined by the block's position in the macro. If an IF block is nested within an IF block that is outside of any other block in the declaration part, it can use any element that the outside block can use. If an IF block is nested within another block that is in an IF block, it takes on the syntax rules for the block it is inside.

In the following example, the nested IF block must follow the rules used when it is inside an HTML block.


```
%IF block
...
  %HTML block
...
    %IF block
```

You can nest up to 1024 IF blocks.


Syntax

►►—%IF—| condition list |—| statement_block |—| else_if spec |—%ENDIF—►►

condition list:




statement_block:




condition:



term:



else_if spec:



Notes:

- 1 This language construct is valid when the IF block is located outside of any other block in the declaration part of the macro.
- 2 This language construct is valid when the IF block is located in an HTML block, MACRO_FUNCTION block, REPORT block, ROW block, or WHILE block.

Values

%IF

The keyword that specifies conditional string processing.

condition list

Compares the values of conditions and terms. Condition lists can be connected using Boolean operators. A condition list can be nested inside another condition list.

statement_block

The following valid Net.Data macro constructs. Please see diagram notes and restrictions to determine the context in which the macro constructs are valid.

define statement

The DEFINE block or statement. Defines variables and sets configuration variables. Variable names must begin with a letter or underscore (_) and contain any alphanumeric characters or underscore. See “DEFINE Block or Statement” on page 10 for syntax and examples.

function block

A keyword that specifies a subroutine that can be invoked from the Net.Data macro. The executable statements in a FUNCTION block can contain language statements that are directly interpreted by a language environment, or they can indicate a call to an external program. See “FUNCTION Block” on page 17 for syntax and examples.

function call

Invokes one or more FUNCTION or MACRO_FUNCTION blocks, or a Net.Data built-in function with specified arguments. See “Function Call (@)” on page 24 for syntax and examples.

HTML block

Includes any alphabetic or numeric characters, as well as HTML tags to be formatted for the client’s browser.

XML block

Includes any alphabetic or numeric characters, as well as XML tags to be formatted for the client application.

presentation statement

Includes any alphabetic or numeric characters, and HTML or XML tags to be formatted for the client’s browser.

if block

The IF block. Performs conditional string processing. String values in the

condition list are treated as numeric for comparisons if they are strings that represent integers and have no leading or trailing white space. They can have a single leading plus (+) or minus (-) sign.

include statement

The INCLUDE statement. Reads and incorporates a file into the Net.Data macro. See “INCLUDE Statement” on page 35 for syntax and examples.

macro_function block

A keyword that specifies a subroutine that can be invoked from the Net.Data macro. The executable statements in a MACRO_FUNCTION block can contain Net.Data macro language source statements. See “MACRO_FUNCTION Block” on page 39 for syntax and examples.

message block

The MESSAGE block. A set of return codes, the associated messages, and the actions Net.Data takes when a function call is returned. See “MESSAGE Block” on page 43 for syntax and examples.

string

Any sequence of alphabetic and numeric characters and punctuation. If the string is in the term of the condition list, it can contain any character except the new-line character. If the string is in the executable block of code, it can contain any character, including the new-line character.

variable reference

Returns the value of a variable and is specified with \$ and (). For example: if VAR='abc', then \$(VAR) returns the value 'abc'. See “Variable Reference” on page 4 for syntax information.

while block

The WHILE block. Performs looping with conditional string processing. See “WHILE Block” on page 53 for syntax and examples

condition

A comparison between two terms using comparison operators. An IF condition is treated as a numeric comparison if both of the following conditions are true:

- The condition operator is one of the following operators: <,<=,>,>=,==,!=
- Both terms are strings representing valid integers, where a valid integer is a string of digits, optionally preceded by a plus (+) or minus (-) sign, and no other white space.

If either condition is not true, a normal string comparison is performed.

term

A variable name, string, variable reference, or function call.

%ELIF

A keyword that starts the alternative processing path and can contain condition lists and most Net.Data macro statements.

%ENDIF

A keyword that closes the %IF block.

%ELSE

A keyword that executes associated statements if all other condition lists are not satisfied.

Context

The IF block can be found in these contexts:

- Outside of any other block in the declaration part of a Net.Data macro
- HTML block

- XML block
- IF block
- MACRO_FUNCTION block
- REPORT block
- ROW block
- WHILE block

Restrictions

The IF block can contain these elements when located outside of any other block in the declaration part of the Net.Data macro:

- Comment block
- DEFINE block
- DEFINE statement
- FUNCTION block
- Function call
- HTML block
- XML block
- IF block
- INCLUDE statement
- MACRO_FUNCTION block
- MESSAGE block
- Variable reference

The IF block can contain these elements when located in the HTML block, XML block, MACRO_FUNCTION block, REPORT block, ROW block, or WHILE block of the Net.Data macro:

- Comment block
- Function calls
- IF block
- INCLUDE statement
- presentation statement
- String
- Variable reference
- WHILE block

You can nest up to 1024 IF blocks.

Examples

Example 1: An IF block in the declaration part of a Net.Data macro

```
%DEFINE a = "1"
%DEFINE b = "2"

...
%IF (OUT_FORMAT = "HTML")
    %define DTW_HTML_TABLE = "YES"
%ELSE
    %define DTW_HTML_TABLE = "NO"
%ENDIF

%HTML(REPORT) {
    ...
%}
```

Example 2: An IF block inside an HTML block

```
%HTML(REPORT) {
    @myFunctionCall()
    %IF (RETURN_CODE == failure_rc)
        <p> The function call failed with failure code $(RETURN_CODE).
    %ELIF (RETURN_CODE == warning_rc)
```

```

    <p> The function call succeeded with warning code $(RETURN_CODE).
%ELIF (RETURN_CODE == success_rc)
    <p>The function call was successful.
%ELSE
    <p>The function call returned with unknown return code $(RETURN_CODE).
%ENDIF
%}

```

Example 3: A numeric comparison

```

%IF (ROW_NUM < "100")
    <p>The table is not full yet...</p>
%ELIF (ROW_NUM == "100")
    <p>The table is now full...</p>
%ELSE
    <p>The table has overflowed...</p>
%ENDIF

```

A numeric comparison is done because the implicit table variable ROW_NUM always returns an integer value, and the value that is being compared is also an integer.

Example 4: Nested IF blocks

```

%IF (MONTH == "January")
    %IF (DATE = "1")
        HAPPY NEW YEAR!
    %ELSE
        Ho hum, just another day.
    %ENDIF
%ENDIF

```

INCLUDE Statement

Purpose

Reads and incorporates a file into the Net.Data macro in which the statement is specified.

Net.Data searches the directories specified in the INCLUDE_PATH statement in the initialization file to find the include file.


You can use include files the same way you can in most high-level languages. They can insert common headings and footings, define common sets of variables, or incorporate a common subroutine library of FUNCTION block definitions into a Net.Data macro.

Net.Data executes an INCLUDE statement only once when processing the macro and inserts the content of the included file at the location of the INCLUDE statement in the macro. Any variable references in the name of the included file are resolved at the time the INCLUDE statement is first executed, not when the content of the included file is to be executed.

When an INCLUDE statement is in a ROW or WHILE block, Net.Data does not repeatedly execute the INCLUDE statement. Net.Data executes the INCLUDE statement the first time it executes the ROW or WHILE block, incorporates the content of the included file into the block, and then repeatedly executes the ROW or WHILE block with the content of the included file.

Authorization Tip: Ensure that the user ID under which Net.Data executes has access rights to any files referenced by any INCLUDE statements. See the section on specifying Web server access rights to Net.Data files in the configuration chapter of *Net.Data Administration and Programming Guide* for more information.

Syntax



Values

%INCLUDE

The keyword that indicates a file is to be read and incorporated into the Net.Data macro.

name

An alphabetic or numeric string beginning with an alphabetic character or underscore and containing any combination of alphabetic, numeric, underscore, or period characters.

string

Any sequence of alphabetic and numeric characters and punctuation, except the new-line character.

variable reference

Returns the value of a variable and is specified with \$ and (). For example: if VAR='abc', then \$(VAR) returns the value 'abc'. See "Variable Reference" on page 4 for syntax information.

Context

The INCLUDE statement can be found in these contexts:

- DEFINE block
- HTML block
- XML block
- REPORT block
- ROW block
- IF block
- MESSAGE block
- MACRO_FUNCTION block
- WHILE block
- Outside of any block in the declaration part of the Net.Data macro

Restrictions

The INCLUDE statement can contain these elements:

- Comment block
- Strings
- Variable references

Function calls in the string are not allowed.

You can nest up to ten INCLUDE statements.

Examples

Example 1: An INCLUDE statement in an HTML block

```
%HTML(start){  
%INCLUDE "header.hti"  
...  
%}
```

Example 2: An INCLUDE statement in a REPORT block

```
%REPORT {  
  %INCLUDE "report_header.txt"  
  %ROW {  
    %INCLUDE "row_include.txt"  
  %}  
  %INCLUDE "report_footer.txt"  
%}
```

Example 3: Variable references in an INCLUDE statement


```
%define REMOTE_USER = %ENVVAR  
%include "${REMOTE_USER}.hti"
```


LIST Statement

Purpose

Builds a delimited list of values. You can use the LIST statement when you construct SQL queries with multiple items like those found in some WHERE or HAVING clauses.

Syntax



Values

%LIST

The keyword that specifies that variables are to be used to build a delimited list of values.

string

Any sequence of alphabetic and numeric characters and punctuation, except the new-line character.

variable reference

Returns the value of a variable and is specified with \$ and (). For example: if `VAR='abc'`, then `$(VAR)` returns the value 'abc'. See “Variable Reference” on page 4 for syntax information.

function call

Invokes one or more FUNCTION or MACRO_FUNCTION blocks, or a Net.Data built-in function with specified arguments. See “Function Call (@)” on page 24 for syntax and examples.

variable name

A name that identifies a variable. See “Variable Name” on page 4 for syntax information.

Context

The LIST statement can be found in these contexts:

- DEFINE statement

Restrictions

The LIST statement can contain these elements:

- Comment block
- Variable references
- Function calls
- Strings

Examples

Example 1: A list of variables

```
%DEFINE{
DATABASE="custcity"
%LIST " OR " conditions
conditions="cond1='Sao Paolo'"
```

```
conditions="cond2='Seattle'"
conditions="cond3='Shanghai'"
whereClause=conditions ? "WHERE ${conditions}" : ""
%}
```


For more information on using LIST statements with variables, see “List Variables” on page 63.

MACRO_FUNCTION Block


Purpose

Defines a subroutine that can be invoked from the Net.Data macro. The executable statements in a MACRO_FUNCTION block must be Net.Data macro language source statements.


Syntax




parm passing spec:



returns spec:



function body:



Notes:

- 1 The default parameter type of IN applies when no parameter type is specified at the beginning of the parameter list. A parameter without a parameter type uses the type most recently specified in the parameter list, or type IN if no type has been specified. For example, in the parameter list `(parm1, INOUT parm2, parm3, OUT parm4, parm5)`, parameters `parm1`, `parm3`, and `parm5` do not have parameter types. The parameter `parm1` has a

type of IN because no initial parameter type has been specified. The parameter *parm3* has a type of INOUT because it is the most recently specified parameter type. Similarly, the parameter *parm5* has a type of OUT because it is the most recently specified type in the parameter list.

Values

%MACRO_FUNCTION

The keyword that specifies a subroutine that can be invoked from the Net.Data macro. The executable statements in a MACRO_FUNCTION block must contain language statements that Net.Data directly interprets.

function_name

The name of the function being defined. An alphabetic or numeric string that begins with an alphabetic character or underscore and contains any combination of alphabetic, numeric, underscore, or period characters.

parm passing spec:

IN Specifies that Net.Data passes input data to the language environment. IN is the default.

OUT

Specifies that the language environment returns output data to Net.Data.

INOUT

Specifies that Net.Data passes input data to the language environment and the language environment returns output data to Net.Data.

name

An alphabetic or numeric string beginning with an alphabetic character or underscore and containing any combination of alphabetic, numeric, or underscore characters. *name* can represent a Net.Data table or a result set.

returns spec:

RETURNS

Declares the variable that contains the function value after the function completes.

function body:

variable reference

Returns the value of a variable and is specified with \$ and (). For example: if VAR='abc', then \$(VAR) returns the value 'abc'. See “Variable Reference” on page 4 for syntax information.

if block

The IF block. Performs conditional string processing. String values in the condition list are treated as numeric for comparisons if they represent integers and have no leading or trailing white space. They might have one leading plus (+) or minus (-) sign.

function call

Invokes one or more FUNCTION or MACRO_FUNCTION blocks, or a Net.Data built-in function with specified arguments. See “Function Call (@)” on page 24 for syntax and examples.

presentation statement

Includes any alphabetic or numeric characters, as well as HTML tags to be formatted for the client's browser.

include statement

The INCLUDE statement. Reads and incorporates a file into the Net.Data macro. See “INCLUDE Statement” on page 35 for syntax and examples.

while block

The WHILE block. Performs looping with conditional string processing. See “WHILE Block” on page 53 for syntax and examples.

report block

The REPORT block. Formatting instructions for the output of a function call. You can use header and footer information for the report. See “REPORT Block” on page 47 for syntax and examples.

Context

The MACRO_FUNCTION block can be found in these contexts:

- IF block
- Outside of any block in the declaration part of the Net.Data macro

Restrictions

The MACRO_FUNCTION block can contain these elements:

- Comment block
- presentation statements
- IF block
- INCLUDE statement
- REPORT block
- WHILE block
- Variable references
- Function calls

Examples

Example 1: A macro function that specifies message handling

```
%MACRO_FUNCTION setMessage(IN rc, OUT message) {
%IF (rc == "0")
    @dtw_assign(message, "Function call was successful.")
%ELIF (rc == "-1")
    @dtw_assign(message, "Function failed, out of memory.")
%ELIF (rc == "-2")
    @dtw_assign(message, "Function failed, invalid parameter.")
%ENDIF
%}
```

Example 2: A macro function that specifies header information

```
%MACRO_FUNCTION setup(IN browserType) {
%{ call this function at the top of each HTML block in the macro %}
%INCLUDE "header_info.html"
@dtw_rdate()
%IF (browserType == "IBM")
    @setupIBM()
%ELIF (browserType == "MS")
    @setupMS()
%ELIF (browserType == "NS")
    @setupNS()
%ELSE
    @setupDefault()
%ENDIF
%}
```

Example 3: A macro function that contains a REPORT block

```

%MACRO_FUNCTION myfunc (INOUT table) {
  %REPORT {
    <table>
    %ROW {
      <tr><td>$(V1)</td><td>$(V2)</td></tr>
    %}
    </table>
  %}
%}

```

Example 4: A macro function that uses the RETURNS keyword

```

%MACRO_FUNCTION myfunc () RETURNS(VALUE) {
  @DTW_ASSIGN(VALUE, "Success...")
%}

```

MESSAGE Block


Purpose

Specifies messages to display and actions to take based on the return code from a function.

Define the set of return codes, along with their corresponding messages and actions in the MESSAGE block. When a function call completes, Net.Data compares its return code with return codes defined in the MESSAGE block. If the function's return code matches one in the MESSAGE block, Net.Data displays the message and evaluates the action to determine whether to continue processing or exit the Net.Data macro.

A MESSAGE block can be global in scope, or local to a single FUNCTION block. If the MESSAGE block is defined at the outermost macro layer, it is considered global in scope. When multiple global MESSAGE blocks are defined, only the last block processed is considered active. If the MESSAGE block is defined inside a FUNCTION block, the block is local in scope to the FUNCTION block where it is defined. See the MESSAGE block section in the *Net.Data Administration and Programming Guide* for return code processing rules.


Syntax




return code spec:



SQLSTATE:



message text spec:



action spec:



Values

%MESSAGE

A keyword for the block that defines a set of return codes, the associated messages, and the actions Net.Data takes when a function call is returned.

return code spec

A positive or negative integer. If the value of the Net.Data RETURN_CODE variable matches the *return code spec* value, the remaining information in the message statement is used to process the function call. You can also specify messages for return codes not specifically entered in the MESSAGE block.

+DEFAULT

A keyword used to specify a default positive message code. Net.Data uses the information in this message statement to process the function call if RETURN_CODE is greater than zero (0) and an exact match is not specified.

-DEFAULT

A keyword to specify a default negative message code. Net.Data uses the information in this message statement to process the function call if RETURN_CODE is less than zero (0) and an exact match is not specified.

DEFAULT

A keyword to specify the default message code. Net.Data uses the information in this message statement to process the function call, if all of the following conditions are met:

- If RETURN_CODE is greater or less than zero, but not zero
- If no exact match for the return code is specified
- If the +DEFAULT or -DEFAULT values are not specified for when RETURN_CODE is greater or less than zero

msg_code

The message code that specifies errors and warnings that can occur during processing. A string of numeric digits with values from 0 to 9.

SQLSTATE

A keyword that provides application programs with common codes for common error conditions. The SQLSTATE values are based on the SQLSTATE specification contained in the SQL standard, and the coding scheme is the same on all IBM implementations of SQL. This value is matched with the Net.Data variable SQL_STATE.

state_id

The SQLSTATE. An alphanumeric string of five characters (bytes) with a format of *ccsss*, where *cc* indicates class and *sss* indicates subclass.

message text spec

A string that is sent to the Web browser if either the RETURN_CODE matches the *return_code* value or the SQL_STATE variable matches the SQLSTATE value in the current message statement.

string

Any sequence of alphabetic and numeric characters and punctuation. If the string appears within double quotes, the new-line character is not allowed.

variable reference

Returns the value of a variable and is specified with \$ and (). For example: if VAR='abc', then \$(VAR) returns the value 'abc'. See “Variable Reference” on page 4 for syntax information.

function call

Invokes one or more FUNCTION or MACRO_FUNCTION blocks, or a Net.Data built-in function with specified arguments. See “Function Call (@)” on page 24 for syntax and examples.

action spec

Specifies what action Net.Data takes if the RETURN_CODE variable matches the *return_code* value, or the SQL_STATE variable matches the SQLSTATE value in the current message statement.

EXIT

A keyword that specifies to exit the macro immediately when the error or warning corresponding to the specified message code occurs. This value is the default.

CONTINUE

A keyword that specifies to continue processing when the error or warning corresponding to the specified message code occurs.

include statement

The INCLUDE statement. Reads and incorporates a file into the Net.Data macro. The INCLUDE statement can appear anywhere in the MESSAGE. See “INCLUDE Statement” on page 35 for syntax and examples.

Context

The MESSAGE block can be found in these contexts:

- FUNCTION block
- IF block
- Outside of all blocks or statements in the declaration part of the Net.Data macro

Restrictions

The MESSAGE block can contain these elements:

- Comment block
- Function calls
- Variable references
- presentation statements
- Strings
- INCLUDE statement

For OS/390: SQL functions cannot be called from inside SQL functions.

Examples

Example 1: A local MESSAGE block

```
%{ local message block inside a FUNCTION block %}
%FUNCTION(DTW_REXX) my_function() {
  %EXEC { my_command.cmd %}
  %MESSAGE{
-601: {<h3>The table has already been created, please go back and enter your name.</h3>
<p><a href="input">Return</a>
%}
default: "<h3>Can't continue because of error $(RETURN_CODE)</h3>"%}      : exit
%}
```

Example 2: A global MESSAGE block

```
%{ global message block %}
%MESSAGE {
  -100      : "Return code -100 message"      : exit
  100      : "Return code 100 message"       : continue
  +default : {
This is a long message that spans more
than one line. You can use HTML tags, including
links and forms, in this message. %}      : continue
%}

%{ local message block inside a FUNCTION block %}
%FUNCTION(DTW_REXX) my_function() {
  %EXEC { my_command.cmd %}
  %MESSAGE {
    -100      : "Return code -100 message"      : exit
    100      : "Return code 100 message"       : continue
    -default : {
This is a long message that spans more
than one line. You can use HTML tags, including
links and forms, in this message. %}      : exit
%}
%}
```

Example 3: A MESSAGE block containing INCLUDE statements.


```
%message {
  %include "rc1000.msg"
  %include "rc2000.msg"
  %include "defaults.msg"
%}
```

REPORT Block

Purpose

Formats output from a function call. You can enter a table name parameter to specify that the report is to use the data in the named table. Otherwise, the report is generated with the first output table found in the function parameter list, or with the default table data if no table name is in the list.

Syntax



Values

%REPORT

The keyword for specifying formatting instructions for the output of a function call. You can use header and footer information for the report.

name

This value represents a Net.Data table or result set. See the Report Block section in the *Net.Data Administration & Programming Guide* for more information.

string

Any sequence of alphabetic and numeric characters and punctuation.

if block

The IF block. Performs conditional string processing. String values in the condition list are treated as numeric for comparisons if they represent integers and have no leading or trailing white space. They can have one leading plus (+) or minus (-) sign. See “IF Block” on page 29 for syntax and examples.

variable reference

Returns the value of a variable and is specified with \$ and (). For example: if `VAR='abc'`, then `$(VAR)` returns the value 'abc'. See “Variable Reference” on page 4 for syntax information.

function call

Invokes one or more FUNCTION or MACRO_FUNCTION blocks, or a Net.Data built-in function with specified arguments. See “Function Call (@)” on page 24 for syntax and examples.

presentation statements

Includes any alphabetic or numeric characters, as well as HTML tags to be formatted for the client’s browser.

include statement

The INCLUDE statement. Reads and incorporates a file into the Net.Data macro. See “INCLUDE Statement” on page 35 for syntax and examples.

row block

The ROW block. Displays HTML formatted data once for each row of data that is returned from a function call. See “ROW Block” on page 49 for syntax and examples.

while block

The WHILE block. Performs looping with conditional string processing. See “WHILE Block” on page 53 for syntax and examples.

Context

The REPORT block can be found in these contexts:

- FUNCTION statement or block

Restrictions

The REPORT block can contain these elements:

- Comment block
- IF block
- INCLUDE statements
- ROW blocks
- WHILE blocks
- Function calls
- presentation statements
- Strings
- Variable references

Examples

Example 1: A two-column HTML table showing a list of names and locations

```
%FUNCTION(DTW_SQL) mytable() {
  %REPORT{
    <h2>Query Results</h2>
    <p>Select a name for details.</p>
    <table border="1">
      <tr><td>Name</td><td>Location</td></tr>
      %ROW{
        <tr>
          <td>
            <a href="/cgi-bin/db2www/name.mac/details?name=$(V1)&loc=$(V2)">$(V1)
          </a></td>
          <td>$(V2)</td>
        </tr>
      %}
    </table>
  %}
```


Selecting a name in the table calls the *details* HTML block of the *name.mac* Net.Data macro and sends it the two values as part of the URL. In this example, the values can be used in *name.mac* to look up additional details about the name.

ROW Block

Purpose

Processes each table row returned from a function call. Net.Data processes the statements within the ROW block once for each row.

Syntax



Values

%ROW

The keyword that specifies that HTML formatted data is to be displayed, once for each row of data returned from a function call.

string

Any sequence of alphabetic and numeric characters and punctuation.

if block

The IF block. Performs conditional string processing. String values in the condition list are treated as numeric for comparisons if they are strings that represent integers and have no leading or trailing white space. They can have a single leading plus (+) or minus (-) sign. See “IF Block” on page 29 for syntax and examples.

variable reference

Returns the value of a variable and is specified with \$ and (). For example: if VAR='abc', then \$(VAR) returns the value 'abc'. See “Variable Reference” on page 4 for syntax information.

function call

Invokes one or more FUNCTION or MACRO_FUNCTION blocks, or built-in functions with specified arguments. See “Function Call (@)” on page 24 for syntax and examples.

presentation statements

Includes any alphabetic or numeric characters, as well as HTML tags to be formatted for the client’s browser.

include statement

The INCLUDE statement. Reads and incorporates a file into the Net.Data macro. See “INCLUDE Statement” on page 35 for syntax and examples.

while block

The WHILE block. Performs looping with conditional string processing. See “WHILE Block” on page 53 for syntax and examples.

Context

The ROW block can be found in these contexts:

- REPORT block

Restrictions

The ROW block can contain these elements:

- Comment block
- IF blocks
- INCLUDE statements
- WHILE blocks
- Function calls
- Variable references
- presentation statements
- Strings

Examples

Example 1: A two-column HTML table showing a list of names and locations

```
%REPORT{
<h2>Query Results</h2>
<p>Select a name for details.</p>
<table border="1">
<tr><th>Name</th><th>Location</th></tr>

%ROW{
<tr>
<td>
<a href="/cgi-bin/db2www/name.mac/details?name=$(V1)&location=$(V2)">$(V1)</a></td>
<td>$(V2)</td></tr>
%}

</table>
%}
```

Selecting a name in the table calls the *details* HTML block of the *name.mac* Net.Data macro and sends it the two values as part of the URL. In this example, the values can be used in *name.mac* to look up additional details about the name.

TABLE Statement

Purpose

Defines a variable which is a collection of related data. The variable contains a set of rows and columns including a row of column headers describing the fields in each row. A table statement can only be in a DEFINE statement or block.

When a TABLE variable is referenced while executing an HTML block, Net.Data displays the content of the table as either a plain character table or, if the DTW_HTML_TABLE variable is set to YES, as an HTML table. When a TABLE variable is referenced while executing an XML block, Net.Data returns the table as a RowSet.

Syntax

►► %TABLE | upper limit | ►►

upper limit:

|
| (| number |) |
| ALL |

Values

%TABLE

A keyword that specifies the definition of a collection of related data containing an array of identical records, or rows, and an array of column names describing the fields in each row.

upper limit

The number of rows that can be contained in the table. If the upper limit value is not specified, the table can contain an unlimited number of rows.

number

A string of digits. A value of 0 allows for unlimited number of rows in the table.

ALL

A keyword that allows for an unlimited number of rows in the table.

Context

The TABLE statement can be found in these contexts:

- DEFINE statement

Restrictions

The TABLE statement can contain these elements:

- Comment block
- Numbers

Examples

Example 1: A Net.Data table with an upper limit of 30 rows

```
%DEFINE myTable1=%TABLE(30)
```

Example 2: A Net.Data table that uses the default of all rows

```
%DEFINE myTable2=%TABLE
```

Example 3: A Net.Data table that specifies all rows


```
%DEFINE myTable3=%TABLE(ALL)
```


WHILE Block


Purpose

Provides a looping construct based on conditional string processing. You can use the WHILE block in the HTML block, the REPORT block, the ROW block, the IF block, and the MACRO_FUNCTION block. String values in the condition list are treated as numeric for comparisons if they are strings that represent integers and have no leading or trailing white space. They can have a single leading plus (+) or minus (-) sign.

Syntax




condition list:



condition:



term:



Values

%WHILE

The keyword that specifies loop processing.

condition list

Compares the values of conditions and terms. Condition lists can be connected using Boolean operators. A condition list can be nested inside another condition list.

condition

A comparison between two terms using comparison operators. An IF condition is treated as a numeric comparison if both of the following conditions are true:

- The condition operator is one of the following operators: <,<=,>,>=,==,!=
- Both terms are strings representing valid integers, where a valid integer is a string of digits, optionally preceded by a plus (+) or minus (-) sign, and no other white space.

If either condition is not true, a normal string comparison is performed.

term

A variable name, string, variable reference, for function call.

function call

Invokes one or more FUNCTION or MACRO_FUNCTION blocks, or built-in functions with specified arguments. See “Function Call (@)” on page 24 for syntax and examples.

presentation statement

Includes any alphabetic or numeric characters, as well as HTML tags to be formatted for the client’s browser.

if block

The IF block. Performs conditional string processing. String values in the condition list are treated as numeric for comparisons if they represent integers and have no leading or trailing white space. They can have one leading plus (+) or minus (-) sign. See “IF Block” on page 29 for syntax and examples.

include statement

The INCLUDE statement. Reads and incorporates a file into the Net.Data macro. See “INCLUDE Statement” on page 35 for syntax and examples.

while block

The WHILE block. Performs looping with conditional string processing. See “WHILE Block” on page 53 for syntax and examples.

variable reference

Returns the value of a variable and is specified with \$ and (). For example: if VAR='abc', then \$(VAR) returns the value 'abc'. See “Variable Reference” on page 4 for syntax information.

string

Any sequence of alphabetic and numeric characters and punctuation. A string in the term of the condition list can contain any character except the new-line character.

variable name

A name that identifies a variable. See “Variable Name” on page 4 for syntax information.

Context

The WHILE block can be found in these contexts:

- HTML block
- REPORT block
- ROW block
- MACRO_FUNCTION block
- IF block
- WHILE block

Restrictions

The WHILE block can contain these elements:

- Comment block
- IF block
- WHILE block
- Strings
- presentation statements
- Function calls
- Variable references
- INCLUDE statements

Examples

Example 1: A WHILE block that generates rows in a table

```
%DEFINE loopCounter = "1"

%HTML(build_table) {
%{ generate table tag and column headings %}
<table border="1">
<tr>
<th>Item #</th>
<th>Description</th>
</tr>
%WHILE (loopCounter <= "100") {
  %{ generate individual rows %}
  <tr>
  <td>$(loopCounter)</td>
  <td>@getDescription(loopCounter)</td>
  </tr>


  %{ increment loop counter %}
  @dtw_add(loopCounter, "1", loopCounter)
%}
</table>
%}
```

XML Block

Purpose

Defines how a Web page is to be presented in XML-enabled Web clients. The name of the XML block to be executed is specified on the URL when Net.Data is invoked. The XML block can contain most Net.Data macro language statements and any XML content. For more information on the style and presentation of XML in Net.Data, see *Net.Data Administration and Programming Guide*

Syntax



Values

%XML

The keyword that specifies that the block is a presentation block that contains XML.

name

An alphabetic or numeric string that begins with an alphabetic character or underscore and contains any combination of alphabetic, numeric, or underscore characters, including periods.

variable reference

Returns the value of a variable and is specified with \$ and (). For example: if `VAR='abc'`, then `$(VAR)` returns the value 'abc'. See "Variable Reference" on page 4 for syntax information.

if block

The IF block. Performs conditional string processing. String values in the condition list are treated as numeric for comparisons if they are strings that represent integers and have no leading or trailing white space. They can have a single leading plus (+) or minus (-) sign. See "IF Block" on page 29 for syntax and examples.

function call

Invokes one or more FUNCTION or MACRO_FUNCTION blocks, or a Net.Data built-in function with specified arguments. See "Function Call (@)" on page 24 for syntax and examples.

XML statements

Includes any XML that is well-formed or also complies with the DTD or stylesheet that applies to your application.

include statement

The INCLUDE statement. Reads and incorporates a file into the Net.Data macro. See "INCLUDE Statement" on page 35 for syntax and examples.

while block

The WHILE block. Performs looping with conditional string processing. See “WHILE Block” on page 53 for syntax and examples.

Context

The XML block can be found in these contexts:

- IF block
- Outside of any block in the declaration part of the Net.Data macro

Restrictions

The XML block can contain these elements:

- Comment block
- IF block
- XML statements
- INCLUDE statement
- WHILE block
- Variable references
- Function calls

Examples

Example 1. An XML block including a standard prolog and calling a function:

```
%XML (Report) {
%INCLUDE "style3header.xml"
<XMLBlock name="Results">
@xmp1()
</XMLBlock>
%}
```

Example 2. xmp1() could be defined to return a small result set from an SQL query:

```
%FUNCTION DTW_SQL xmp1() {
    SELECT LASTNME,EMPNO FROM EMPLOYEES
    WHERE LASTNME LIKE 'M%'
%}

%XML (Report) {
<?xml version="1.0" ?>
<?xml-stylesheet type="text/xsl" href="ndReport.xsl" ?>
<XMLBlock name="Results">
@xmp1()
</XMLBlock>
%}
```

Chapter 2. Variables

Net.Data provides two types of variables: user-defined variables and Net.Data variables.

“User-defined Variables” on page 60

Variables that you define for your application. You can define the variables that perform the following tasks:

- **“Conditional Variables” on page 60**
Assign a variable value based on the value of another variable or string.
- **“Environment Variables” on page 61**
Use the ENVVAR language construct to reference environment variables.
- **“Executable Variables” on page 61**
Use the EXEC language construct to invoke other programs from a variable reference.
- **“Hidden Variables” on page 62**
Hide variable reference from HTML source.
- **“List Variables” on page 63**
Build a delimited string of values using the LIST language construct.
- **“Table Variables” on page 64**
Pass an array of values to and from a function. Can be used for report output.

Net.Data Variables

Variables that are for miscellaneous processing and file manipulation, table processing, report formatting, and language environments.

Some variables have values that you can define or modify, others are defined by Net.Data. The description for the variable specifies whether you define a value or not. See the description of a variable to determine how the value is defined.

The following variable types are provided by Net.Data:

- **“Net.Data Table Processing Variables” on page 65**
Defined by Net.Data to let you process Net.Data tables. Use these variables to access data from SQL queries and function calls. They are only recognized inside REPORT or ROW blocks, unless otherwise specified.
- **“Net.Data Report Variables” on page 74**
Help you customize reports from a function. You can define report variables in the DEFINE section, or assign them in any Net.Data block.
- **“Net.Data Language Environment Variables” on page 80**
Help you customize the way FUNCTION blocks are processed, using language environments.
- **“Net.Data Miscellaneous Variables” on page 98**
Defined by Net.Data to affect Net.Data processing, find out the status of a function call, and obtain information about the result set of a database query. Some miscellaneous variables are set by Net.Data and cannot be changed.

The output for many Net.Data variables varies depending on the operating system on which it runs.

User-defined Variables

This section describes the user-defined variables. You define these variables within the macro.

Conditional Variables

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

A conditional variable is one that is set based on the value of another variable or string. This is also called a *ternary operation*.

The syntax to conditionally set a variable is:

```
condVar = testVar ? trueValue : falseValue
```

Where:

condVar

The conditional variable to be set.

testVar

A test variable used to determine the condition. An empty string is evaluated as false.

trueValue

Is the value to use if the test variable is true.

falseValue

Is the value to use if the test variable is false.

Example 1: A conditional variable defined with two possible values

```
varA = varB ? "value_1" : "value_2"
```

varB is the test. So, varA is assigned either "value_1" or "value_2", depending on whether varB exists and is not empty.

Example 2: A conditional variable used with a LIST statement and WHERE clause

```
%DEFINE{
%list " AND " where_list
where_list = ? "custid = $(cust_inp)"
where_list = ? "product_name LIKE '$(prod_inp)%'"
where_clause = ? "WHERE $(where_list)"
}%

%FUNCTION(DTW_SQL) mySelect() {
    SELECT * FROM prodtbale $(where_clause)
}%
```

Conditional and LIST variables are most effective when used together. The above example shows how to set up a WHERE clause in the DEFINE block. The variables *cust_inp* and *prod_inp* are HTML input variables passed from the Web browser,

usually from an HTML form. The variable *where_list* is a LIST variable made of two conditional statements, each statement containing a variable from the Web browser.

If the Web browser returns values for both variables *cust_inp* and *prod_inp*, for example, IBM and 755C, the *where_clause* is:

```
WHERE custid = IBM AND product_name LIKE '755C%'
```

If either variable *cust_inp* or *prod_inp* is empty or not defined, the WHERE clause changes to be an empty string. For example, if *prod_inp* is empty, the WHERE clause is:

```
WHERE custid = IBM
```

If both values are empty or undefined, the variable *where_clause* is empty and no WHERE clause appears in SQL queries containing *\$(where_clause)*.

Environment Variables

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Environment variables let you use the Net.Data ENVVAR language construct to reference environment variables that exist in the process under which Net.Data is running.

Example 1: A variable is assigned the value of an environment variable

```
%define SERVER_NAME=%ENVVAR
```

```
...
```

```
The server is $(SERVER_NAME)
```

The environment variable *SERVER_NAME* has the value of the current server name, which, in this example, is *www.ibm.com*.

```
The server is www.ibm.com
```

See “ENVVAR Statement” on page 14 for more information about the ENVVAR statement.

Executable Variables

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Executable variables allow you to invoke other programs from a variable reference using the executable variable feature. An executable variable is defined in a Net.Data macro using the EXEC language element. For more information about the EXEC language element, see “EXEC Block or Statement” on page 15.

When Net.Data encounters an executable variable in a macro, it looks for the referenced executable program using the following method:

1. It searches the EXEC_PATH in the Net.Data initialization file. See the configuration chapter in *Net.Data Administration and Programming Guide* for more information about EXEC_PATH.
2. If Net.Data does not locate the program, it searches the directories defined by the system. If it locates the executable program, Net.Data runs the program.

Example 1: An executable variable definition

```
%DEFINE runit=%exec "testProg"
```

The variable *runit* is defined to execute the executable program *testProg*; *runit* becomes an executable variable.

Net.Data runs the executable program when it encounters a executable variable reference in a Net.Data macro. For example, the program *testProg* is executed when a executable variable reference is made to the variable *runit* in a Net.Data macro.

A simple method is to reference an executable variable from another variable definition. Example 2 demonstrates this method. The variable *date* is defined as an executable variable and *dateRpt* is then defined as a variable reference, that contains the executable variable.

Example 2: An executable variable as a variable reference

```
%DEFINE date=%exec "date"
```

When Net.Data resolves the variable reference $\$(date)$, Net.Data searches for the executable *date* and runs the program:

If the presentation block contains the following:

Today is $\$(date)$

The browser displays the results of the executable:

Today is 02-14-2001

An executable variable is never set to the value of the output of the executable program it calls. Using the previous example, the value of *date* is null. If you use it in a DTW_ASSIGN function call to assign its value to another variable, the value of the new variable after the assignment is null also. The only purpose of an executable variable is to invoke the program it defines.

You can also pass parameters to the program to be executed by specifying them with the program name on the variable definition.

Example 3: Executable variables with parameters

```
%DEFINE mph=%exec "calcMPH  $\$(distance)$   $\$(time)$ "
```

The values of *distance* and *time* are passed to the program *calcMPH*.

Hidden Variables

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

With hidden variables, you can reference variables while hiding the actual variable value in your HTML source. To use hidden variables:

1. Define a variable for each string you want to hide.
2. In the HTML block where the variables are referenced, use double dollar signs instead of a single dollar sign to reference the variables. For example, \$\$*(X)* instead of \$(*X*).

Do not reference hidden variables with dynamically constructed variable names.

Example 1: Hidden variables in a HTML form

```
%DEFINE {
name="customer.name"
addr="customer.address"
%}

%FUNCTION(DTW_SQL) mySelect() {
  SELECT $(Field) FROM customer
%}

%HTML(INPUT) {
<form ...>
<p>Select fields to view:</p>
<select name="field">
<option value="$$ (name)"> Name</option>
<option value="$$ (addr)"> Address</option>
.
.
</select>
.
.
</form>
%}
```

When the HTML form is displayed on a Web browser, \$\$*(name)* and \$\$*(addr)* are replaced with \$(*name*) and \$(*addr*) respectively, so the actual table and column names never appear on the HTML form. When the customer submits the form, the HTML(REPORT) block is called. When @mySelect() calls the FUNCTION block, \$(*Field*) is substituted in the SQL statement with customer.name or customer.addr in the SQL query.

List Variables

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

You can use list variables to build a delimited string of values. They are particularly useful in helping you construct an SQL query with multiple items like those found in some WHERE or HAVING clauses.

The blanks are significant. Usually you want to have a blank space on both sides of the value. Most queries use Boolean or mathematical operators (for example, AND, OR, and >). See “LIST Statement” on page 37 for syntax and more information.

Example 1: Use of conditional, hidden, and list variables

```
%DEFINE {
DATABASE="custcity"
%LIST " OR " conditions
cond1="cond1='Sao Paolo'"
cond2="cond2='Seattle'"
}
```

```

cond3="cond3='Shanghai'"
whereClause= ? "WHERE $(conditions)"
%}

%HTML(INPUT){
<form method="post" action="/cgi-bin/db2www/example2.max/report">
Select one or more cities:<br />
<input type="checkbox" name="conditions" value="$(cond1)" />Sao Paulo<br />
<input type="checkbox" name="conditions" value="$(cond2)" />Seattle<br />
<input type="checkbox" name="conditions" value="$(cond3)" />Shanghai<br />
<input type="submit" value="submit query" />
</form>
%}

%FUNCTION(DTW_SQL) mySelect(){
SELECT name, city FROM citylist
$(whereClause)
%}

%HTML (Report){
@mySelect()
%}

```

If no boxes are checked in the HTML form, then *conditions* is empty, so *whereClause* is also empty in the query. Otherwise, *whereClause* has the selected values separated by the Boolean operator OR. For example, if all three cities are selected, the SQL query is:

```

SELECT name, city FROM citylist
WHERE cond1='Sao Paolo' OR cond2='Seattle' OR cond3='Shanghai'

```

Example 2: Value separators

```

%DEFINE %LIST " | " VLIST
%REPORT{
%ROW{
<em>$(ROW_NUM):</em> $(VLIST)
%}
%}

```

The table processing variable VLIST uses two quotes and an OR bar, (|), as a value separator in this example. The string of values are separated by the value in quotes.

Table Variables

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

The table variable defines a collection of related data. It contains a set of rows and columns including a row of column headers. Use table variables to pass groups of values to a function. You can refer to the individual elements of a table (the rows) in a REPORT block of a function or by using table built-in functions. Table variables are often used for output from an SQL function and input to a report, but you can also pass them as IN, OUT, or INOUT parameters to any non-SQL function. Tables can only be passed to SQL functions as OUT parameters. See “TABLE Statement” on page 51 for syntax and more information.

When a TABLE variable is referenced, Net.Data displays the content of the table as either a plain character table, or as an HTML table if the DTW_HTML_TABLE variable is set to YES. When an XML block is executed, Net.Data returns a RowSet structure (see “XML Block” on page 56).

Example 1: A SQL result set that is passed to a REXX program

```
%DEFINE{
  DATABASE = "iddata"
  MyTable = %TABLE(ALL)
  DTW_DEFAULT_REPORT = "NO"
}%

%FUNCTION(DTW_SQL) Query(OUT table) {
  select * from survey
}%

%FUNCTION(DTW_REXX) showTable(INOUT table) {
  Say 'Number of Rows: 'table_ROWS
  Say 'Number of Columns: 'table_COLS
  do j=1 to table_COLS
    Say "Here are all of the values for column " table_N.j ":"
    do i = 1 to table_ROWS
      Say "<b>"i"</b>: " table_V.i.j
    end
  end
}%

%HTML (Report){
  <HTML>
  <pre>
  @Query(MyTable)
  <p>
  @showTable(MyTable)
  </p>
  </pre>
  </HTML>
}%
```

The HTML REPORT block calls an SQL query, saves the result in a table variable and then passes the variable to a REXX function.

Net.Data Table Processing Variables

Net.Data defines these variables for use in the REPORT and ROW blocks, unless noted otherwise. Use these variables to reference values that your queries return.

- “Nn” on page 66
- “NLIST” on page 67
- “NUM_COLUMNS” on page 68
- “NUM_ROWS” on page 69
- “ROW_NUM” on page 70
- “TOTAL_ROWS” on page 71
- “V_columnName” on page 72
- “VLIST” on page 73
- “Vn” on page 74

Nn

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

The column name returned by a function call or query for column n.

You can reference Nn in REPORT and ROW blocks.

Examples

Example 1: A variable reference for a column name

The name of column 2 is \$(N2).

Example 2: Saves the value of a column name for use outside a REPORT block using DTW_ASSIGN

```
%define coll=""
...
%function (DTW_SQL) myfunc(OUT coll) {
  select * from atable
  %report {
    @dtw_assign(coll, N1)
    %row{ %}
  %}
%}

%html(report) {
  @myfunc(colname)
  The column name for the first column is $(colname)
%}
```

This example shows how you can use this variable outside the REPORT block by using DTW_ASSIGN. For more information, see “DTW_ASSIGN” on page 168.

Example 3: Nn within an HTML table to define column names

```
%REPORT{
<h2>Product directory</h2>
<table border="1" cellpadding="3">
<tr><td>$(N1)</td><td>$(N2)</td><td>$(N3)</td></tr>
%ROW{
<tr><td>$(V1)</td><td>$(V2)</td><td>$(V3)</td></tr>
%}
</table>

%}
```

NLIST

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Contains a list of all the column names from the result of a function call or query. The default separator is a space.

You can reference NLIST in REPORT and ROW blocks.

Examples

Example 1: A list of column names with ALIGN

```
%DEFINE ALIGN="YES"
...
%FUNCTION (DTW_SQL) myfunc() {
select * from MyTable
%report{
Your query was on these columns: ${NLIST}.
%row {
...
%}
%}
%}
```

The list of column names uses a space between column names with ALIGN set to YES.

Example 2: A %LIST variable to change the separator to " | "

```
%DEFINE %LIST " | " NLIST
...
%FUNCTION (DTW_SQL) myfunc() {
select * from MyTable
%report{
Your query was on these columns: ${NLIST}.
%row {
...
%}
%}
%}
```

NUM_COLUMNS

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

The number of table columns that Net.Data is processing in the report block; the columns are returned by a function call or query.

You can reference NUM_COLUMNS in REPORT and ROW blocks.

Examples

Example 1: NUM_COLUMNS used as a variable reference with NLIST

```
%REPORT{
Your query result has $(NUM_COLUMNS) columns: $(NLIST).
...
%}
```


NUM_ROWS

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
					X			

Purpose

The number of rows in the table that Net.Data is processing in the REPORT block. The number of rows is affected by the value of the *upper limit* parameter defined for the Net.Data table holding the data. For example, if *upper limit* is set to 30, but the SELECT statement returns 1000 rows, the value of NUM_ROWS is 30. Additionally, if *upper limit* is set to 30 and the SELECT statement returns 20 rows, NUM_ROWS equals 20. See “TABLE Statement” on page 51 for more information about the TABLE statement and the *upper limit* parameter.

NUM_ROWS is not affected by the value of START_ROW_NUM as long as START_ROW_NUM is not passed to the language environment. For example, if START_ROW_NUM is set to 5 (specifying that the table displayed on the Web page should be populated starting with row 5) and the SELECT statement returns 25 rows, NUM_ROWS is set to 25, not 21. The first four rows are discarded from the table, but are included in the value of NUM_ROWS. However, if START_ROW_NUM is passed to the language environment, then NUM_ROWS will only contain the number of rows starting at the row specified by START_ROW_NUM. In the example above, NUM_ROWS will be set to 21.

You can reference NUM_ROWS in REPORT and ROW blocks.

Examples

Example 1: Displays the number of names being processed in the REPORT block

```
%DEFINE DTW_SET_TOTAL_ROWS="YES"
%DEFINE RPT_MAX_ROWS="10"

%REPORT{
<h2>E-mail directory</h2>
<ul>
%ROW{
<li>Name: <a href="mailto:$(V1)">$(V2)</a><br />
Location: $(V3)
%}
</ul>
Names displayed: $(NUM_ROWS)<br />
Names found: $(TOTAL_ROWS)
%}
```

ROW_NUM

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

A table variable whose value Net.Data increments each time a row is processed in a Net.Data table. The variable acts as a counter and its value is the number of the current row being processed.

RPT_MAX_ROWS can affect the value of ROW_NUM. For example, if 100 rows are in a table, and you have set RPT_MAX_ROWS to 20, the final value of ROW_NUM is 20, because row 20 was the last row processed.

You can reference ROW_NUM only from within a ROW block.

Examples

Example 1: Populates a column in the HTML output by using ROW_NUM to label each row in the table

```
%REPORT{
<table border="1">
<tr><td> Row Number </td> <td> Customer </td></tr>
%ROW{
<tr><td> $(ROW_NUM) </td> <td> $(V_custname) </td></tr>
%}
</table>
%}
```

The REPORT block produces a table like the one shown below.

Row Number	Customer
1	Jane Smith
2	Jon Chiu
3	Frank Nguyen
4	Mary Nichols

TOTAL_ROWS

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

The total number of rows a query returns, no matter what the value of *upper_limit* for the TABLE language construct. For example, if RPT_MAX_ROWS is set to display a maximum of 20 rows, but the query returns 100 rows, this variable is set to 100 after ROW processing.

Operating system differences:

- On the OS/400 operating system, this variable can be referenced anywhere in a REPORT or ROW block.
- On the OS/390, OS/2, Windows NT, and UNIX operating systems, this variable can be referenced in the REPORT footer, only.

Language Environment Restriction: Use this variable only with the following database language environments:

- SQL
- ODBC
- Oracle

Required: You must set DTW_SET_TOTAL_ROWS to YES to use this variable. See “DTW_SET_TOTAL_ROWS” on page 90 for more information.

Examples

Example 1: Displays the total number of names found

```
%DEFINE DTW_SET_TOTAL_ROWS="YES"

%REPORT{
<h2>E-mail directory</h2>
<u1>
%ROW{
<li>Name: <a href="mailto:$(V1)">$(V2)</a><br />
Location: $(V3)</li>
%}
</u1>
Names found: $(TOTAL_ROWS)
%}
```

V_columnName

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

The value for the specified column name for the current row. The variable is not set for undefined column names. A query containing two column names with the same name gives unpredictable results. Consider using an AS clause in your SQL to rename duplicate column names.

You can reference *V_columnName* only within a ROW block.

Net.Data assigns the variable for each column in the table; use the variable in a variable reference, specifying the name of the column you want to reference. To use this variable outside the block, assign the value of *V_columnName* to a previously defined global variable or an OUT or INOUT function parameter variable.

Values

V_columnName

Table 1. *V_columnName* Values

Values	Description
<i>columnName</i>	The column name in current row of the database table.

Examples

Example 1: Using *V_columnName* as a variable reference

```
%FUNCTION(DTW_SQL) myQuery() {  
  SELECT NAME, ADDRESS from $(qtable)  
  %REPORT{  
  
    %ROW{  
  
      Value of NAME column in row $(ROW_NUM) is $(V_NAME).<br />  
    %}  
    %}  
    %}
```

VLIST

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

A list of all the field values for the current row being processed in a ROW block.

You can reference VLIST only within a ROW block. The default separator is a space.

Net.Data assigns the variable for each row in the table; reference the variable to obtain the values of all the fields in the current row. To use this variable outside the block, assign the value of VLIST to a previously defined global variable or an OUT or INOUT function parameter variable.

Examples

Example 1: Using list tags to display query results

```
%DEFINE ALIGN="YES"

%REPORT{
Here are the results of your query:
<ol>
%ROW{
<li>$(VLIST)</li>
%}
</ol>
%}
```

Example 2: Using a list variable to change the separator to <p>

```
%DEFINE %LIST "<br />" VLIST

%REPORT{
Here are the results of your query:
%ROW{
<hr />$(VLIST)
%}
%}
```

Vn

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

The value for the specified column number *n* for the current row.

You can reference *Vn* only within a ROW block.

Net.Data assigns the variable for each field in the table; use the variable in a variable reference, specifying the number of the field you want to reference. To use this variable outside the block, assign the value of *Vn* to a previously defined global variable or an OUT or INOUT function parameter variable.

Examples

Example 1: Report displaying an HTML table

```
%REPORT{
<h2>E-mail directory</h2>
<table border="1" cellpadding="3">
<tr><td>Name</td><td>E-mail address</td><td>Location</td></tr>
%ROW{
<tr><td>$(V1)</td>
<td><a href="mailto:$(V2)">$(V2)</a></td>
<td>$(V3)</td></tr>
%}
</table>
%}
```

The second column shows the e-mail address. You can send the person a message by clicking on the link.

Net.Data Report Variables

These variables help you customize your reports. Each variable has a default value. You can override the default value by assigning a new value to the variable.

- “ALIGN” on page 75
- “DTW_DEFAULT_REPORT” on page 76
- “DTW_HTML_TABLE” on page 77
- “RPT_MAX_ROWS” on page 78
- “START_ROW_NUM” on page 79

ALIGN

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Controls leading and trailing spaces used with the table processing variables NLIST and VLIST.

Performance Tip: Use ALIGN only when necessary as it requires that Net.Data determine the maximum column length for all columns in the table to calculate padding requirements. This process can impact performance.

When set to YES, ALIGN provides padding to align table processing variables for display. If you want to embed query results in HTML links or form actions, use the default value of NO to prevent Net.Data from surrounding report variables with leading and trailing spaces.

Specify the value of this variable using a DEFINE statement or with the @DTW_ASSIGN() function.

Values

ALIGN="YES" | "NO"

Table 2. ALIGN Values

Values	Description
YES	Net.Data adds leading and trailing spaces to report variables with spaces to align them for display.
NO	Net.Data does not add leading or trailing spaces. NO is the default.

Examples

Example 1: Using the ALIGN variable to separate each column by a space

```
%DEFINE ALIGN="YES"
<p>Your query was on these columns: $(NLIST)</p>
```

DTW_DEFAULT_REPORT

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Determines whether Net.Data generates a default report for functions that have no REPORT block. When this variable is set to YES, Net.Data generates the default report. When set to NO, Net.Data suppresses default report generation.

Suppressing the default report is useful, for example, if you receive the results of a function call in a table variable and want to pass the results to a different function to process.

Specify the value of this variable using a DEFINE statement or with the @DTW_ASSIGN() function.

Values

DTW_DEFAULT_REPORT="YES"|"NO"|"MULTIPLE"

Table 3. DTW_DEFAULT_REPORT Values

Values	Description
YES	Net.Data generates the default report for functions without REPORT blocks and displays the results at the browser. YES is the default. For OS/390: Net.Data generates default reports for each result set or output table that is not assigned to a REPORT block.
NO	Net.Data discards the default report for functions without REPORT blocks.
MULTIPLE	Net.Data generates default reports for result sets or output tables that are not assigned to a REPORT block, in functions with multiple REPORT blocks For OS/390: MULTIPLE is not supported

Examples

Example 1: Overriding the default report generated by Net.Data

```
%DEFINE DTW_DEFAULT_REPORT="NO"
```


DTW_HTML_TABLE

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Displays results in an HTML table instead of displaying the table in a text-type format (that is, using the TABLE tags rather than the PRE tags). This variable has no effect in an XML block.

The generated TABLE tag includes a border and cell-padding specification:

```
<table border cellpadding="2">
```

Specify the value of this variable using a DEFINE statement or with the @DTW_ASSIGN() function.

Values

DTW_HTML_TABLE="YES"|"NO"

Table 4. DTW_HTML_TABLE Values

Values	Description
YES	Displays table data using HTML table tags.
NO	Displays table data in a text format, using PRE tags. NO is the default.

Examples

Example 1: Displays results from an SQL function with HTML tags

```
%DEFINE DTW_HTML_TABLE="YES"
```

```
%FUNCTION(DTW_SQL){  
SELECT NAME, ADDRESS FROM $(qTable)  
%}
```

RPT_MAX_ROWS

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Specifies the number of rows in a table that are processed in a function REPORT block or during the generation of a default report if a REPORT block is not specified.

The database language environments use this variable to limit the number of rows returned, which can substantially improve performance for large result sets. Use this variable with START_ROW_NUM to break queries with large result sets into smaller tables, each on its own HTML page.

Specify the value of this variable using a DEFINE statement or with the @DTW_ASSIGN() function.

Values

RPT_MAX_ROWS="ALL"|"0"|"number"

Table 5. RPT_MAX_ROWS Values

Values	Description
ALL	Indicates that there is no limit on the number of rows to be displayed in a table generated by a function call. All rows will be displayed.
0	Specifies that all rows in the table will be displayed. This value is the same as specifying ALL.
number	A positive integer indicating the maximum number of rows to be displayed in a table generated by a function call. If the FUNCTION block contains a REPORT and ROW block, this number specifies the number of times the ROW block is executed.

Examples

Example 1: Defines RPT_MAX_ROWS in a DEFINE statement

```
%DEFINE RPT_MAX_ROWS="20"
```

The above method limits the number of rows any function returns to 20 rows.

Example 2: Uses HTML input to define the variable with an HTML form

```
Maximum rows to return (0 for no limit):  
<input type="text" name="rpt_max_rows" size="3" />
```

The lines in the above example can be placed in a FORM tag to let the application users set the number of rows they want returned from a query.

START_ROW_NUM

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Specifies the starting row number in a table that will get processed in a function REPORT block, during the generation of a default report if a REPORT block is not specified, or the setting of a Net.Data table variable.

The database language environments use this variable to determine the starting row in the result set to begin processing. To substantially improve performance for large result sets, use this variable with RPT_MAX_ROWS to break queries with large result sets into smaller tables.

OS/400, Windows NT, OS/2, and UNIX users: To pass this variable to the language environment, include it as an IN parameter in the database language environment's ENVIRONMENT statement in the Net.Data initialization file. To learn more about the database language environment statement, see the configuration chapter of the *Net.Data Administration and Programming Guide* for your operating system.

OS/390 users: START_ROW_NUM is implicitly passed to the database language environments when it is defined in the macro.

Specify the value of this variable using a DEFINE statement or with the @DTW_ASSIGN() function.

Values

START_ROW_NUM="number"

Table 6. START_ROW_NUM Values

Values	Description
<i>number</i>	A positive integer indicating the row number with which to begin displaying a report. The default value is 1. If START_ROW_NUM is specified in a database language environment's environment statement in the initialization file, this number specifies the row number of the result set processed by the database language environment.

Examples

Example 1: Scrolling with HTML form Next and Previous buttons

```
%define START_ROW_NUM = "1"
%define RPT_MAX_ROWS = "13"
%define DTW_SET_TOTAL_ROWS = "yes"
%function(DTW_SQL) select() {
  select * from usrnd01.customer
  %REPORT {
    @DTW_ADD(START_ROW_NUM, RPT_MAX_ROWS, next_row_num)
    @DTW_SUBTRACT(START_ROW_NUM, RPT_MAX_ROWS, prev_row_num)
    @DTW_SUBTRACT(next_row_num, "1", last_row)
    <h2>Reporting rows $(START_ROW_NUM) through $(last_row)</h2>
    <table BORDER="2">
      <tr><th>$(N1)</th><th>$(N2)</th><th>$(N3)</th>
        <th>$(N4)</th><th>$(N5)</th></tr>
    %ROW {
```

```
|<td>$(V1)</td><td>$(V2)</td><td>$(V3)</td>
  <td>$(V4)</td><td>$(V5)</td></tr>
%}
</table>
<p>&nbsp;</p>
<p><h3>
%IF (START_ROW_NUM > RPT_MAX_ROWS)
  <a href="report?START_ROW_NUM=$(prev_row_num)">PREVIOUS</a> |||
%ELSE
  PREVIOUS |||
%ENDIF
%IF (next_row_num < TOTAL_ROWS)
  <a href="report?START_ROW_NUM=$(next_row_num)">NEXT</a>
%ELSE
  NEXT
%ENDIF
</h3>
TOTAL_ROWS = $(TOTAL_ROWS)</p>
%}
%}
%html(report) {
<html><body>
@select()
</body></html>
%}

|  |

```

Net.Data Language Environment Variables

Use these variables with functions to help you customize the way FUNCTION blocks are processed by language environments. Each variable has a default value. You can override the default value by assigning a new value to the variable.

- “DATABASE” on page 81
- “DB_CASE” on page 83
- “DB2PLAN” on page 84
- “DB2SSID” on page 85
- “DTW_APPLET_ALTTTEXT” on page 86
- “DTW_EDIT_CODES” on page 87
- “DTW_PAD_PGM_PARMS” on page 88
- “DTW_SAVE_TABLE_IN” on page 89
- “DTW_SET_TOTAL_ROWS” on page 90
- “LOCATION” on page 91
- “LOGIN” on page 92
- “NULL_RPT_FIELD” on page 93
- “PASSWORD” on page 94
- “SHOWSQL” on page 95
- “SQL_STATE” on page 96
- “TRANSACTION_SCOPE” on page 97

DATABASE

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X		X	X	X	X

Purpose

Specifies the database or ODBC data source to access when calling a database function. This variable can be changed multiple times within a macro to access multiple databases or ODBC data sources.

Requirement: For the value of this variable in the macro to take effect, it must be listed on the ENVIRONMENT statement for the SQL language environment. See the Administration and Programming Guide for your operating system for more information on environment statements.

OS/400 operating system: This variable is optional. Net.Data, by default, specifies DATABASE="*LOCAL"; the DTW_SQL language environment uses the local relational database directory entry.

Windows NT, OS/2, and UNIX operating systems: Define this variable before calling any database function, except when using the DTW_ORA (Oracle) language environment. Additionally, you must use Live Connection when accessing multiple databases from the same HTML block and through the same language environment.

Specify the value of this variable using a DEFINE statement or with the @DTW_ASSIGN() function.

Values

DATABASE="dbname"

Table 7. DATABASE Values

Values	Description
dbname	The name of the database Net.Data connects to.

Examples

Example 1: Specifies to connect to the CELDIAL database for any SQL operations

```
%DEFINE DATABASE="CELDIAL"

%FUNCTION (DTW_SQL) getRpt() {
  SELECT * FROM customer
%}

%HTML (Report) {
  %INCLUDE "rpthead.htm"
  @getRpt()
  %INCLUDE "rptfoot.htm"
%}
```

The database CELDIAL is accessed when the function getRpt is called.

Example 2: Overrides previous DATABASE definitions with DTW_ASSIGN

```
%DEFINE DATABASE="DB2C1"
...
%HTML(monthRpt){
  @DTW_ASSIGN(DATABASE, "DB2D1")
}
```

```
%INCLUDE "rpthead.htm"  
@getRpt()  
%INCLUDE "rptfoot.htm"  
%}
```

The HTML block queries the database DB2D1, regardless of what the previous value for DATABASE was.

DB_CASE

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Specifies which case to use for SQL commands and converts all characters to either upper or lower case. If this variable is not defined, the default action is to not convert the SQL command characters.

Specify the value of this variable using a DEFINE statement or with the @DTW_ASSIGN() function.

Values

DB_CASE="UPPER" | "LOWER"

OS/390 Only:

DB_CASE="UPPER" | "LOWER" | ""

Table 8. DB_CASE Values

Values	Description
UPPER	Converts the entire SQL statement to upper case.
LOWER	Converts the entire SQL statement to lower case.
(empty string)	OS/390 Only: Does not convert. Resets the string to the original value.

Examples

Example 1: Specifies upper case for all SQL commands

```
%DEFINE DB_CASE="UPPER"
```

DB2PLAN

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
				X				

Purpose

Allocates a plan for a connection to a local DB2 subsystem. The variable specifies the name of a plan for the Net.Data SQL language environment at the local DB2 subsystem that Net.Data will access.

Specify the value of this variable using a DEFINE statement or with the @DTW_ASSIGN() function.

Requirement: For the value of this variable in the macro to take effect, it must be listed on the ENVIRONMENT statement for the SQL language environment. See the *Administration and Programming Guide* for your operating system for more information on environment statements.

Values

DB2PLAN="*plan_name*"

Table 9. DB2PLAN Values

Values	Description
<i>plan_name</i>	The name of the DB2 plan. The name can be eight characters or less.

Examples

Example 1: Specifies the plan in the DEFINE statement

```
%DEFINE DB2PLAN="DTWNDPLN"
```


DB2SSID

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
				X				

Purpose

Establishes a connection to a local DB2 subsystem. The variable specifies the subsystem ID of the local DB2 subsystem that Net.Data will access. Only one local database connection is allowed for each macro.

Requirement: For the value of this variable in the macro to take effect, it must be listed on the ENVIRONMENT statement for the SQL language environment. See the *Administration and Programming Guide* for your operating system for more information on environment statements.

Values

DB2PLAN="*subsystem_id*"

Table 10. DB2SSID Values

Values	Description
<i>subsystem_id</i>	The name of the DB2 subsystem. The name can be eight characters or less.

Examples

Example 1: Specifies a subsystem ID in the DEFINE statement

```
%DEFINE DB2SSID="DBNC"
```

DTW_APPLET_ALTTEXT

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Displays HTML tags and text to browsers that do not recognize the APPLET tag and is used with the the Applet built-in functions.

Specify the value of this variable using a DEFINE statement or with the @DTW_ASSIGN() function.

Values

DTW_APPLET_ALTTEXT="*text_and_markup*"

Table 11. DTW_APPLET_ALTTEXT Values

Values	Description
<i>text_and_markup</i>	Text and markup that should be displayed to browsers that do not recognize the APPLET tag.

Examples

Example 1: Alternate text that indicates a Web browser restriction

```
%DEFINE DTW_APPLET_ALTTEXT="<p>Sorry, your browser is not java-enabled.</p>"
```

DTW_EDIT_CODES

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
					X			

Purpose

Converts NUMERIC, DECIMAL, INTEGER and SMALLINT data types that are returned as a result of an SQL operation for the DTW_SQL language environment. The variable DTW_EDIT_CODES is a string of characters that correspond to the resulting columns of the table that DTW_SQL LE will build; for example, the fifth character in DTW_EDIT_CODES will be applied to the fifth column of the result set if that column is one of the supported types. This single character can be any of the supported system supplied edit codes that are defined in *Data Description Specification Reference*.

For example, a DECIMAL(6,0) field would normally be displayed as the character string '112698'. By specifying an edit code of 'Y' for that column in the variable DTW_EDIT_CODES, the corresponding column in the resulting table is displayed as a character string that represents the date of '11/26/98'.

Tip: Applying a user-supplied edit code to a column that results in a character string with non-numeric characters (such as commas or currency symbols) can cause syntax errors if the character string is sent back to the server for subsequent processing within a Net.Data macro. For example, the non-numeric column value might be used for numeric comparisons in subsequent DTW_SQL functions calls, causing syntax errors.

Specify the value of this variable using a DEFINE statement or with the @DTW_ASSIGN() function.

Values

DTW_EDIT_CODES="edit_code"

Table 12. DTW_EDIT_CODES Values

Values	Description
edit_code	Specifies a string of characters that correspond to the resulting columns of the table that the SQL language environment builds.

Examples

Example 1:

```
@DTW_ASSIGN(DTW_EDIT_CODES "JJLJJ*****Y")
```

DTW_PAD_PGM_PARMS

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
					X			

Purpose

Indicates to a language environment whether character parameters (data type of CHAR or CHARACTER) are to be padded with blanks when they are being passed to a program or stored procedure.

For IN or INOUT parameters, if the length of parameter value is less than the precision that is specified, blanks are inserted to the right of the parameter value until the length of the parameter value is the same as the precision.

For OUT parameters, the parameter value is set to *precision* blanks.

After the call to the program or stored procedure, all trailing blanks are removed from OUT and INOUT parameter values.

Set this variable in the Net.Data initialization file to specify a value for all of your macros. You can override the value by defining it in the macro. If DTW_PAD_PGM_PARMS is not defined in the macro, it uses the value in the Net.Data initialization file.

DTW_PAD_PGM_PARMS is supported by the Direct Call and SQL language environments.

Values

DTW_PAD_PGM_PARMS="YES" | "NO"

Table 13. DTW_PAD_PGM_PARMS Values

Values	Description
YES	All IN and INOUT character parameter values are left justified and padded with blanks for the defined precision of the parameter, before the parameters are passed to a program or stored procedure. Trailing blanks are removed after the call to a program or stored procedure.
NO	No padding is added to character parameter values (values are NULL-terminated) when passing parameters to programs or stored procedures. Trailing blanks are not removed after calling a program or stored procedure.

Examples

Example 1: Pads parameters with blanks

DTW_PAD_PGM_PARMS="YES"

DTW_SAVE_TABLE_IN

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Identifies a table variable that the SQL language environment uses to store table data from a query. This table can then be used later, for example, in a REXX program that analyzes table data.

Specify the value of this variable using a DEFINE statement or with the @DTW_ASSIGN() function.

Values

DTW_SAVE_TABLE_IN="table_name_var"

Table 14. DTW_SAVE_TABLE_IN Values

Values	Description
table_name_var	The name of a table for the SQL language environment to store table data from a query.

Examples

Example 1: A previously-defined table variable used in a REXX call

```
%DEFINE theTable = %TABLE(2)
%DEFINE DTW_SAVE_TABLE_IN = "theTable"

%FUNCTION(DTW_SQL) doQuery() {
  SELECT MODNO, COST, DESCRIP FROM EQPTABLE
  WHERE TYPE='MONITOR'
%}

%FUNCTION(DTW_REXX) analyze_table(myTable) {
  %EXEC{ anzTbl.cmd %}
%}

%HTML(doTable) {
  @doQuery()
  @analyze_table(theTable)
%}
```

A REXX FUNCTION block calls the REXX program anzTbl.cmd, which uses the table variable theTable to analyze data in the table. The variable theTable was returned from a previous SQL function call.

DTW_SET_TOTAL_ROWS

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Specifies to a database language environment to assign the total number of rows in the result set to TOTAL_ROWS. The default setting is to not assign the number; therefore, DTW_SET_TOTAL_ROWS must be set to YES to use TOTAL_ROWS in your macro.

Specify the value of this variable using a DEFINE statement or with the @DTW_ASSIGN() function.

OS/400, OS/2, Windows NT, and UNIX users: To pass this variable to the language environment, include it as an IN variable in the database language environment's ENVIRONMENT statement in the Net.Data initialization file. See the configuration chapter of *Net.Data Administration and Programming Guide* to learn more about the database language environment statement.

OS/390 users: DTW_SET_TOTAL_ROWS is implicitly passed to the database language environments when it is defined in the macro.

Performance tip: Setting DTW_SET_TOTAL_ROWS to YES affects performance because to determine the total rows, the database language environment requires that all rows be retrieved.

Values

DTW_SET_TOTAL_ROWS="YES"|"NO"

Table 15. DTW_SET_TOTAL_ROWS Values

Values	Description
YES	Assigns the value of the total number of rows to the TOTAL_ROWS variable.
NO	Net.Data does not set the TOTAL_ROWS variable and TOTAL_ROWS cannot be referenced in a macro. NO is the default.

Examples

Example 1: Defines DTW_SET_TOTAL_ROWS for using TOTAL_ROWS

```
%DEFINE DTW_SET_TOTAL_ROWS="YES"

...

%FUNCTION (DTW_SQL) myfunc() {
select * from MyTable
%report {
...
%row
...
%}
<p>Your query is limited to $(TOTAL_ROWS) rows. The query returned too many rows.
%}
%}
```

LOCATION

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
				X				

Purpose

Establishes a connection to a remote database server. The variable specifies the name by which the remote server is known to the local DB2 subsystem. The value of LOCATION must be defined in the SYSIBM.SYSLOCATIONS table of the Communications Database (CDB). If this variable is not defined within a macro, any SQL requests made by the macro are executed at the local DB2 subsystem.

Requirement: For the value of this variable in the macro to take effect, it must be listed on the ENVIRONMENT statement for the SQL language environment. See the *Net.Data Administration and Programming Guide* for your operating system for more information on environment statements.

Specify the value of this variable using a DEFINE statement or with the @DTW_ASSIGN() function.

Values

LOCATION="remote_dbase_name"

Table 16. LOCATION Values

Values	Description
remote_dbase_name	The name of a valid remote database server that is defined in the SYSIBM.SYSLOCATIONS table of the CDB. The name can be eight characters or less.

Examples

Example 1: Defines the remote database location in the DEFINE statement

```
%DEFINE LOCATION="QMFDJ00"
```

LOGIN

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X		X	X	X	X

Purpose

Provides access to protected data by passing a user ID to the database language environment. Use this variable with PASSWORD to incorporate the security algorithms of DB2.

OS/400 Users: OS/400 ignores both LOGIN and PASSWORD if the DATABASE variable is not defined or if it is set to a value of *"*LOCAL"*. Database access is routed through the user profile under which Net.Data is running.

Security tip: While you can code this value in the Net.Data macro, it is preferable to have the application user enter user IDs in an HTML form. Additionally, using the default value of the Web server ID provides a level of access that might not meet your security needs.

Requirement: For the value of this variable in the macro to take effect, it must be listed on the ENVIRONMENT statement for the SQL language environment. See the *Net.Data Administration and Programming Guide* for your operating system for more information on environment statements.

Specify the value of this variable using a DEFINE statement or with the @DTW_ASSIGN() function.

Values

LOGIN=*database_user_id*

Table 17. LOGIN Values

Values	Description
<i>database_user_id</i>	A valid database user ID. The default is to use the user ID that started the Web server.

Examples

Example 1: Restricting access to the user ID, DB2USER

```
%DEFINE LOGIN="DB2USER"
```

Example 2: Using an HTML form input line

```
USERID: <input type="text" name="login" size="6" />
```

This example shows a line you can include as part of an HTML form for application users to enter their user IDs.

NULL_RPT_FIELD

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
					X			

Purpose

Specifies a string the user can provide to the DTW_SQL language environment to represent NULL values that are returned in an SQL result set.

Specify the value of this variable using a DEFINE statement or with the @DTW_ASSIGN() function.

Values

NULL_RPT_FIELD="null_char"

Table 18. NULL_RPT_FIELD Values

Values	Description
<i>null_char</i>	Specifies a string to represent NULL values that are returned in an SQL result set. The default is an empty string.

Examples

Example 1: Specifies a string representing NULL values in the SQL language environment

```
%DEFINE NULL_RPT_FIELD = "++++"
```

PASSWORD

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X		X	X	X	X

Purpose

Provides access to protected data by passing a password to the database language environment. Use this variable with LOGIN to incorporate the security algorithms of DB2.

OS/400 Users: OS/400 ignores both LOGIN and PASSWORD if the DATABASE variable is not defined or if it is set to a value of `"*LOCAL"`. Database access is routed through the user profile under which Net.Data is running.

Security tip: While you can code this value in the Net.Data macro, it is preferable to have application users enter passwords in an HTML form.

Specify the value of this variable using a DEFINE statement or with the @DTW_ASSIGN() function.

Values

PASSWORD="*password*"

Table 19. PASSWORD Values

Values	Description
<i>password</i>	Specifies a valid password to provide automatic access to the database language environment.

Examples

Example 1: Restricting access to application users with the password NETDATA

```
%DEFINE PASSWORD="NETDATA"
```

Example 2: HTML form input line

```
PASSWORD: <input type="password" name="password" size="8" />
```

This example shows a line you can include as part of an HTML form for application users to input their own passwords.

SHOWSQL

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Hides or displays the SQL of the query used on the Web browser. Displaying the SQL during testing is especially helpful when you are debugging your Net.Data macros. SHOWSQL can only be used if DTW_SHOWSQL is set to YES in the Net.Data configuration file. For more information about the DTW_SHOWSQL configuration variable, see the configuration chapter in *Net.Data Administration and Programming Guide* for your operating system.

Specify the value of this variable using a DEFINE statement or with the @DTW_ASSIGN() function.

Values

SHOWSQL="YES"|"NO"

Table 20. SHOW_SQL Values

Values	Description
YES	Displays the SQL of the query sent to the database.
NO	Hides the SQL of the query sent to the database. NO is the default.

Restriction: SHOWSQL generates HTML or XML markup. When used within other presentation statements, such as JavaScript, syntax errors can occur.

Examples

Example 1: Displays all SQL queries

In the configuration file:

```
DTW_SHOWSQL YES
```

In the macro:

```
%DEFINE SHOWSQL="YES"
```

Example 2: Specifying whether to display SQL using HTML form input.

In the configuration file:

```
DTW_SHOWSQL YES
```

In the macro:

```
SHOWSQL: <input type="radio" name="showsql" value="yes" /> Yes  
         <input type="radio" name="showsql" value="" checked /> No
```

SQL_STATE

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Accesses or displays the SQL state value returned from the database.

This variable is a predefined variable and its value cannot be modified. Use the variable as a variable reference.

Examples

Example 1: Displays the SQL state in the REPORT block

```
%FUNCTION (DTW_SQL) val1() {  
  select * from customer  
%REPORT {  
  ...  
%ROW {  
  ...  
%}  
  SQLSTATE=$(SQL_STATE)  
%}
```

TRANSACTION_SCOPE

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Specifies the transaction scope for SQL commands, determining whether Net.Data issues a COMMIT after each SQL command or after all SQL commands in an HTML block complete successfully. When you specify that all SQL commands must complete successfully before a commit, an unsuccessful SQL command causes all previously executed SQL to *the same database* in that block to be rolled back.

For the TRANSACTION_SCOPE variable to take effect, include it in the ENVIRONMENT statement in the Net.Data configuration file. You can then specify the value of this variable using a DEFINE statement or with the @DTW_ASSIGN() function.

Consistency considerations: On operating systems other than OS/400 and OS/390, updates to the database receiving unsuccessful responses might be rolled back while the updates to the other databases accessed in the same HTML block might be committed when all of the following conditions are true:

- TRANSACTION_SCOPE = "MULTIPLE" is specified
- Multiple databases are accessed in one HTML block (which is possible when using Live Connection)
- An unsuccessful response is returned from an SQL request

If you access multiple databases from Net.Data on OS/400 or using IBM's DataJoiner, you can achieve multiple database update coordination and consistency when updating from Net.Data.

On OS/400 and OS/390, TRANSACTION_SCOPE = "MULTIPLE" causes all IBM database updates issued from a single HTML block to be committed or rolled back together.

On operating systems other than OS/400, the REXX, Perl, and Java language environments run in their own separate operating system processes. Thus, any database updates you issue from these language environments are committed or rolled back separately from database updates issued from a Net.Data macro, regardless of the Net.Data TRANSACTION_SCOPE value.

Values

TRANSACTION_SCOPE="SINGLE" | "MULTIPLE"

Table 21. TRANSACTION_SCOPE Values

Values	Description
SINGLE	Net.Data issues a COMMIT after each SQL command in an HTML block successfully completes.
MULTIPLE	Specifies the Net.Data issues a COMMIT only after all SQL commands in an HTML block complete successfully. MULTIPLE is the default.

Examples

Example 1: Specifies to issue a COMMIT after each transaction

```
%DEFINE TRANSACTION_SCOPE="SINGLE"
```

Net.Data Miscellaneous Variables

These variables are Net.Data-defined variables that you can use to affect Net.Data processing, find out the status of a function call, and obtain information about the result set of a database query, as well as determine information about file locations and dates. You might find these variables useful in functions you write or use them when testing your Net.Data macros.

- “DTW_CURRENT_FILENAME” on page 99
- “DTW_CURRENT_LAST_MODIFIED” on page 100
- “DTW_DEFAULT_MESSAGE” on page 101
- “DTW_LOG_LEVEL” on page 102
- “DTW_MACRO_FILENAME” on page 103
- “DTW_MACRO_LAST_MODIFIED” on page 104
- “DTW_MBMODE” on page 105
- “DTW_MP_PATH” on page 106
- “DTW_MP_VERSION” on page 107
- “DTW_PRINT_HEADER” on page 108
- “DTW_REMOVE_WS” on page 109
- “DTW_USE_DB2_PREPARE_CACHE” on page 110
- “RETURN_CODE” on page 112

DTW_CURRENT_FILENAME

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

The name and extension of the current input file. The input file is either a Net.Data macro or a file specified in an INCLUDE statement.

This variable is a predefined variable and its value cannot be modified. Use the variable as a variable reference.

Examples

<p>This file is <i>\$(DTW_CURRENT_FILENAME)</i>,
and was updated on \$(DTW_CURRENT_LAST_MODIFIED).</p>

DTW_CURRENT_LAST_MODIFIED

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

The date and time the current file was last modified. The current file can be a Net.Data macro or a file specified in an INCLUDE statement. The output format is determined by the system on which Net.Data runs.

This variable is a predefined variable and its value cannot be modified. Use the variable as a variable reference.

Examples

<p>This file is <i>\$(DTW_CURRENT_FILENAME)</i>,
and was updated on \$(DTW_CURRENT_LAST_MODIFIED).</p>

DTW_DEFAULT_MESSAGE

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Contains the message text returned from a call to a built-in function or to language environment when an error occurs.

You can use the DTW_DEFAULT_MESSAGE variable in any part of the Net.Data macro.

This variable is a predefined variable, its value cannot be modified. Use the variable as a variable reference.

Examples

The default text for when a function returns a non-zero return code

```
%MESSAGE{  
default: {<h2>Net.Data received return code: $(RETURN_CODE).  
Error message is $(DTW_DEFAULT_MESSAGE)</h2> %} : continue  
%}
```

The user sees the error message with additional information, if a function returns a return code other than 0.

DTW_LOG_LEVEL

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X			X	X	X

Purpose

The level of messages that Net.Data writes to the log file.

You can specify the value of this variable using a DEFINE statement or with the @DTW_ASSIGN() function.

Requirement: Define DTW_LOG_DIR in the Net.Data initialization file to initiate logging; otherwise Net.Data does not log messages when you specify the DTW_LOG_LEVEL variable in the macro.

Values

DTW_LOG_LEVEL="OFF|ERROR|WARNING"

Table 22. DTW_LOG_LEVEL Values

Values	Description
OFF	Net.Data does not log errors. OFF is the default.
ERROR	Net.Data logs error messages.
WARNING	Net.Data logs warnings, as well as error messages.

Examples

```
%DEFINE DTW_LOG_LEVEL="ERROR"
```

DTW_MACRO_FILENAME

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

The name and extension of the current Net.Data macro.

This variable is a predefined variable and its value cannot be modified. Use the variable as a variable reference.

Examples

<p>This Net.Data macro is <i>\$(DTW_MACRO_FILENAME)</i>,
and was updated on \$(DTW_MACRO_LAST_MODIFIED).</p>

DTW_MACRO_LAST_MODIFIED

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

The date and time the Net.Data macro was last modified. The output format depends on the system on which Net.Data runs.

This variable is a predefined variable and its value cannot be modified. Use the variable as a variable reference.

Examples

<p>This Net.Data macro is <i>\$(DTW_MACRO_FILENAME)</i>,
and was updated on \$(DTW_MACRO_LAST_MODIFIED).</p>

DTW_MBMODE

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X		X	X	X

Purpose

Provides multibyte character set (MBCS) support for Net.Data built-in string and word functions. You can set this variable in the Net.Data initialization file, but you can use it in the macro to set or override the current setting.

Specify the value of this variable using a DEFINE statement or with the @DTW_ASSIGN() function.

OS/400 users: Net.Data for OS/400 automatically enables functions for MBCS support and does not need this variable. Net.Data for OS/400 ignores this variable in macros that are migrated to the OS/400 operating system.

Values

DTW_MBMODE="YES"|"NO"

Table 23. DTW_MBMODE Values

Values	Description
YES	Specifies MBCS support for string and word functions.
NO	Specifies that string and word functions do not have MBCS support. NO is the default.

Examples

Example 1: Overrides the value in the Net.Data initialization file.

In the initialization file:

```
DTW_MBMODE NO
```

In the macro:

```
%DEFINE DTW_MBMODE = "YES"
```

DTW_MP_PATH

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

The content of this variable specifies the full path and filename of the Net.Data executable.

This variable is a predefined variable and its value cannot be modified. Use the variable as a variable reference.

Examples

The Net.Data executable file is `${DTW_MP_PATH}`.

DTW_MP_VERSION

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

The version and release number of Net.Data running on the server.

This variable is a predefined variable and its value cannot be modified. Use the variable as a variable reference.

Examples

This Web application uses `$(DTW_MP_VERSION)`.

DTW_PRINT_HEADER

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Specifies whether or not Net.Data will automatically supply the HTTP header.

You must have this variable set before Net.Data processes any text sent to the Web browser, because Net.Data reads this variable once before displaying text and does not look at it again. Any changes to the DTW_PRINT_HEADER variable are ignored after Net.Data has sent text to the browser.

If you are using DTW_PRINT_HEADER to generate your own headers (DTW_PRINT_HEADER = "NO"), you must either ensure that DTW_REMOVE_WS is set to "NO" or use the DTW_rHEXTOCHAR() built-in function to generate a new line after the HTTP headers.

Specify the value of this variable using a DEFINE statement, or if outside of a block you can specify it using the @DTW_ASSIGN() function.

Values

DTW_PRINT_HEADER="YES"|"NO"

Table 24. DTW_PRINT_HEADER Values

Values	Description
YES	Net.Data prints out the text Content-type: text/HTML or Content-type: text/xml for the HTTP header. YES is the default.
NO	Net.Data does not print out an HTTP header. You can generate custom HTTP header information.

Examples

Example 1: Setting DTW_PRINT_HEADER to NO to customize your own header.

```
%define DTW_REMOVE_WS="YES"
%define DTW_PRINT_HEADER="NO"
@DTW_ASSIGN(CRLF, "@DTW_rHEXTOCHAR("0D25")")
%HTML(report) {Expires: Thu, 31 Jan 2001 16:00:00 GMT$(CRLF)
Content-type: text/wml$(CRLF)}$(CRLF)
...
%}
```


DTW_REMOVE_WS

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

If you set the value of this variable to "YES" in the DEFINE block, Net.Data will remove extra white space in the resulting web pages. Use this variable with caution when the formatting of the output requires that the whitespace not be changed, for example:

- Text between <pre></pre> tags.
- Languages other than HTML, such as the JavaScript.

Values

DTW_REMOVE_WS="YES"|"NO"

Table 25. DTW_REMOVE_WS Values

Values	Description
YES	Net.Data compresses a sequence of two or more white spaces to one new-line character, generating shorter HTML result pages.
NO	Net.Data does not compress white spaces. NO is the default.

Examples

Example 1: Removing extraaneous white space

DTW_REMOVE_WS="YES"

DTW_USE_DB2_PREPARE_CACHE

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Specifies that Net.Data should take advantage of the DB2 prepare cache. If you have SQL statements where the only parts that change are the data in the WHERE clause conditions or in the individual values in a VALUES clause, then setting this variable to YES will improve the response time of those statements. Net.Data does this by assuming that variable references and function calls in an SQL statement are what changes from statement to statement, and the rest will be static. Therefore, when DB2 prepares the statement, it looks the same as a previous query and can make use of its cache. This feature will be most effective on queries that are executed frequently, where the data within the query changes just as frequently.

You can set this value by using a DEFINE statement or with the DTW_ASSIGN() function.

To activate this feature for all of your SQL statements by default, set the DTW_USE_DB2_PREPARE_CACHE configuration variable to "yes" in your Net.Data initialization file. See the *Net.Data Administration and Programming Guide* for more information on the configuration variable.

Restrictions:

- This feature will not work with SQL statements that use variable references or function calls to generate text such as column names, table names, or an entire WHERE clause. For example, the following statement is invalid for use with this feature:

```
SELECT $(col) FROM TAB1
```
- Special care must be taken to handle single quotes correctly in your referenced variables. For example, if the column returns a string that contains quotes, such as "O'Brien," use the DTW_ADDQUOTE() function to escape the string's single quotes.

Values

DTW_USE_DB2_PREPARE_CACHE [=] "YES"|"NO"

Table 26. DTW_USE_DB2_PREPARE_CACHE Values

Values	Description
YES	Specifies that Net.Data modify all SQL statements to take advantage of the prepare cache. You can disable this feature for a particular SQL statement by setting the macro variable to "NO" using %DEFINE or @DTW_ASSIGN().
NO	Specifies that Net.Data leave the SQL statement untouched. This is the default, unless the configuration variable is set to YES.

Examples

Example 1: A valid SQL statement for use with this feature.

```
%DEFINE DTW_USE_DB2_PREPARE_CACHE="YES"
...
%FUNCTION(DTW_SQL) myfunc(IN m, IN y) {
  select id, projname, due from projects
  where month = '$(m)' and year = '$(y)'
%}
```

If the projects table were instead a variable, such as \$(table1), the statement would be invalid for use with this feature.

RETURN_CODE

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

The return code returned by a call to a built-in function or a call to a language environment. Net.Data uses this value to process MESSAGE blocks. You can use this variable to determine whether a function call succeeded or failed. A value of zero indicates successful completion of a function call.

You can reference the RETURN_CODE variable in any part of the Net.Data macro.

This value is predefined; it is not recommended to modify the value. Use it as a variable reference.

Examples

A default message when a return code is not 0

```
%MESSAGE{  
default: "<h2>Net.Data received return code: $(RETURN_CODE)</h2>" : continue  
%}
```

If a function returns a return code other than 0, the default message is displayed.

Chapter 3. Net.Data Built-in Functions

Net.Data provides a wide variety of functions that you can use without creating your own FUNCTION blocks. Net.Data built-in functions are divided into the following categories:

- **General-purpose functions** help you develop Web pages with Net.Data and do not fit in the other categories. See “General Functions” on page 114.
- **Math functions** perform mathematical operations. See “Math Functions” on page 148.
- **String-manipulation functions** modify strings and characters. See “String Functions” on page 166.
- **Word-manipulation functions** modify words or sets of words. See “Word Functions” on page 193.
- **Table-manipulation functions** help you generate forms and reports from your table data. See “Table Functions” on page 203.
- **Flat-file interface functions** perform file input and output. See “Flat File Interface Functions” on page 246.
- **Web-registry functions** perform operations on a Web registry. See “Web Registry Functions” on page 280.
- **Persistent macro functions** support transaction processing in Net.Data. See “Persistent Macro Functions” on page 298

Although some function parameters are described as having type *integer* or *float*, the terms are used to denote a string that represents an integer or float value, respectively.

Function Names

Net.Data built-in functions begin with DTW, which is a reserved prefix. User-defined functions should not use this prefix.

Using the DTW prefix for functions that are not Net.Data built-in functions may result in unpredictable behavior.

Built-in function names are not case sensitive.

Input and Output Parameters

Functions can have parameter passing specifications that determine whether Net.Data uses the parameter for input, output, or both input and output. These parameter passing specifications are specified by the following keywords:

IN Specifies that the parameter passes input data to the language environment from Net.Data.

OUT Specifies that the parameter returns output data from the language environment to Net.Data.

INOUT

Specifies that the parameter passes input data to the language environment and returns output data from the language environment to Net.Data.

Function Result Formatting

Many functions have one or more of the following forms:

- Functions beginning with DTW_r and DTWR_r return their results to the function call, so they do not have an output parameter. This example shows the server time:

```
@DTW_rTIME().
```

- Functions beginning with DTW_m perform the function on multiple parameters. Each parameter behaves as both an input parameter and an output parameter. The function is performed on the parameter and the results are returned in the parameter. This example converts the three input parameters to all capital letters for a consistent look in the display:

```
@DTW_mUPPERCASE(model, style, shipNo)
Shipment $(shipNo) contains $(quantity) of model $(model) $(style).
```

- Other functions beginning with DTW_, DTWF_, and DTWR_ return their results in an output parameter. You must specify the output parameter. This example shows the server time:

```
@DTW_TIME(nowTime)
Current local time is $(nowTime).
```

- Functions beginning with DTWA_ have no output parameters.

Function Parameter Rules

Place function parameters in the correct order. You must specify all *input* parameters before the last input parameter can be specified, or specify a null (“”) to accept the default. For example, you can call DTW_TB_INPUT_TEXT as in the following example:

```
@DTW_TB_INPUT_TEXT(myTable, "1", "2", "", "", "32")
```

In the above example the fourth and fifth parameters use default values. Include them as nulls to indicate that “32” is the value for MAXLENGTH in the generated HTML. The final parameter is not specified, so the default value is used. If you choose to accept the default value for MAXLENGTH and the two previous parameters, omit them, as shown below:

```
@DTW_TB_INPUT_TEXT(myTable, "1", "2")
```

You must specify intermediate null values in the parameter lists for input parameters when subsequent non-null *input* parameters exist. You do not need to specify intermediate null input parameters before specifying your final *output* parameter.

General Functions

General functions help you develop Web pages with Net.Data and do not fit in the other categories. The following functions are general-purpose functions:

- “DTW_ADDQUOTE” on page 116
- “DTW_CACHE_PAGE” on page 118
- “DTW_DATE” on page 122
- “DTW_EXIT” on page 124
- “DTW_GETCOOKIE” on page 125
- “DTW_GETENV” on page 127
- “DTW_GETINIDATA” on page 128
- “DTW_HTMLENCODE” on page 129
- “DTW_QHTMLENCODE” on page 133

- “DTW_SENDMAIL” on page 134
- “DTW_SETCOOKIE” on page 139
- “DTW_SETENV” on page 143
- “DTW_TIME” on page 145
- “DTW URLESCSEQ” on page 147

DTW_ADDQUOTE

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Replaces single quotes in an input string with two single quotes.

Format

@DTW_ADDQUOTE(stringIn, stringOut)

@DTW_rADDQUOTE(stringIn)

@DTW_mADDQUOTE(stringMult, stringMult2, ..., stringMultn)

Parameters

Table 27. DTW_ADDQUOTE Parameters

Data Type	Parameter	Use	Description
string	<i>stringIn</i>	IN	A variable or literal string. DTW_mADDQUOTE can have multiple input strings.
string	<i>stringOut</i>	OUT	A variable that contains the modified form of <i>stringIn</i> .
string	<i>stringMult</i>	INOUT	<ul style="list-style-type: none">On input: A variable that contains a string.On output: A variable containing the input string with each single quote (') character replaced by two single-quote characters.

Return Codes

Table 28. DTW_ADDQUOTE Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.

Usage Notes

Consider using this function for all SQL INPUT statements where input is obtained from a Web browser. For example, if you enter O'Brien as a last name, as in the following example, the single quote might give you an error:

```
INSERT INTO USER1.CUSTABLE (LNAME, FNAME)
VALUES ('O'Brien', 'Patrick')
```

Using the DTW_ADDQUOTE function changes the SQL statement and prevents the error:


```
INSERT INTO USER1.CUSTABLE (LNAME, FNAME)
VALUES ('O'Brien', 'Patrick')
```

Examples

Example 1: Adds an extra single quote on the OUT parameter

```
@DTW_ADDQUOTE(string1,string2)
```

- Input: string1="John's Web page"
- Returns: string2="John''s Web page"

Example 2: Adds an extra single quote on the returned value of the function call

```
@DTW_rADDQUOTE("The title of the article is 'Once upon a time'")
```

- Returns: "The title of the article is ''Once upon a time''"

Example 3: Adds extra single quotation marks on each of the INOUT parameters of the function call

```
@DTW_mADDQUOTE(string1,string2)
```

- Input: string1="Joe's bag", string2="''to be or not to be'"
- Returns: string1="Joe''s bag", string2="''to be or not to be''"

Example 4: Inserts extra single quotation marks into data being inserted in a DB2 table

```
%FUNCTION(DTW_SQL) insertName(){
INSERT INTO USER1.CUSTABLE (LNAME,FNAME)
VALUES ('@DTW_rADDQUOTE(lastname)', '@DTW_rADDQUOTE(firstname)')
%}
```

- Input: lastname="O'Brien", firstname="Patrick"
- Returns: "O''Brien", "Patrick"

DTW_CACHE_PAGE

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X								X

Purpose

Caches partial or complete Web pages that are generated as a result of the processing of macros.

Format

@DTW_CACHE_PAGE(cacheID, pageID, age, status)

Parameters

Table 29. DTW_CACHE_PAGE Parameters

Parameter	Use	Description
<i>cacheID</i>	IN	A string variable identifying the cache where the page will be placed.
<i>pageID</i>	IN	A string variable containing an identifier used to locate the cached page in a subsequent DTW_CACHE_PAGE cache request. The string can be a URL.
<i>age</i>	IN	<p>A string variable containing a length of time in seconds. This parameter determines whether a page has expired. If the page is older than <i>age</i>, the page is not sent to the browser.</p> <p>If <i>age</i> is specified as -1, and the page exists in the cache, Net.Data sends it to the Web browser regardless of its age directly from the cache. Net.Data does not replace the page in the cache.</p>
<i>status</i>	OUT	<p>A string variable indicating the state of the cached page. Possible values are in lowercase:</p> <ul style="list-style-type: none">• ok: The output page will be cached when the macro execution terminates.• new: The page is not in the cache.• renew: The page is in the cache, but has expired.• no_cache: The cache identifier specified does not exist. It must be defined in the cache configuration files. Your macro can continue executing without page caching.• inactive: The cache you specified has been marked inactive. Your macro can continue executing without page caching.• busy: Your macro has issued the DTW_CACHE_PAGE built-in function before in this execution. Your macro can continue executing.• error: An error occurred while trying to communicate with the cache.

Return Codes

Table 30. DTW_CACHE_PAGE Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
1007	A parameter contains a value which is not valid.

Usage Notes

1. When invoked, DTW_CACHE_PAGE() attempts to retrieve the specified page from the cache and to send it to the Web browser as if it were the output page generated from the macro. If the page is found and it has not expired, Net.Data stops processing the macro, exits from the macro, and sends the cached page to the Web browser.

If the requested page is not in the cache or the existing cached page is older than the value of *age*, Net.Data generates a new output page. When the macro successfully completes, Net.Data sends the new page to the browser and caches the page.

2. For most caching applications, specify DTW_CACHE_PAGE() at the top of the macro to cache all of the Web page that is generated when the macro executes. This technique makes it easier to maintain the macro when the macro is updated. For example, when the function is in the middle of the macro, it might not be noticed when a HTML report section is added earlier in the macro. Net.Data would not cache the new report output. Additionally, this method improves performance as Net.Data stops all further processing when it determines that the page is cached.

For advanced caching applications, you can place the function in specific locations of the macro when you need to make the decision to cache at a specific point during processing, rather than at the beginning of the macro. For example, you might need to make the caching decision based on how many rows are returned from a query or function call.

Examples

Example 1: Places the DTW_CACHE_PAGE() function at the beginning of the macro to capture all HTML output

```
%IF (customer_status == "Classic")
@DTW_CACHE_PAGE("mymacro.mac", "http://www.mypage.org", "-1", status)
%ENDIF
% DEFINE { ...%}

...

%HTML (Output) {
<title>This is the page title
</head>
```

```

<body>
<center>
This is the Main Heading
<p>It is $(time). Have a nice day!
</body>
</HTML>

%}

```

Example 2: Places the function in the HTML block because the decision to cache depends on the expected size of the HTML output

```

%DEFINE { ...%}

...

%FUNCTION(DTW_SQL) count_rows(){
    select count(*) from customer
%REPORT{
    %ROW{
        @DTW_ASSIGN(ALL_ROWS, V1)
    %}
    %}
    %}

%FUNCTION(DTW_SQL) all_customers(){
    select * from customer
%}

%HTML (Output) {
<HTML>
<head>
<title>This is the customer list
</head>
<body>

@count_rows()

    %IF (ALL_ROWS > "100")
        @DTW_CACHE_PAGE("mymacro.mac", "http://www.mypage.org", "-1", status)
    %ENDIF

    @all_customers()

    </body>
</HTML>
%}

```

In this example, the page is cached or retrieved based on the expected size of the HTML output. HTML output pages are considered cache-worthy only when the database table contains more than 100 rows. Net.Data always sends the text in the OUTPUT block, This is the customer list, to the browser after executing the macro; the text is never cached. The lines following the function call, @count_rows(), are cached or retrieved when the conditions of the IF block are satisfied. Together, both parts form a complete Net.Data output page.

Example 3: Dynamically retrieves the cache ID and the cached page ID

```

%HTML(OUTPUT) {
    %IF (customer == "Joe Smith")

        @DTW_CACHE_PAGE(@DTW_rGETENV("DTW_MACRO_FILENAME"),
        @DTW_rGETENV("URL"), "-1", status)

    %ENDIF

```

```
...  
  
<HTML>  
  <head>  
    <title>This is the page title</title>  
  </head>  
  <body>  
    <center>  
      <h3>This is the Main Heading</h3>  
      <p>It is @DTW_rDATE(). Have a nice day!</p>  
    </center>  
  </body>  
</HTML>  
  
%}
```

DTW_DATE

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Returns the current system date in the specified format.

Format

@DTW_DATE(format, stringOut)

@DTW_DATE(stringOut)

@DTW_rDATE(format)

@DTW_rDATE()

Parameters

Table 31. DTW_DATE Parameters

Data Type	Parameter	Use	Description
string	<i>format</i>	IN	A variable or literal string specifying the data format. Valid formats include: D - Day of the year (001-366) E - European date format (dd/mm/yy) N - Normal date format (dd mon yyyy) O - Ordered date format (yy/mm/dd) S - Standard date format (yyyymmdd) U - USA date format (mm/dd/yy) The default is N.
string	<i>stringOut</i>	OUT	A variable that contains the date in the specified format.

Return Codes

Table 32. DTW_DATE Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
1007	A parameter contains a value which is not valid.

Examples

Example 1: Normal date format

```
@DTW_DATE(results)
```

- Returns: results = "25 Apr 1997"

Example 2: European date format

```
@DTW_DATE("E", results)
```

- Returns: results="25/04/97"

Example 3: US date format

```
%HTML (Report){
```

```
<p>This report created on @DTW_rDATE("U").</p>
```

- Returns: 04/25/97

DTW_EXIT

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Specifies to leave the macro immediately. Net.Data sends any Web pages that are generated prior to DTW_EXIT() being called to the Web browser .

Format

@DTW_EXIT()

Return Codes

Table 33. DTW_EXIT Return Codes

Return Code	Explanation
1003	An incorrect number of parameters were passed on a function call.

Usage Notes

1. Use DTW_EXIT() to immediately stop the processing of a macro. Using this technique saves the time Net.Data would use to process the entire file.
2. Ensure that the entire macro is syntactically correct before adding the DTW_EXIT() function. Using DTW_EXIT() causes Net.Data to stop processing the macro when it encounters the call to this function, which can prevent you from catching errors that occur after the DTW_EXIT() function has been processed.

Examples

Example 1: Exiting a macro

```
%HTML(cache_example) {  
  
<HTML>  
  <head>  
    <title>This is the page title</title>  
  </head>  
  <body>  
    <center>  
      <h3>This is the Main Heading</h3>  
      <!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!>  
      <! Joe Smith sees a very short page                               !>  
      <!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!>  
      %IF (customer == "Joe Smith")  
  
@DTW_EXIT()  
  
%ENDIF  
  
...  
  
</body>  
</HTML>  
%}
```


DTW_GETCOOKIE

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Returns the value of the specified cookie.

Format

@DTW_GETCOOKIE(IN cookie_name, OUT cookie_value)

@DTW_rGETCOOKIE(IN cookie_name)

Parameters

Table 34. DTW_GETCOOKIE Parameters

Data Type	Parameter	Use	Description
string	<i>cookie_name</i>	IN	A variable or literal string that specifies the name of the cookie.
string	<i>cookie_value</i>	OUT	A variable containing the value of the cookie retrieved by the function, such as user state information. OS/400 and OS/390 users: If the cookie value has URL style encodings (for example "%20"), the cookie value is decoded before the value is returned.

Return Codes

Table 35. DTW_GETCOOKIE Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
8000	The cookie cannot be found.

Usage Notes

Define and retrieve a cookie in two separate HTTP requests. Because a cookie is visible only after it has been sent to the client, if a macro tries to get a cookie that was defined in the same HTTP request, you might receive unexpected results.

Examples

Example 1: Retrieves cookies that contain user ID and password information

```
@DTW_GETCOOKIE("mycookie_name_for_userID", userID)
@DTW_GETCOOKIE("mycookie_name_for_password", password)
```

Example 2: Determines if a cookie for a user exists before gathering user information

```
%MESSAGE {
    8000 : "" : continue
}%

%HTML(welcome) {
    <HTML>
    <body>
    <h1>Net.Data Club</h1>
    @DTW_GETCOOKIE("NDC_name", name)
    %IF (RETURN_CODE == "8000") %{ The cookie is not found. %}
    <form method="post" action="remember">
    <p>Welcome to the club. Please enter your name.<br />
    <input name="name" />
    <input type="submit" value="submit" /></p>
    </form>
    %ELSE
    <p>Hi, $(name). Welcome back.</p>
    %ENDIF
    </body>
    </HTML>
}%
```

The HTML welcome section checks whether the cookie NDC_name exists. If the cookie exists, the browser displays a personalized greeting. If the cookie does not exist, the form prompts for the user's name, and posts it to the HTML remember section, which sets the user's name into the cookie NDC_name as shown below:

```
%HTML(remember) {
    <HTML>
    <body>
    <h1>Net.Data Club</h1>
    @DTW_SETCOOKIE("NDC_name",
        name,
        "expires=Wednesday, 01-Dec-2010 00:00:00;path=/")
    <p>Thank you.</p>
    <p><a href="welcome">Come back</a></p>
    </body>
    </HTML>
}%
```

DTW_GETENV

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Returns the value of the specified environment variable.

Format

@DTW_GETENV(envVarName, envVarValue)

@DTW_rGETENV(envVarName)

Parameters

Table 36. DTW_GETENV Parameters

Data Type	Parameter	Use	Description
string	<i>envVarName</i>	IN	A variable or literal string.
string	<i>envVarValue</i>	OUT	The value of the environment variable specified in <i>envVarName</i> . An empty string is returned if the value is not found.

Return Codes

Table 37. DTW_GETENV Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.

Usage Notes

You can also use the ENVVAR statement to reference the values of environment variables. For more information, see “ENVVAR Statement” on page 14.

Examples

Example 1: Returns the value for the PATH statement on the OUT parameter

```
@DTW_GETENV(myEnvVarName, myEnvVarValue)
```

- Input: myEnvVarName = "PATH"
- Returns: myEnvVarValue = "/usr/bin"

Example 2: Returns the value for the protocol of the server

```
<p>The server is @DTW_rGETENV("SERVER_PROTOCOL").</p>
```

Returns:

The server is "HTTP/1.0".

DTW_GETINIDATA

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Returns the value of the specified configuration variable.

Format

@DTW_GETINIDATA(iniVarName, iniVarValue)

@DTW_rGETINIDATA(iniVarName)

Parameters

Table 38. DTW_GETINIDATA Parameters

Data Type	Parameter	Use	Description
string	<i>iniVarName</i>	IN	A variable or literal string.
string	<i>iniVarValue</i>	OUT	The value of the configuration variable specified in <i>iniVarName</i> .

Return Codes

Table 39. DTW_GETINIDATA Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.

Usage Notes

1. If a configuration variable is specified that is not the configuration file, Net.Data returns an empty string.
2. **For OS/390, OS/2, Windows NT, and UNIX users:** configuration path variables (MACRO_PATH, EXEC_PATH, and INCLUDE_PATH), as well as ENVIRONMENT statements, cannot be retrieved with this call.
3. **For OS/400 users:** ENVIRONMENT statements cannot be retrieved with this call.

Examples

Example 1: Returns the Net.Data path variable value.

```
myEnvVarName = "FFI_PATH"  
@DTW_GETINIDATA(myEnvVarName, myEnvVarValue)
```

Yields: myEnvVarValue = "D:\FFI"

DTW_HTMLENCODE

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Encodes selected characters using HTML character escape codes.

Format

@DTW_HTMLENCODE(stringIn, stringOut)

@DTW_rHTMLENCODE(stringIn)

Parameters

Table 40. DTW_HTMLENCODE Parameters

Data Type	Parameter	Use	Description
string	<i>stringIn</i>	IN	A variable or literal string.
string	<i>stringOut</i>	OUT	A variable containing the modified input string in which certain characters have been replaced by the HTML character escape codes.

Return Codes

Table 41. DTW_HTMLENCODE Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.

Usage Notes

1. Use this function to encode character data that you do not want the Web browser to interpret as HTML. For example, by using the appropriate escape code, you can display characters such as less-than (<) and greater-than (>) within a Web page, which would otherwise be interpreted by the browser as components of HTML tags.
2. Table 42 shows the characters that are encoded by the DTW_HTMLENCODE function.

Table 42. Character Escape Codes for HTML

Character	Name	Code
SPACE	Space	
"	Double quote	"
#	Number sign	#
%	Percent	%

Table 42. Character Escape Codes for HTML (continued)

&	Ampersand	&
[Left bracket	(
]	Right bracket)
+	Plus	+
\	Slash	/
:	Colon	:
;	Semicolon	;
<	Less than	<
=	Equals	=
>	Greater than	>
?	Question mark	?
@	At sign	@
/	Backslash	\
^	Carat	^
{	Left brace	{
	Straight line	|
}	Right brace	}
~	Tilde	~

Examples

Example 1: Encodes the space character

```
@DTW_HTML_ENCODE(string1,string2)
```

- Input: string1 = "Jim's dog"
- Returns: string2 = "Jim's dog"

Example 2: Encodes spaces, the less-than sign, and the equal sign

```
@DTW_rHTML_ENCODE("X <= 10")
```

- Returns: "X <= 10"

DTW_LOG_ERRORMSG

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
				X				

Purpose

Allows you to write a message to the error log.

Format

@DTW_LOG_ERRORMSG(stringIn)

Parameters

Table 43. DTW_LOG_ERRORMSG Parameters

Data Type	Parameter	Use	Description
string	<i>stringIn</i>	IN	A variable, literal string, or a combination.

Return Codes

Table 44. DTW_LOG_ERRORMSG Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.

Usage Notes

Use this function to write messages to the error log. One example would be to use a message block to catch a message that would otherwise be displayed on the screen, and to then use this function to write a customized message to the error log.

This function will only work when error logging is enabled. See *Net.Data Administration and Programming Guide* for information on enabling the error log. The format of the message that is written to the log will have the same format as the Net.Data error messages written to the log. If tracing is also activated, this function will write the error in both the error and trace log.

Examples

Report the error code and function in which it was generated.

```
@DTW_LOG_ERRORMSG("Error occured in myfunc(), errorcode=$(myerrcode)")
```

DTW_LOG_TRACMSG

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
				X				

Purpose

Allows you to write a message to the trace log.

Format

@DTW_LOG_TRACMSG(stringIn)

Parameters

Table 45. DTW_LOG_TRACMSG Parameters

Data Type	Parameter	Use	Description
string	<i>stringIn</i>	IN	A variable, literal string, or a combination.

Return Codes

Table 46. DTW_LOG_TRACMSG Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.

Usage Notes

Use this function to write messages to the trace log. One example would be to aid in debugging your application, or to provide extra information to someone servicing your application.

This function will only work when trace logging is activated. See *Net.Data Administration and Programming Guide* for information on activating the trace log. If error logging is also activated, the errors will be logged in the trace log as well as the error log.

Examples

Report the current state of the variables at a given point in a function.

```
@DTW_LOG_TRACMSG("Checkpoint 1: Var1='${var1}' Var2='${var2}')
```


DTW_QHTMLENCODE

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Performs the same function as @DTW_HTMLENCODE but also encodes the single-quote character (') as '. The HTML character escape codes that DTW_QHTMLENCODE uses are shown in Table 42 on page 129.

Format

@DTW_QHTMLENCODE(stringIn, stringOut)

@DTW_rQHTMLENCODE(stringIn)

Parameters

Table 47. DTW_QHTMLENCODE Parameters

Data Type	Parameter	Use	Description
string	<i>stringIn</i>	IN	A variable or literal string.
string	<i>stringOut</i>	OUT	A variable that contains the modified form of <i>stringIn</i> in which certain characters are replaced by the HTML character escape codes.

Return Codes

Table 48. DTW_QHTMLENCODE Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.

Examples

Example 1: Encodes an apostrophe and a space

```
@DTW_QHTMLENCODE(string1,string2)
```

- Input: string1 = "Jim's dog"
- Returns: string2 = "Jim's dog"

Example 2: Encodes apostrophes, spaces, and an ampersand

```
@DTW_rQHTMLENCODE("John's & Jane's")
```

- Returns: "John's & Jane's"

DTW_SENDMAIL

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Dynamically builds and transmits electronic mail (e-mail) messages.

Format

@DTW_SENDMAIL(IN Sender, IN Recipient, IN Message, IN Subject, IN CarbonCopy, IN BlindCarbonCopy, IN ReplyTo, IN Organization, IN Attachments)

@DTW_SENDMAIL(IN Sender, IN Recipient, IN Message, IN Subject, IN CarbonCopy, IN BlindCarbonCopy, IN ReplyTo, IN Organization)

@DTW_SENDMAIL(IN Sender, IN Recipient, IN Message, IN Subject, IN CarbonCopy, IN BlindCarbonCopy, IN ReplyTo)

@DTW_SENDMAIL(IN Sender, IN Recipient, IN Message, IN Subject, IN CarbonCopy, IN BlindCarbonCopy)

@DTW_SENDMAIL(IN Sender, IN Recipient, IN Message, IN Subject, IN CarbonCopy)

@DTW_SENDMAIL(IN Sender, IN Recipient, IN Message, IN Subject)

@DTW_SENDMAIL(IN Sender, IN Recipient, IN Message)

Parameters

Table 49. DTW_SENDMAIL Parameters

Data Type	Parameter	Use	Description
string	<i>sender</i>	IN	A variable or literal string that specifies the author's address. This parameter is required. Valid formats are: <ul style="list-style-type: none">• Name <user@domain>• <user@domain>• user@domain
string	<i>recipient</i>	IN	A variable or literal string that specifies the e-mail addresses to which this message will be sent. This value can contain multiple recipients, separated by a comma (.). This parameter is required. Valid <i>recipient</i> formats are: <ul style="list-style-type: none">• Name <user@domain>• <user@domain>• user@domain
string	<i>message</i>	IN	A variable or literal string that contains the text of the e-mail message. This parameter is required.
string	<i>subject</i>	IN	A variable or literal string that contains the text of subject line. This is an optional parameter. You must specify a null string ("") to specify additional parameters.

Table 49. DTW_SENDMAIL Parameters (continued)

Data Type	Parameter	Use	Description
string	<i>CarbonCopy</i>	IN	A variable or literal string that contains the e-mail addresses, or names and e-mail addresses of additional recipients. This value can contain multiple additional recipients separated by a comma (.). See the <i>Recipient</i> parameter for valid recipient formats. This is an optional parameter. You must specify a null string ("") to specify additional parameters.
string	<i>BlindCarbonCopy</i>	IN	A variable or literal string that contains the e-mail addresses, or names and e-mail addresses of additional recipients, but the recipients do not appear in the e-mail header. This value can contain multiple additional recipients separated by a comma (.). See the <i>Recipient</i> parameter for valid recipient formats. This is an optional parameter. You must specify a null string ("") to specify additional parameters.
string	<i>ReplyTo</i>	IN	A variable or literal string that contains the e-mail address to which replies to this message should be sent. This is an optional parameter. You must specify a null string ("") to specify additional parameters. Valid <i>ReplyTo</i> formats are: <ul style="list-style-type: none"> • Name <user@domain> • <user@domain> • user@domain
string	<i>Organization</i>	IN	A variable or literal string that contains the organization name of the <i>sender</i> . This is an optional parameter.
string	<i>Attachments</i>	IN	A variable or literal string that specifies the relative paths to the files to be sent. This value can contain multiple files, separated by a comma, but cannot contain a range string (..). These files will be searched in the order of directories listed in the DTW_ATTACHMENT_PATH configuration variable, which is set in the Net.Data initialization file. The following content types can be sent as attachments: <ul style="list-style-type: none"> • image/jpeg • image/gif • audio/basic • application/octet-stream (general)

Return Codes

Table 50. DTW_SENDMAIL Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
7000	Net.Data is unable to connect to the specified SMTP server.
7001	An SMTP error occurred while Net.Data tried to relay the e-mail message to the specified SMTP server.
7002	The specified SMTP server does not support the Extended Simple Mail Transfer Protocol (ESMTP).

Usage Notes

1. You can use the optional configuration variable, DTW_SMTP_SERVER, to specify the SMTP server to use for transmitting e-mail messages. The value of this parameter can either be a hostname or an IP address. When this variable is not defined, Net.Data uses the local host as the SMTP server. See the configuration chapter in the *Net.Data Administration and Programming Guide* for your operating system to learn more about this variable. DTW_SMTP_SERVER is ignored on OS/390.
2. **OS/2, Windows NT, and UNIX users:** Standard Simple Mail Transfer Protocol (SMTP) servers accept only 7-bit data, such as U.S. ASCII characters. If your message has 8-bit characters, it is recommended that you specify an Extended Simple Mail Transfer Protocol (ESMTP) server; ESMTP servers accept 8-bit characters. Net.Data does not encode your 8-bit data into 7-bit data. If you do not have access to an ESMTP server, remove all 8-bit characters from the e-mail message.

Net.Data for OS/390 users do not need to modify e-mail messages for SMTP servers.
3. Character set support:
 - **OS/400 users:** You can use the optional configuration variable, DTW_SMTP_CHARSET to specified which ASCII character to use when converting the message from EBCDIC to ASCII. If DTW_SMTP_CHARSET is not specficied, the default character set is iso-8859-1. See the configuration chapter in *Net.Data Administration and Programming Guide for OS/400* to learn more about this variable and the supported character sets.
 - **OS/2, Windows NT, and UNIX users:** Table 51 describes the supported character sets:

Table 51. Character sets supported by Net.Data

Locale	Character set	OS/2 or UNIX codepage	Windows NT codepage
U.S, Western Europe	"iso-8859-1"	819	1252
Japan	"x-sjis"	943	932

Table 51. Character sets supported by Net.Data (continued)

Locale	Character set	OS/2 or UNIX codepage	Windows NT codepage
Chinese (simplified)	"gb2312"	1381	936
Korea	"euc-kr"	970	949
Chinese (traditional)	"big5"	950	950

4. The following list describes conditions under which Net.Data does not send an e-mail message:
 - The specified SMTP server cannot be reached.
 - The specified SMTP server does not support the Extended Simple Mail Transfer Protocol (ESMTP), but the specified e-mail message contains non-U.S. ASCII characters.
5. The *attachments* parameter is not valid on OS/390.

Examples

Example 1: Function call that builds and sends a simple e-mail message

```
@DTW_SENDMAIL("<ibmuser1@ibm.com>", "<ibmuser2@ibm.com>", "There is a
meeting at 9:30.", "Status meeting")
```

The DTW_SENDMAIL function sends an e-mail message with the following information:

```
Date: Mon, 3 Apr 1998 09:54:33 PST
To: <ibmuser2@ibm.com>
From: <ibmuser1@ibm.com>
Subject: Status meeting
```

There is a meeting at 9:30.

The information for Date is constructed by using the system date and time functions and is formatted in a SMTP-specific data format.

Example 2: Function call that builds and sends an e-mail message with multiple recipients, carbon copy and blind carbon copy recipients, and the company name

```
@DTW_SENDMAIL("IBM User 1 <ibmuser1@ibm.com>", "IBM User 2 <ibmuser2@ibm.com>,
IBM User 3 <ibmuser3@ibm.com>, IBM User 4 <ibmuser4@ibm.com>", "There is a
meeting at 9:30.", "Status meeting", "IBM User 5 <ibmuser5@ibm.com>",
"IBM User 6 <ibmuser6@ibm.com>", "meeting@ibm.com", "IBM")
```

The DTW_SENDMAIL function sends an e-mail message with the following information:

```
Date: Mon, 3 Apr 1998 09:54:33 PST
To: IBM User 2 <ibmuser2@ibm.com>, IBM User 3 <ibmuser3@ibm.com>,
    IBM User 4 <ibmuser4@ibm.com>
CC: IBM User 5 <ibmuser5@ibm.com>
BCC: IBM User 6 <ibmuser6@ibm.com>
From: IBM User 1 <ibmuser1@ibm.com>
ReplyTo: meeting@ibm.com
Organization: IBM
Subject: Status meeting
```

There is a meeting at 9:30.

Example 3: Macro that builds and sends e-mail through a Web form interface

```

%HTML(start) {
<HTML>
<body>
<h1>Net.Data E-Mail Example</h1>
<form method="post" action="sendemail">
<p>To:<br /><input name="recipient" /></p>
<p>Subject:<br /><input name="subject" /></p>
<p>Message:<br /><textarea name=message rows="20" cols="40">
</textarea></p>
<p><input type="submit" value="Send E-mail"></p>
</form>
</body>
</HTML>
%}

%HTML(sendemail) {
<HTML>
<body>
<h1>Net.Data E-Mail Example</h1>
@DTW_SENDMAIL("Net.Data E-mail Service <netdata@us.ibm.com>",
recipient, message, subject)
<p>E-mail has been sent out.</p>
</body>
</HTML>
%}

```

This macro sends e-mail through a Web form interface. The HTML start section displays a form into which the recipient's e-mail address, a subject, and a message can be typed. When the user clicks on the **Send E-mail** button, the message is sent out to the recipients specified in the HTML(sendemail) section. This section calls DTW_SENDMAIL and uses the parameters obtained from the Web form to determine the content of the e-mail message, as well as the sender and recipients. Once the e-mail messages have been sent, a confirmation notice is displayed.

Example 4: A macro that uses an SQL query to determine the list of recipients

```

%Function(DTW_SQL) mailing_list(IN message) {
SELECT EMAIL_ADDRESS FROM CUSTOMERS WHERE STATE='CA'
%REPORT {
Sending product information to our customers in California...<p>
%ROW {
@DTW_SENDMAIL("John Doe Corp. <john.doe@doe.com>", V1, message,
"New Product Release")
E-mail sent out to customer $(V1).<br />
%}
%}
%}

```

This macro sends out an automated e-mail message to a specified group of customers determined by the results of a SQL query from the customer database. The SQL query also retrieves the e-mail addresses of the customers. The e-mail contents are determined by the value of *message* and can be static or dynamic (for example, you could use another SQL query to dynamically specify the version number of the product or the prices of various offerings).

DTW_SETCOOKIE

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Generates JavaScript code that sets a cookie on the client system.

Format

@DTW_SETCOOKIE(IN cookie_name, IN cookie_value, IN adv_opts)

@DTW_SETCOOKIE(IN cookie_name, IN cookie_value)

Parameters

Table 52. DTW_SETCOOKIE Parameters

Data Type	Parameter	Use	Description
string	<i>cookie_name</i>	IN	A variable or literal string that specifies the name of the cookie
string	<i>cookie_value</i>	IN	A variable or literal string the specifies the value of the cookie. Avoid using semicolons, commas, and spaces as a part of <i>cookie_value</i> . When they are required, use the Net.Data function DTW_rURLESCSEQ to process the string that contains the special characters before passing it to DTW_SETCOOKIE. For example, @DTW_SETCOOKIE("my_cookie_name", @DTW_rURLESCSEQ("my cookie value"))
string	<i>adv_opts</i>	IN	A string that contains optional attributes, separated by semicolons, that are used to define the cookie.*

Table 52. DTW_SETCOOKIE Parameters (continued)

Data Type	Parameter	Use	Description
<p>*The optional attributes can be:</p> <p>expires = <i>date</i> Specifies a date string that defines the valid lifetime of the cookie. After the date expires, the cookie is not longer stored or retrieved. Syntax: <i>weekday</i>, <i>DD-month-YYYY HH:MM:SS GMT</i></p> <p>Where:</p> <p><i>weekday</i> Specifies the full name of the weekday.</p> <p><i>DD</i> Specifies the numerical date of the month.</p> <p><i>month</i> Specifies the three-character abbreviation of the month.</p> <p><i>YYYY</i> Specifies the four-character number of the year.</p> <p><i>HH:MM:SS</i> Specifies the timestamp with hours, minutes, and seconds.</p> <p>domain = <i>domain_name</i> Specifies the domain attributes of the cookie, for use in domain attribute matching.</p> <p>path = <i>path</i> Specifies the subset of URLs in a domain for which the cookie is valid.</p> <p>secure Specifies that the cookie is transmitted only over secured channels to HTTPS servers.</p> <p>When the secure option is not specified, the cookie can be sent over unsecured channels. The secure option does not require that the browser encrypt the cookie, nor does it ensure that the page containing the DTW_SETCOOKIE statement is transmitted over SSL.</p> <p>For additional information about all of the advanced options, see the Netscape cookie specification at http://home.netscape.com</p>			

Return Codes

Table 53. DTW_SETCOOKIE Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.

Usage Notes

1. If the client Web browser does not support Java Script, the browser does not set the cookie.
2. Because DTW_SETCOOKIE generates Java Script code, do not call DTW_SETCOOKIE inside a <script> or <noscript> HTML element.
3. To retrieve a cookie, use the DTW_GETCOOKIE() function. See "DTW_GETCOOKIE" on page 125 to learn how to define a cookie.
4. Define and retrieve a cookie in two separate HTTP requests. Because a cookie is visible only after it has been sent to the client, if a macro tries to get a cookie that was defined in the same HTTP request, you might receive unexpected results.

Examples

Example 1: Defines cookies that contain user ID and password information with the Secure advanced option

```
@DTW_SETCOOKIE("mycookie_name_for_userID", "User1")
@DTW_SETCOOKIE("mycookie_name_for_password", "sd3dT", "secure")
```

Example 2: Defines cookies that contain the expiration date advanced option

```
@DTW_SETCOOKIE("mycookie_name_for_userID", "User1",
    "expires=Wednesday 01-Dec-2010 00:00:00")
@DTW_SETCOOKIE("mycookie_name_for_password", "sd3dT",
    "expires=Wednesday, 01-Dec-2010 00:00:00;secure")
```

Function calls should be on one line; the lines are split in this example for formatting purposes.

Example 3: Determines if a cookie for a user exists before gathering user information

```
%HTML(welcome) {
  <HTML>
  <body>
  <h1>Net.Data Club</h1>
  @DTW_GETCOOKIE("NDC_name", name)
  %IF (RETURN_CODE == "8000") %{ The cookie is not found. %}
  <form method="post" action="remember">
  <p>Welcome to the club. Please enter your name.<br />
  <input name="name">
  <input type="submit" value="submit"><br /></p>
  </form>
  %ELSE
  <p>Hi, $(name). Welcome back.</p>
  %ENDIF
  </body>
  </HTML>
  %}
```

The HTML(welcome) section checks whether the cookie NDC_name exists. If the cookie exists, the browser displays a personalized greeting. If the cookie does not exist, the browser prompts for the user's name, and posts it to the HTML(remember) section. This section records the user's name into the cookie NDC_name as shown below:

```
%HTML(remember) {
  <HTML>
  <body>
  <h1>Net.Data Club</h1>
  @DTW_SETCOOKIE("NDC_name", name,
    "expires=Wednesday, 01-Dec-2010 00:00:00;path=/")
  <p>Thank you.</p>
```

```
<p><a href="welcome">Come back</a></p>
</body>
</HTML>
%}
```

DTW_SETENV

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Assigns an environment variable with a specified value and returns the previous value.

Format

@DTW_SETENV(envVarName, envVarValue, prevValue)

@DTW_rSETENV(envVarName, envVarValue)

Parameters

Table 54. DTW_SETENV Parameters

Data Type	Parameter	Use	Description
string	<i>envVarName</i>	IN	A variable or literal string representing the environment variable.
string	<i>envVarValue</i>	IN	A variable or literal string with the value to which the environment variable is assigned.
string	<i>prevValue</i>	OUT	A variable that contains the previous value of the environment variable.

Return Codes

Table 55. DTW_SETENV Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.

Usage Notes

If no previous value for the environment variable is found, an empty string is returned.

Examples

Example 1: Returns the value for the previous path

```
@DTW_SETENV("PATH", "myPath", prevValue)
```

- Input: envVarName = "PATH", envVarValue = "myPath"
- Returns: prevValue = "myPreviousPath"

Example 2: Returns the value for the previous path and assigns the value for PATH value

```
@DTW_rSETENV("PATH", "myPath")
```

- Input: envVarName = "PATH", envVarValue = "myPath"
- Returns: "myPreviousPath", PATH = "myPath"

DTW_TIME

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Returns the current system time in the specified format.

Format

@DTW_TIME(stringIn, stringOut)

@DTW_TIME(stringOut)

@DTW_rTIME(stringIn)

@DTW_rTIME()

Parameters

Table 56. DTW_TIME Parameters

Data Type	Parameter	Use	Description
string	<i>stringIn</i>	IN	A variable or literal string specifying the time format. Valid formats are: C - Civil time (hh:mmAM/PM using a 12-hour clock) L - Local time (hh:mm:ss) N - Normal time (hh:mm:ss using a 24-hour clock); default X - Extended time (hh:mm:ss.ccc, using a 24-hour clock and where ccc is the number of milliseconds) H - Number of hours since midnight M - Number of minutes since midnight S - Number of seconds since midnight
string	<i>stringOut</i>	OUT	A variable that contains the time in the specified format.

Return Codes

Table 57. DTW_TIME Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
1007	A parameter contains a value which is not valid.

Examples

Example 1: Twenty-four hour clock format

@DTW_TIME(results)

- Returns: results = "10:30:53"

Example 2: Civil time format

@DTW_TIME("C", results)

- Returns: results = "10:30AM"

Example 3: Returns the number of minutes since midnight with the function call

@DTW_rTIME("M")

- Returns: "630"

Example 4: Returns the default time and data formats with the function call

%REPORT{

<p>This report was created at @DTW_rTIME(), @DTW_rDATE().</p>

%}

- Returns: This report was created 15:04:39, 01 May 1997.

DTW_URLESCSEQ

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Replaces selected characters not allowed in a URL with their escape values, known as URL-encoded codes.

Format

@DTW_URLESCSEQ(stringIn, stringOut)

@DTW_rURLESCSEQ(stringIn)

Parameters

Table 58. DTW_URLESCSEQ Parameters

Data Type	Parameter	Use	Description
string	<i>stringIn</i>	IN	A variable or literal string.
string	<i>stringOut</i>	OUT	A variable containing the input string with characters that are not allowed in URLs that are replaced with their hexadecimal escape values.

Return Codes

Table 59. DTW_URLESCSEQ Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.

Usage Notes

Use this function to pass any of the characters listed in Table 60 to another macro or HTML block.

Table 60. Character Escape Values for URLs

Character	Name	Code
SPACE	Space	%20
"	Double quote	%22
#	Number sign	%23
%	Percent	%25
&	Ampersand	%26
+	Plus	%2B
\	Backslash	%2F

Table 60. Character Escape Values for URLs (continued)

:	Colon	%3A
;	Semicolon	%3B
<	Less than	%3C
=	Equals	%3D
>	Greater than	%3E
?	Question mark	%3F
@	At sign	%40
[Left bracket	%5B
/	Slash	%5C
]	Right bracket	%5D
^	Carat	%5E
{	Left brace	%7B
	Straight line	%7C
}	Right brace	%7D
~	Tilde	%7E

Examples

Example 1: Replaces the space and an ampersand characters in *string1* with their escape values and assigns the result to *string2*

```
@DTW_URLESCSEQ(string1,string2)
```

- Input: string1 = "Guys & Dolls"
- Returns: string2 = "Guys%20%26%20Dolls"

Example 2: Replaces space and ampersand characters with their escape codes.

```
@DTW_rURLESCSEQ("Guys & Dolls")
```

- Returns: "Guys%20%26%20Dolls"

Example 3: Uses DTW_rURLESCSEQ in a ROW block, and replaces space and 'at' characters with their escape codes.

```
%ROW{
<p><a href="fullrpt.mac/input
?name=@DTW_rURLESCSEQ(V1)&email=@DTW_rURLESCSEQ(V2)">
$(V1)</a></p>
%}
• Input: V1="Patrick O'Brien", V2="obrien@ibm.com"
• Returns:
<p><a href="fullrpt.mac/input?name=Patrick%20O'Brien
&email="obrien%40ibm.com">Patrick O'Brien</a></p>
```

When the application user clicks on the name "Patrick O'Brien," the values specified for the name and e-mail address flow within the query string of the URL that causes Net.Data to execute the input section of the fullrpt.mac macro.

Math Functions

These functions let you do mathematical calculations.

NLS considerations for math functions: Net.Data displays decimal points in numerical values based on regional settings specified at the Web server under which Net.Data is running. For example, if the decimal point is specified as a comma (,) at the Web server, Net.Data uses the comma to format decimal data. Net.Data uses the following settings to determine which character is used to specify a decimal point:

For OS/390, Windows NT, OS/2, and UNIX operating systems:

The LOCALE under which the Web server executes

For the OS/400 operating system:

- V4R2 or subsequent releases: specified by the user profile under which the process is running.
- V4R1 or previous releases: retrieved from the QDECFMT system value.

The following functions are available for mathematical calculations:

- “DTW_ADD” on page 150
- “DTW_DIVIDE” on page 152
- “DTW_DIVREM” on page 154
- “DTW_FORMAT” on page 156
- “DTW_INTDIV” on page 159
- “DTW_MULTIPLY” on page 161
- “DTW_POWER” on page 163
- “DTW_SUBTRACT” on page 165

DTW_ADD

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Adds two numbers.

Format

@DTW_ADD(number1, number2, precision, result)

@DTW_ADD(number1, number2, result)

@DTW_rADD(number1, number2, precision)

@DTW_rADD(number1, number2)

Parameters

Table 61. DTW_ADD Parameters

Data Type	Parameter	Use	Description
float	<i>number1</i>	IN	A variable or literal string representing a number.
float	<i>number2</i>	IN	A variable or literal string representing a number.
integer	<i>precision</i>	IN	A variable or literal string representing a positive whole number that specifies the precision of the result. The default is 9.
float	<i>result</i>	OUT	A variable that contains the sum of <i>number1</i> and <i>number2</i> .

Return Codes

Table 62. DTW_ADD Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
4000	A parameter contains an invalid whole number value.
4001	A parameter contains an invalid number value.
4002	The result of an arithmetic operation had an exponent that was outside the supported range of -999,999,999 to +999,999,999.

Examples

Example 1:

```
@DTW_ADD(NUM1, NUM2, "2", result)
```

- Input: NUM1 = "105", NUM2 = "3"
- Returns: result = "1.1E+2"

Example 2:

```
@DTW_rADD("12", NUM2, "5")
```

- Input: NUM2 = "7.00"
- Returns: "19.00"

DTW_DIVIDE

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Divides one number by the other.

Format

@DTW_DIVIDE(number1, number2, precision, result)

@DTW_DIVIDE(number1, number2, result)

@DTW_rDIVIDE(number1, number2, precision)

@DTW_rDIVIDE(number1, number2)

Parameters

Table 63. DTW_DIVIDE Parameters

Data Type	Parameter	Use	Description
float	<i>number1</i>	IN	A variable or literal string representing a number that is to be divided.
float	<i>number2</i>	IN	A variable or literal string representing a number.
integer	<i>precision</i>	IN	A variable or literal string representing a positive whole number that specifies the precision of the result. The default is 9.
float	<i>result</i>	OUT	A variable that contains the result of <i>number1</i> divided by <i>number2</i> .

Return Codes

Table 64. DTW_DIVIDE Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
4000	A parameter contains an invalid whole number value.
4001	A parameter contains an invalid number value.
4002	The result of an arithmetic operation had an exponent that was outside the supported range of -999,999,999 to +999,999,999.

Examples

Example 1:

```
@DTW_DIVIDE("8.0", NUM2, result)
```

- Input: NUM2 = "2"
- Returns: result = "4"

Example 2:

```
@DTW_rDIVIDE("1", NUM2, "5")
```

- Input: "1", NUM2 = "3"
- Returns: "0.33333"

Example 3:

```
@DTW_rDIVIDE(NUM1, "2", "5")
```

- Input: NUM1 = "5"
- Returns: "2.5"

DTW_DIVREM

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Divides one number by the other and returns the remainder.

Format

@DTW_DIVREM(number1, number2, precision, result)

@DTW_DIVREM(number1, number2, result)

@DTW_rDIVREM(number1, number2, precision)

@DTW_rDIVREM(number1, number2)

Parameters

Table 65. DTW_DIVREM Parameters

Data Type	Parameter	Use	Description
float	<i>number1</i>	IN	A variable or literal string representing a number that is to be divided.
float	<i>number2</i>	IN	A variable or literal string representing a number.
integer	<i>precision</i>	IN	A variable or literal string representing a positive whole number that specifies the precision of the result. The default is 9.
float	<i>result</i>	OUT	A variable that contains the remainder of <i>number1</i> divided by <i>number2</i> .

Return Codes

Table 66. DTW_DIVIDEREM Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
4000	A parameter contains an invalid whole number value.
4001	A parameter contains an invalid number value.
4002	The result of an arithmetic operation had an exponent that was outside the supported range of -999,999,999 to +999,999,999.

Usage Notes

The sign of the remainder, if nonzero, is the same as that of the first parameter.

Examples

Example 1:

```
@DTW_DIVREM(NUM1, NUM2, result)
```

- Input: NUM1 = "2.1", NUM2 = "3"
- Returns: result = "2.1"

Example 2:

```
@DTW_rDIVREM("10", NUM2)
```

- Input: NUM2 = "0.3"
- Returns: "0.1"

Example 3:

```
@DTW_rDIVREM("3.6", "1.3")
```

- Returns: "1.0"

Example 4:

```
@DTW_rDIVREM("-10", "3")
```

- Returns: "-1"

DTW_FORMAT

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Customizes the formatting for a number.

Format

@DTW_FORMAT(number, before, after, expx, expt, precision, result)

@DTW_FORMAT(number, before, after, expx, expt, result)

@DTW_FORMAT(number, before, after, expx, result)

@DTW_FORMAT(number, before, after, result)

@DTW_FORMAT(number, before, result)

@DTW_FORMAT(number, result)

@DTW_rFORMAT(number, before, after, expx, expt, precision)

@DTW_rFORMAT(number, before, after, expx, expt)

@DTW_rFORMAT(number, before, after, expx)

@DTW_rFORMAT(number, before, after)

@DTW_rFORMAT(number, before)

@DTW_rFORMAT(number)

Parameters

Table 67. DTW_FORMAT Parameters

Data Type	Parameter	Use	Description
float	<i>number</i>	IN	A variable or literal string representing a number.
integer	<i>before</i>	IN	A variable or literal string representing a positive whole number. This is an optional parameter. You must enter a null string (") to have additional parameters.
integer	<i>after</i>	IN	A variable or literal string representing a positive whole number. This is an optional parameter. You must enter a null string (") to specify additional parameters.
integer	<i>expx</i>	IN	A variable or literal string representing a positive whole number. You must specify a null string (") to specify additional parameters.
integer	<i>expt</i>	IN	A variable or literal string representing a positive whole number. You must enter a null string (") to specify additional parameters.
integer	<i>precision</i>	IN	A variable or literal string representing a positive whole number that specifies the precision of the result. The default is 9.
float	<i>result</i>	OUT	A variable that contains the number with the specified rounding and formatting.

Return Codes

Table 68. DTW_FORMAT Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
4000	A parameter contains an invalid whole number value.
4001	A parameter contains an invalid number value.

Usage Notes

1. If *number* is the only parameter is specified, the result is formatted as if @DTW_rADD(number,"0") was executed.
2. The *before* and *after* parameters describe how many characters are used for the integer and decimal parts of the *result* parameter, respectively. If you omit either or both of these parameters, the number of characters used for that part is as many as is needed.
3. If the *before* parameter is not large enough to contain the integer part of the number (plus the sign for a negative number), an error results. If the *before* parameter is larger than needed for that part, the *number* parameter value is padded on the left with blanks. If the *after* parameter is not the same size as the decimal part of the *number* parameter, the number is rounded (or extended with zeros) to fit. Specifying 0 causes the number to be rounded to an integer.
4. The *expp* and *expt* parameters control the exponent part of the result. The *expp* parameter sets the number of places for the exponent part; the default is to use as many as is needed (which may be zero). The *expt* parameter sets the trigger point for use of exponential notation. The default is the default value of the precision parameter.
5. If *expp* is 0, no exponent is supplied and the number is expressed in simple form with added zeros as necessary. If *expp* is not large enough to contain the exponent, an error results.
6. If the number of places needed for the integer or decimal part exceeds *expt* or twice *expt*, respectively, use the exponential notation. If *expt* is 0, exponential notation is always used unless the exponent is 0. (If *expp* is 0, this overrides a 0 value of *expt*.) If the exponent is 0 when a nonzero *expp* is specified, then *expp*+2 blanks are supplied for the exponent part of the result. If the exponent is 0 and *expp* is not specified, the simple form is used.

Examples

Example 1:

@DTW_FORMAT(NUM, BEFORE, result)

- Input: NUM = "3", BEFORE = "4"
- Returns: result= " 3"

Example 2:

```
@DTW_FORMAT("1.73", "4", "0", result)
```

- Returns: result = " 2"

Example 3:

```
@DTW_FORMAT("1.73", "4", "3", result)
```

- Returns: result = " 1.730"

Example 4:

```
@DTW_FORMAT(" - 12.73", "", "4", result)
```

- Returns: result = "-12.7300"

Example 5:

```
@DTW_FORMAT("12345.73", "", "", "2", "2", result)
```

- Returns: result = "1.234573E+04"

Example 6:

```
@DTW_FORMAT("1.234573", "", "3", "", "0", result)
```

- Returns: result = "1.235"

Example 7:

```
@DTW_rFORMAT(" - 12.73")
```

- Returns: " - 12.73"

Example 8:

```
@DTW_rFORMAT("0.000")
```

- Returns: "0"

Example 9:

```
@DTW_rFORMAT("12345.73", "", "", "3", "6")
```

- Returns: "12345.73"

Example 10:

```
@DTW_rFORMAT("1234567e5", "", "3", "0")
```

- Returns: "123456700000.000"

Example 11:

```
@DTW_rFORMAT("12345.73", "", "3", "", "0")
```

- Returns: "1.235E+4"

DTW_INTDIV

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Divides one number by the other and returns the integer part of the result.

Format

@DTW_INTDIV(number1, number2, precision, result)

@DTW_INTDIV(number1, number2, result)

@DTW_rINTDIV(number1, number2, precision)

@DTW_rINTDIV(number1, number2)

Parameters

Table 69. DTW_INTDIV Parameters

Data Type	Parameter	Use	Description
float	<i>number1</i>	IN	A variable or literal string representing a number a number that is to be divided.
float	<i>number2</i>	IN	A variable or literal string representing a number.
integer	<i>precision</i>	IN	A variable or literal string representing a positive whole number that specifies the precision of the result. The default is 9.
float	<i>result</i>	OUT	A variable that contains integer part of <i>number1</i> divided by <i>number2</i> .

Return Codes

Table 70. DTW_INTDIV Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
4000	A parameter contains an invalid whole number value.
4001	A parameter contains an invalid number value.
4002	The result of an arithmetic operation had an exponent that was outside the supported range of -999,999,999 to +999,999,999.

Examples

Example 1:

```
@DTW_INTDIV(NUM1, NUM2, result)
```

- Input: NUM1 = "10", NUM2 = "3"
- Returns: result = "3"

Example 2:

@DTW_rINTDIV("2", NUM2)

- Input: NUM2 = "3"
- Returns: "0"

DTW_MULTIPLY

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Multiplies two numbers.

Format

@DTW_MULTIPLY(number1, number2, precision, result)

@DTW_MULTIPLY(number1, number2, result)

@DTW_rMULTIPLY(number1, number2, precision)

@DTW_rMULTIPLY(number1, number2)

Parameters

Table 71. DTW_MULTIPLY Parameters

Data Type	Parameter	Use	Description
float	<i>number1</i>	IN	A variable or literal string representing a number.
float	<i>number2</i>	IN	A variable or literal string representing a number.
integer	<i>precision</i>	IN	A variable or literal string representing a positive whole number that specifies the precision of the result. The default is 9.
float	<i>result</i>	OUT	A variable that contains the product of <i>number1</i> and <i>number2</i> .

Return Codes

Table 72. DTW_MULTIPLY Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
4000	A parameter contains an invalid whole number value.
4001	A parameter contains an invalid number value.
4002	The result of an arithmetic operation had an exponent that was outside the supported range of -999,999,999 to +999,999,999.

Examples

Example 1:

```
@DTW_MULTIPLY(NUM1, NUM2, result)
```

- Input: NUM1 = "4", NUM2 = "5"
- Returns: result = "20"

Example 2:

```
@DTW_rMULTIPLY("0.9", NUM2)
```

- Input: NUM2 = "0.8"
- Returns: "0.72"

DTW_POWER

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Raises a whole number to a whole number power.

Format

@DTW_POWER(number1, number2, precision, result)

@DTW_POWER(number1, number2, result)

@DTW_rPOWER(number1, number2, precision)

@DTW_rPOWER(number1, number2)

Parameters

Table 73. DTW_POWER Parameters

Data Type	Parameter	Use	Description
float	<i>number1</i>	IN	A variable or literal string representing a number that is to be raised to a power.
float	<i>number2</i>	IN	A variable or literal string representing a number.
integer	<i>precision</i>	IN	A variable or literal string representing a positive whole number that specifies the precision of the result. The default is 9.
float	<i>result</i>	OUT	A variable that contains the result of <i>number1</i> raised to the power of <i>number2</i> .

Return Codes

Table 74. DTW_POWER Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
4000	A parameter contains an invalid whole number value.
4001	A parameter contains an invalid number value.
4002	The result of an arithmetic operation had an exponent that was outside the supported range of -999,999,999 to +999,999,999.

Examples

Example 1:

```
@DTW_POWER(NUM1, NUM2, result)
```

- Input: NUM1 = "2", NUM2 = "-3"

- Returns: result = "0.125"

Example 2:

@DTW_rPOWER("1.7", NUM2, precision)

- Input: NUM2 = "8", precision = "5"
- Returns: "69.758"

DTW_SUBTRACT

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Subtracts one number from the other number.

Format

@DTW_SUBTRACT(number1, number2, precision, result)

@DTW_SUBTRACT(number1, number2, result)

@DTW_rSUBTRACT(number1, number2, precision)

@DTW_rSUBTRACT(number1, number2)

Parameters

Table 75. DTW_SUBTRACT Parameters

Data Type	Parameter	Use	Description
float	<i>number1</i>	IN	A variable or literal string representing a number from which another number is to be subtracted.
float	<i>number2</i>	IN	A variable or literal string representing a number.
integer	<i>precision</i>	IN	A variable or literal string representing a positive whole number that specifies the precision of the result. The default is 9.
float	<i>result</i>	OUT	A variable that contains the difference of <i>number1</i> and <i>number2</i> .

Return Codes

Table 76. DTW_SUBTRACT Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
4000	A parameter contains an invalid whole number value.
4001	A parameter contains an invalid number value.
4002	The result of an arithmetic operation had an exponent that was outside the supported range of -999,999,999 to +999,999,999.

Examples

Example 1:

```
@DTW_SUBTRACT(NUM1, NUM2, comp)
%IF(comp > "0")
<p>$(NUM1) is larger than $(NUM2).
%ENDIF
```

- Input: NUM2 = "2.07"
- Returns: "-0.77"

This example shows a way to compare numeric values, which are strings in Net.Data.

Example 2:

```
@DTW_SUBTRACT(NUM1, NUM2, result)
• Input: NUM1 = "1.3, NUM2 = "1.07"
• Returns: result = "0.23"
```

Example 3:

```
@DTW_rSUBTRACT("1.3", NUM2)
• Input: NUM2 = "2.07"
• Returns: "-0.77"
```

String Functions

The following functions are the set of standard string functions that Net.Data supports:

- "DTW_ASSIGN" on page 168
- "DTW_CHARTOHEX" on page 169
- "DTW_CONCAT" on page 170
- "DTW_DELSTR" on page 171
- "DTW_HEXTOCHAR" on page 173
- "DTW_INSERT" on page 174
- "DTW_LASTPOS" on page 176
- "DTW_LENGTH" on page 178
- "DTW_LOWERCASE" on page 179
- "DTW_POS" on page 181
- "DTW_REPLACE" on page 183
- "DTW_REVERSE" on page 185
- "DTW_STRIP" on page 186
- "DTW_SUBSTR" on page 188
- "DTW_TRANSLATE" on page 190
- "DTW_UPPERCASE" on page 192

MBCS support for OS/390, OS/2, Windows NT, and UNIX: You can specify multibyte character set (MBCS) support for word and string functions with the DTW_MBMODE configuration value. Specify this value in the Net.Data initialization file; the default is no support. You can override the value in the initialization file by setting the DTW_MBMODE variable in a Net.Data macro. See the configuration variable section in *Net.Data Administration and Programming Guide* and "DTW_MBMODE" on page 105 for more information.

MBCS support for OS/400: DBCS support is provided automatically and does not require this variable.

Unicode support for OS/2, Windows NT, and UNIX: You can specify Unicode UTF-8 support for word and string functions with the DTW_UNICODE configuration value. Specify this value in the Net.Data initialization file; the default is no support. See the configuration variable section in the *Net.Data Administration and Programming Guide* for more information

DTW_ASSIGN

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Assigns a value to a variable.

Format

@DTW_ASSIGN(stringOut, stringIn)

Parameters

Table 77. DTW_ASSIGN Parameters

Data Type	Parameter	Use	Description
string	<i>stringOut</i>	OUT	A variable that contains the literal string identical to <i>stringIn</i> .
string	<i>stringIn</i>	IN	A variable or literal string.

Return Codes

Table 78. DTW_ASSIGN Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.

Examples

Example 1:

```
@DTW_ASSIGN(RC, "0")
```

- Sets RC to "0".

Example 2:

```
@DTW_ASSIGN(string1, string2)
```

- Sets *string1* to the value of *string2*.

DTW_CHARTOHEX

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Converts each character in a string to two hexadecimal characters.

Format

@DTW_CHARTOHEX(stringIn, stringOut)

@DTW_rCHARTOHEX(stringIn)

Parameters

Table 79. DTW_CHARTOHEX Parameters

Data Type	Parameter	Use	Description
string	<i>stringIn</i>	IN	A variable or literal string that is to be converted.
string	<i>stringOut</i>	OUT	A variable that contains <i>stringIn</i> represented in hexadecimal format.

Return Codes

Table 80. DTW_CHARTOHEX Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.

Usage Notes

Each hexadecimal character represents 4-bits of the input character (a character is represented by 8 bits).

Examples

Example 1: EBCDIC operating systems

@DTW_rCHARTOHEX("12345")

- Returns: "F1F2F3F4F5"

Example 2: ASCII operating systems

@DTW_rCHARTOHEX("12345")

- Returns: "3132333435"

DTW_CONCAT

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Concatenates two strings.

Format

@DTW_CONCAT(stringIn1, stringIn2, stringOut)

@DTW_rCONCAT(stringIn1, stringIn2)

Parameters

Table 81. DTW_CONCAT Parameters

Data Type	Parameter	Use	Description
string	<i>stringIn1</i>	IN	A variable or literal string.
string	<i>stringIn2</i>	IN	A variable or literal string.
string	<i>stringOut</i>	OUT	A variable that contains the string ' <i>stringIn1stringIn2</i> ', where <i>string1</i> is concatenated with <i>string2</i> .

Return Codes

Table 82. DTW_CONCAT Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.

Examples

Example 1:

```
@DTW_CONCAT("This", " is a test.", result)
```

- Returns: result = "This is a test."

Example 2:

```
@DTW_CONCAT(string1, "1-2-3", result)
```

- Input: string1 = "Testing "
- Returns: result = "Testing 1-2-3"

Example 3:

```
@DTW_rCONCAT("This", " is a test.")
```

- Returns: "This is a test."

DTW_DELSTR

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Deletes a substring of a string from the *n*th character for *length* characters.

Format

@DTW_DELSTR(stringIn, n, length, stringOut)

@DTW_DELSTR(stringIn, n, stringOut)

@DTW_rDELSTR(stringIn, n, length)

@DTW_rDELSTR(stringIn, n)

Parameters

Table 83. DTW_DELSTR Parameters

Data Type	Parameter	Use	Description
string	<i>stringIn</i>	IN	A variable or literal string.
integer	<i>n</i>	IN	The position of the character at which the substring to delete begins. If <i>n</i> is greater than the length of <i>stringIn</i> , <i>stringOut</i> is set to the value of <i>stringIn</i> .
integer	<i>length</i>	IN	The length of the substring to delete. The default is to delete all characters to the end of <i>stringIn</i> .
string	<i>stringOut</i>	OUT	A variable that contains the modified form of <i>stringIn</i> .

Return Codes

Table 84. DTW_DELSTR Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
1007	A parameter contains a value which is not valid.

Examples

Example 1:

```
@DTW_DELSTR("abcde", "3", "2", result)
```

- Returns: result = "abe"

Example 2:

```
@DTW_rDELSTR("abcde", "4", "1")
```

- Returns: "abce"

DTW_HEXTOCHAR

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Converts each hexadecimal character in a string to a character value.

Format

@DTW_HEXTOCHAR(stringIn, stringOut)

@DTW_rHEXTOCHAR(stringIn)

Parameters

Table 85. DTW_HEXTOCHAR Parameters

Data Type	Parameter	Use	Description
string	<i>stringIn</i>	IN	A variable or literal string that is to be converted.
string	<i>stringOut</i>	OUT	A variable that contains <i>stringIn</i> represented in character format.

Return Codes

Table 86. DTW_HEXTOCHAR Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
1007	A parameter contains a value which is not valid.

Usage Notes

Each hexadecimal character in the input string represents 4 bits in the resultant character string (a character is represented by 8 bits). The input string must contain an even number of hexadecimal characters and can contain the following characters: 0-9, A-F, and a-f.

Examples

Example 1: EBCDIC operating systems

```
@DTW_rHEXTOCHAR("F1F2F3")
```

- Returns: "123"

Example 2: ASCII operating systems

```
@DTW_rHEXTOCHAR("313233")
```

- Returns: "123"

DTW_INSERT

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Inserts a string into another string starting after the *n*th character.

Format

@DTW_INSERT(stringIn1, stringIn2, n, length, pad, stringOut)

@DTW_INSERT(stringIn1, stringIn2, n, length, stringOut)

@DTW_INSERT(stringIn1, stringIn2, n, stringOut)

@DTW_INSERT(stringIn1, stringIn2, stringOut)

@DTW_rINSERT(stringIn1, stringIn2, n, length, pad)

@DTW_rINSERT(stringIn1, stringIn2, n, length)

@DTW_rINSERT(stringIn1, stringIn2, n)

@DTW_rINSERT(stringIn1, stringIn2)

Parameters

Table 87. DTW_INSERT Parameters

Data Type	Parameter	Use	Description
string	<i>stringIn1</i>	IN	A variable or literal string to be inserted into <i>stringIn2</i> .
string	<i>stringIn2</i>	IN	A variable or literal string.
integer	<i>n</i>	IN	The character position in <i>stringIn2</i> after which <i>stringIn1</i> is inserted. If <i>n</i> is greater than the length of <i>stringIn2</i> , it is padded with the padding character, <i>pad</i> , until it has enough characters. The default is to insert at the beginning of <i>stringIn2</i> .
integer	<i>length</i>	IN	The number of characters of <i>stringIn1</i> to insert. The string is padded with the padding character, <i>pad</i> , if this parameter is greater than the length of <i>stringIn1</i> . The default is the length of <i>stringIn1</i> .
integer	<i>pad</i>	IN	The padding character, as described for <i>n</i> and <i>length</i> . The default pad character is a blank.
string	<i>stringOut</i>	OUT	A variable that contains <i>stringIn2</i> modified by inserting part or all of <i>stringIn1</i> .

Return Codes

Table 88. DTW_INSERT Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.

Table 88. DTW_INSERT Return Codes (continued)

Return Code	Explanation
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
1007	A parameter contains a value which is not valid.

Examples

Example 1:

```
@DTW_INSERT("123", "abc", result)
```

- Returns: result = "123abc"

Example 2:

```
@DTW_INSERT("123", "abc", "5", result)
```

- Returns: result = "abc 123"

Example 3:

```
@DTW_INSERT("123", "abc", "5", "6", result)
```

- Returns: result = "abc 123 "

Example 4:

```
@DTW_INSERT("123", "abc", "5", "6", "/", result)
```

- Returns: result = "abc//123//"

Example 5:

```
@DTW_rINSERT("123", "abc", "5", "6", "+")
```

- Returns: "abc++123++"

DTW_LASTPOS

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Returns the position of the last occurrence of a string in another string, starting from the *n*th character and working backwards (right to left).

Format

@DTW_LASTPOS(stringIn1, stringIn2, n, position)

@DTW_LASTPOS(stringIn1, stringIn2, position)

@DTW_rLASTPOS(stringIn1, stringIn2, n)

@DTW_rLASTPOS(stringIn1, stringIn2)

Parameters

Table 89. DTW_LASTPOS Parameters

Data Type	Parameter	Use	Description
string	<i>stringIn1</i>	IN	A variable or literal string searched for in <i>stringIn2</i> .
string	<i>stringIn2</i>	IN	A variable or literal string.
integer	<i>n</i>	IN	The character position in <i>stringIn2</i> to begin searching for <i>stringIn1</i> . The default is to start searching at the last character and scan backwards (from right to left).
integer	<i>position</i>	OUT	The position of the last occurrence of <i>stringIn1</i> in <i>stringIn2</i> . If no occurrence is found, 0 is returned.

Return Codes

Table 90. DTW_LASTPOS Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
1007	A parameter contains a value which is not valid.

Examples

Example 1:

```
@DTW_LASTPOS(" ", "abc def ghi", result)
```

- Returns: result = "8"

Example 2:

```
@DTW_LASTPOS(" ", "abc def ghi", "10", result)
```

- Returns: result = "8"

Example 3:

```
@DTW_rLASTPOS(" ", "abc def ghi", "7")
```

- Returns: "4"

DTW_LENGTH

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Returns the length of a string.

Format

@DTW_LENGTH(stringIn, length)

@DTW_rLENGTH(stringIn)

Parameters

Table 91. DTW_LENGTH Parameters

Data Type	Parameter	Use	Description
string	<i>stringIn</i>	IN	A variable or literal string.
integer	<i>length</i>	OUT	A symbol containing the number of characters in <i>stringIn</i> .

Return Codes

Table 92. DTW_LENGTH Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.

Examples

Example 1:

```
@DTW_LENGTH("abcdefgh", result)
```

- Returns: result = "8"

Example 2:

```
@DTW_rLENGTH("")
```

- Returns: "0"

DTW_LOWERCASE

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Returns a string in all lowercase.

Format

@DTW_LOWERCASE(stringIn, stringOut)

@DTW_rLOWERCASE(stringIn)

@DTW_mLOWERCASE(stringMult1, stringMult2, ..., stringMultn)

Parameters

Table 93. DTW_LOWERCASE Parameters

Data Type	Parameter	Use	Description
string	<i>stringIn</i>	IN	A variable or literal string with characters of any case.
string	<i>stringOut</i>	OUT	A variable that contains <i>stringIn</i> with all characters in lowercase.
string	<i>stringMult</i>	INOUT	<ul style="list-style-type: none">On input: A variable that contains a string.On output: A variable that contains the input string converted to lowercase.

Return Codes

Table 94. DTW_LOWERCASE Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.

Examples

Example 1:

```
@DTW_LOWERCASE("This", stringOut)
```

- Returns: stringOut = "this"

Example 2:

```
@DTW_rLOWERCASE(string1)
```

- Input: string1 = "Hello"
- Returns: "hello"

Example 3:

```
@DTW_mLOWERCASE(string1, string2, string3)
```

- Input: string1 = "THIS", string2 = "IS", string3 = "LOWERCASE"
- Returns: string1 = "this", string2 = "is", string3 = "lowercase"

DTW_POS

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Returns the position of the first occurrence of a string in another string, using a forward search pattern.

Format

@DTW_POS(stringIn1, stringIn2, n, nOut)

@DTW_POS(stringIn1, stringIn2, nOut)

@DTW_rPOS(stringIn1, stringIn2, n)

@DTW_rPOS(stringIn1, stringIn2)

Parameters

Table 95. DTW_POS Parameters

Data Type	Parameter	Use	Description
string	<i>stringIn1</i>	IN	A variable or literal string to search for.
string	<i>stringIn2</i>	IN	A variable or literal string to search.
integer	<i>n</i>	IN	The character position in <i>stringIn2</i> to begin searching. The default value is to start searching at the first character of <i>stringIn2</i> .
integer	<i>nOut</i>	OUT	A variable that contains the position of the first occurrence of <i>stringIn1</i> in <i>stringIn2</i> . If no occurrence is found, 0 is returned.

Return Codes

Table 96. DTW_POS Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
1007	A parameter contains a value which is not valid.

Examples

Example 1:

```
@DTW_POS("day", "Saturday", result)
```

- Returns: result = "6"

Example 2:

```
@DTW_POS("a", "Saturday", "3", result)
```

- Returns: result = "7"

Example 3:

```
@DTW_rPOS(" ", "abc def ghi", "5")
```

- Returns: "8"

DTW_REPLACE

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Replaces characters in a string.

Format

@DTW_REPLACE(stringIn, stringFrom, stringTo, n, option, stringOut)

@DTW_REPLACE(stringIn, stringFrom, stringTo, n, stringOut)

@DTW_REPLACE(stringIn, stringFrom, stringTo, stringOut)

@DTW_rREPLACE(stringIn, stringFrom, stringTo, n, option)

@DTW_rREPLACE(stringIn, stringFrom, stringTo, n)

@DTW_rREPLACE(stringIn, stringFrom, stringTo)

Parameters

Table 97. DTW_REPLACE Parameters

Data Type	Parameter	Use	Description
string	<i>stringIn</i>	IN	A variable or literal string that is to be searched.
string	<i>stringFrom</i>	IN	A variable or literal string that is to be replaced.
string	<i>stringTo</i>	IN	A variable or literal string that replaces occurrences of <i>stringFrom</i> .
integer	<i>n</i>	IN	The position of the character at which to begin the search.
string	<i>option</i>	IN	Specifies whether to replace all occurrences, or just the first occurrence, and can have one of the following values: A or a Replaces all occurrences. The default is A. F or f Replaces only the first occurrence.
string	<i>stringOut</i>	OUT	A variable that contains <i>stringIn</i> with occurrences of <i>stringFrom</i> replaced by <i>stringTo</i> .

Return Codes

Table 98. DTW_REPLACE Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.

Table 98. DTW_REPLACE Return Codes (continued)

Return Code	Explanation
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.

Examples

Example 1:

@DTW_REPLACE("ABCABCABC", "AB", "1234")

- Returns: "1234C1234C1234C"

DTW_REVERSE

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Reverses a string so that the last character is first, second to last is second, until the entire string is reversed.

Format

@DTW_REVERSE(stringIn, stringOut)

@DTW_rREVERSE(stringIn)

Parameters

Table 99. DTW_REVERSE Parameters

Data Type	Parameter	Use	Description
string	<i>stringIn</i>	IN	A variable or literal string to reverse.
string	<i>stringOut</i>	OUT	A variable that contains the reversed form of <i>stringIn</i> .

Return Codes

Table 100. DTW_REVERSE Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.

Examples

Example 1:

```
@DTW_REVERSE("This is it.", result)
• Returns: result = ".ti si sihT"
```

Example 2:

```
@DTW_rREVERSE(string1)
• Input: string1 = "reversed"
• Returns: "desrever"
```

DTW_STRIP

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Removes leading blanks, trailing blanks, or both from a string.

Format

@DTW_STRIP(stringIn, option, stringOut)

@DTW_STRIP(stringIn, stringOut)

@DTW_rSTRIP(stringIn, option)

@DTW_rSTRIP(stringIn)

Parameters

Table 101. DTW_STRIP Parameters

Data Type	Parameter	Use	Description
string	<i>stringIn</i>	IN	A variable or literal string.
string	<i>option</i>	IN	Specifies which blanks to remove from <i>stringIn</i> . The default is B. B or b - remove both leading and trailing blanks L or l - remove leading blanks only T or t - remove trailing blanks only
string	<i>stringOut</i>	OUT	A variable that contains <i>stringIn</i> with blanks removed as specified by option.

Return Codes

Table 102. DTW_STRIP Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
1007	A parameter contains a value which is not valid.

Examples

Example 1:

```
@DTW_STRIP(" day ", result)
```

- Returns: result = "day"

Example 2:

```
@DTW_STRIP(" day ", "T", result)
```

- Returns: `result = " day"`

Example 3:

```
@DTW_rSTRIP("  a day  ", "L")
```

- Returns: `"a day "`

DTW_SUBSTR

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Returns a substring of a string, with optional pad characters.

Format

@DTW_SUBSTR(stringIn, n, length, pad, stringOut)

@DTW_SUBSTR(stringIn, n, length, stringOut)

@DTW_SUBSTR(stringIn, n, stringOut)

@DTW_rSUBSTR(stringIn, n, length, pad)

@DTW_rSUBSTR(stringIn, n, length)

@DTW_rSUBSTR(stringIn, n)

Parameters

Table 103. DTW_SUBSTR Parameters

Data Type	Parameter	Use	Description
string	<i>stringIn</i>	IN	A variable or literal string to be searched.
integer	<i>n</i>	IN	The first character position of the substring. The default is to start at the beginning of <i>stringIn</i> .
integer	<i>length</i>	IN	The number of characters of the substring. The default is the rest of the string.
string	<i>pad</i>	IN	The padding character used if <i>n</i> is greater than the length of <i>stringIn</i> or if <i>length</i> is longer than <i>stringIn</i> . The default is a blank.
string	<i>stringOut</i>	OUT	A variable that contains a substring of <i>stringIn</i> .

Return Codes

Table 104. DTW_SUBSTR Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
1007	A parameter contains a value which is not valid.

Examples

Example 1:

```
@DTW_SUBSTR("abc", "2", result)
```


- Returns: result = "bc"

Example 2:

```
@DTW_SUBSTR("abc", "2", "4", result)
```

- Returns: result = "bc "

Example 3:

```
@DTW_SUBSTR("abc", "2", "4", ".", result )
```

- Returns: result = "bc.."

Example 4:

```
@DTW_rSUBSTR("abc", "2", "6", ".")
```

- Returns: "bc...."

DTW_TRANSLATE

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Returns a string with each character translated to another character or unchanged.

Format

@DTW_TRANSLATE(stringIn, tableO, tableI, default, stringOut)

@DTW_TRANSLATE(stringIn, tableO, tableI, stringOut)

@DTW_TRANSLATE(stringIn, tableO, stringOut)

@DTW_TRANSLATE(stringIn, stringOut)

@DTW_rTRANSLATE(stringIn, tableO, tableI, default)

@DTW_rTRANSLATE(stringIn, tableO, tableI)

@DTW_rTRANSLATE(stringIn, tableO)

@DTW_rTRANSLATE(stringIn)

Parameters

Table 105. DTW_TRANSLATE Parameters

Data Type	Parameter	Use	Description
string	<i>stringIn</i>	IN	A variable or literal string.
string	<i>tableO</i>	IN	A variable or literal string used as a translation table. Use null (") to specify <i>tableI</i> or <i>default</i> ; otherwise this parameter is optional.
string	<i>tableI</i>	IN	A variable or literal string searched for in <i>stringIn</i> . Use null (") to specify <i>default</i> ; otherwise this parameter is optional.
string	<i>default</i>	IN	The default character to use. The default is a blank.
string	<i>stringOut</i>	OUT	A variable that contains the translated result of <i>stringIn</i> .

Return Codes

Table 106. DTW_TRANSLATE Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
1007	A parameter contains a value which is not valid.

Usage Notes

1. If *tableI*, *tableO*, and the *default* character are not in the parameter list, the *stringIn* parameter is translated to uppercase.
2. If *tableI* and *tableO* are in the list, each character in the input string is searched for in *tableI* and translated to the corresponding character in *tableO*. If a character in *tableI* has no corresponding character in *tableO*, the *default* character is used instead.

Examples

Example 1:

```
@DTW_TRANSLATE("abbc", result)
```

- Returns: result = "ABBC"

Example 2:

```
@DTW_TRANSLATE("abbc", "R", "bc", result)
```

- Returns: result = "aRR "

Example 3:

```
@DTW_rTRANSLATE("abcdef", "12", "abcd", ".")
```

- Returns: "12..ef"

Example 4:

```
@DTW_rTRANSLATE("abbc", "", "", "")
```

- Returns: "abbc"

DTW_UPPERCASE

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Returns a string in uppercase.

Format

@DTW_UPPERCASE(stringIn, stringOut)

@DTW_rUPPERCASE(stringIn)

@DTW_mUPPERCASE(stringMult1, stringMult2, ..., stringMultn)

Parameters

Table 107. DTW_UPPERCASE Parameters

Data Type	Parameter	Use	Description
string	<i>stringIn</i>	IN	A variable or literal string with characters of any case.
string	<i>stringOut</i>	OUT	A variable that contains <i>stringIn</i> with all characters in uppercase.
string	<i>stringMult</i>	INOUT	<ul style="list-style-type: none">On input: A variable that contains a string.On output: A variable that contains the input string converted to uppercase.

Return Codes

Table 108. DTW_UPPERCASE Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.

Examples

Example 1:

```
@DTW_UPPERCASE("Test", result)
```

- Returns: result = "TEST"

Example 2:

```
@DTW_rUPPERCASE(string1)
```

- Input: string1 = "Web pages"
- Returns: "WEB PAGES"

Example 3:

```
@DTW_mUPPERCASE(string1, string2, string3)
```

- Input: string1 = "This", string2 = "is", string3 = "uppercase"
- Returns: string1 = "THIS", string2 = "IS", string3 = "UPPERCASE"

Word Functions

These functions supplement the string functions by modifying words or sets of words. Net.Data interprets a word as a space-delimited string, or a string with spaces on both sides. Here are some examples:

String value	Number of words
one two three	3
one , two , three	5
Part 2: Internet Sales Grow	5

MBCS support for OS/390, OS/2, Windows NT, and UNIX: You can specify multibyte character set (MBCS) support for word and string functions with the DTW_MBMODE configuration value. Specify this value in the Net.Data initialization file; the default is no support. You can override the value in the initialization file by setting the DTW_MBMODE variable in a Net.Data macro. See the configuration variable section in *Net.Data Administration and Programming Guide* and “DTW_MBMODE” on page 105 for more information.

MBCS support for OS/400: DBCS support is provided automatically and does not require this variable.

Unicode support for OS/2, Windows NT, and UNIX: You can specify Unicode UTF-8 support for word and string functions with the DTW_UNICODE configuration value. Specify this value in the Net.Data initialization file; the default is no support. See the configuration variable section in the *Net.Data Administration and Programming Guide* for more information.

The following functions are word functions that Net.Data supports:

- “DTW_DELWORD” on page 194
- “DTW_SUBWORD” on page 196
- “DTW_WORD” on page 198
- “DTW_WORDINDEX” on page 199
- “DTW_WORDLENGTH” on page 200
- “DTW_WORDPOS” on page 201
- “DTW_WORDS” on page 203

DTW_DELWORD

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Deletes words in a string, starting from word *n* for the number of words specified by *length*.

Format

@DTW_DELWORD(stringIn, n, length, stringOut)

@DTW_DELWORD(stringIn, n, stringOut)

@DTW_rDELWORD(stringIn, n, length)

@DTW_rDELWORD(stringIn, n)

Parameters

Table 109. DTW_DELWORD Parameters

Data Type	Parameter	Use	Description
string	<i>stringIn</i>	IN	A variable or literal string.
integer	<i>n</i>	IN	The word position of the first word to be deleted.
integer	<i>length</i>	IN	The number of words to delete. The default is to delete all words from <i>n</i> to the end of <i>stringIn</i> . Optional parameter.
string	<i>stringOut</i>	OUT	A variable that contains the modified form of <i>stringIn</i> .

Return Codes

Table 110. DTW_DELWORD Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
1007	A parameter contains a value which is not valid.

Examples

Example 1

```
@DTW_DELWORD("Now is the time", "5", result)
```

- Returns: result = "Now is the time"

Example 2:

```
@DTW_DELWORD("Now is the time", "2", result)
```

- Returns: result = "Now"

Example 3:

```
@DTW_DELWORD("Now is the time", "2", "2", result)
```

- Returns: result = "Now time"

Example 4:

```
@DTW_rDELWORD("Now is the time.", "3")
```

- Returns: "Now is"

DTW_SUBWORD

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Returns a substring of a string, beginning at word *n* s for the number of words specified by *length*.

Format

@DTW_SUBWORD(stringIn, n, length, stringOut)

@DTW_SUBWORD(stringIn, n, stringOut)

@DTW_rSUBWORD(stringIn, n, length)

@DTW_rSUBWORD(stringIn, n)

Parameters

Table 111. DTW_SUBWORD Parameters

Data Type	Parameter	Use	Description
string	<i>stringIn</i>	IN	A variable or literal string.
integer	<i>n</i>	IN	The word position of the first word of the substring. A null is returned if this value is greater than the number of words in <i>stringIn</i> .
integer	<i>length</i>	IN	The number of words in the substring. If this value is greater than the number of words from <i>n</i> to the end of <i>stringIn</i> , all words to the end of <i>stringIn</i> are returned. The default is to return all words from <i>n</i> to the end of <i>stringIn</i> .
string	<i>stringOut</i>	OUT	A variable that contains a substring of <i>stringIn</i> specified by <i>n</i> and <i>length</i> .

Return Codes

Table 112. DTW_SUBWORD Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
1007	A parameter contains a value which is not valid.

Examples

Example 1:

```
@DTW_SUBWORD("Now is the time", "5", result)
```


- Returns: result = ""

Example 2:

```
@DTW_SUBWORD("Now is the time", "2", result)
```

- Returns: result = "is the time"

Example 3:

```
@DTW_SUBWORD("Now is the time", "2", "2", result)
```

- Returns: result = "is the"

Example 4:

```
@DTW_rSUBWORD("Now is the time", "3")
```

- Returns: "the time"

DTW_WORD

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Returns the *n*th word in a string.

Format

@DTW_WORD(stringIn, n, stringOut)

@DTW_rWORD(stringIn, n)

Parameters

Table 113. DTW_WORD Parameters

Data Type	Parameter	Use	Description
string	<i>stringIn</i>	IN	A variable or literal string.
integer	<i>n</i>	IN	The word position of the word to return. If this value is greater than the number of words in <i>stringIn</i> , a null is returned.
string	<i>stringOut</i>	OUT	A variable that contains the word at word position <i>n</i> .

Return Codes

Table 114. DTW_WORD Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
1007	A parameter contains a value which is not valid.

Examples

Example 1:

```
@DTW_WORD("Now is the time", "3", result)
```

- Returns: result = "the"

Example 2:

```
@DTW_WORD("Now is the time", "5", result)
```

- Returns: result = ""

Example 3:

```
@DTW_rWORD("Now is the time", "4")
```

- Returns: "time"

DTW_WORDINDEX

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Returns the character position of the first character in the *n*th word of a string.

Format

@DTW_WORDINDEX(stringIn, n, stringOut)

@DTW_rWORDINDEX(stringIn, n)

Parameters

Table 115. DTW_WORDINDEX Parameters

Data Type	Parameter	Use	Description
string	<i>stringIn</i>	IN	A variable or literal string.
integer	<i>n</i>	IN	The word position of the word to index. If this value is greater than the number of words in the input string, 0 is returned.
string	<i>stringOut</i>	OUT	A variable that contains the character position of the <i>n</i> th word of <i>stringIn</i> .

Return Codes

Table 116. DTW_WORDINDEX Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
1007	A parameter contains a value which is not valid.

Examples

Example 1:

```
@DTW_WORDINDEX("Now is the time", "3", result)
```

- Returns: result = "8"

Example 2:

```
@DTW_WORDINDEX("Now is the time", "6", result)
```

- Returns: result = "0"

Example 3:

```
@DTW_rWORDINDEX("Now is the time", "2")
```

- Returns: "5"

DTW_WORDLENGTH

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Returns the length of the *n*th word of a string.

Format

@DTW_WORDLENGTH(stringIn, n, stringOut)

@DTW_rWORDLENGTH(stringIn, n)

Parameters

Table 117. DTW_WORDLENGTH Parameters

Data Type	Parameter	Use	Description
string	<i>stringIn</i>	IN	A variable or literal string.
integer	<i>n</i>	IN	The word position of the word whose length you want to know. If this value is greater than the number of words in the input string, 0 is returned.
string	<i>stringOut</i>	OUT	A variable that contains the length of the <i>n</i> th word in <i>stringIn</i> .

Return Codes

Table 118. DTW_WORDLENGTH Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
1007	A parameter contains a value which is not valid.

Examples

Example 1:

```
@DTW_WORDLENGTH("Now is the time", "1", result)
```

- Returns: result = "3"

Example 2:

```
@DTW_rWORDLENGTH("Now is the time", "6")
```

- Returns: "0"

DTW_WORDPOS

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Returns the word number of the first occurrence of one string within another.

Format

@DTW_WORDPOS(stringIn1, stringIn2, n, stringOut)

@DTW_WORDPOS(stringIn1, stringIn2, stringOut)

@DTW_rWORDPOS(stringIn1, stringIn2, n)

@DTW_rWORDPOS(stringIn1, stringIn2)

Parameters

Table 119. DTW_WORDPOS Parameters

Data Type	Parameter	Use	Description
string	<i>stringIn1</i>	IN	A variable or literal string.
string	<i>stringIn2</i>	IN	A variable or literal string to search.
integer	<i>n</i>	IN	The word position in <i>stringIn2</i> to begin searching. If this value is larger than the number of words in <i>stringIn2</i> , 0 is returned. The default is to search from the beginning of <i>stringIn2</i> .
string	<i>stringOut</i>	OUT	The word position of <i>stringIn1</i> in <i>stringIn2</i> .

Return Codes

Table 120. DTW_WORDPOS Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
1007	A parameter contains a value which is not valid.

Usage Notes

Multiple blanks are treated as single blanks for comparison.

Examples

Example 1:

```
@DTW_WORDPOS("the", "Now is the time", result)
```

- Returns: result = "3"

Example 2:

```
@DTW_WORDPOS("The", "Now is the time", result)
```

- Returns: result = "0"

Example 3:

```
@DTW_WORDPOS("The", "Now is the time", "5", result)
```

- Returns: result = "0"

Example 4:

```
@DTW_WORDPOS("is the", "Now is the time", result)
```

- Returns: result = "2"

Example 5:

```
@DTW_rWORDPOS("be", "To be or not to be", "3")
```

- Returns: "6"

DTW_WORDS

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Returns the number of words in a string.

Format

@DTW_WORDS(stringIn, stringOut)

@DTW_rWORDS(stringIn)

Parameters

Table 121. DTW_WORDS Parameters

Data Type	Parameter	Use	Description
string	<i>stringIn</i>	IN	A variable or literal string.
string	<i>stringOut</i>	OUT	A variable that contains the number of words in <i>stringIn</i> .

Return Codes

Table 122. DTW_WORDS Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.

Examples

Example 1:

```
@DTW_WORDS("Now is the time", result)
```

- Returns:

```
result = "4"
```

Example 2:

```
@DTW_rWORDS(" ")
```

- Returns: "0"

Table Functions

These functions simplify working with Net.Data tables and are more efficient than writing your own functions using REXX, C, or Perl.

- “DTW_TB_APPENDROW” on page 205
- “DTW_TB_COLS” on page 207
- “DTW_TB_DELETEROW” on page 209
- “DTW_TB_DELETECOL” on page 208

- “DTW_TB_DLIST” on page 211
- “DTW_TB_DUMP” on page 213
- “DTW_TB_DUMPV” on page 214
- “DTW_TB_GETN” on page 216
- “DTW_TB_GETV” on page 218
- “DTW_TB_HTMLENCODING” on page 220
- “DTW_TB_INPUT_CHECKBOX” on page 222
- “DTW_TB_INPUT_RADIO” on page 224
- “DTW_TB_INPUT_TEXT” on page 226
- “DTW_TB_INSERTCOL” on page 228
- “DTW_TB_INSERTROW” on page 229
- “DTW_TB_LIST” on page 231
- “DTW_TB_QUERYCOLNONJ” on page 233
- “DTW_TB_ROWS” on page 235
- “DTW_TB_SELECT” on page 236
- “DTW_TB_SETCOLS” on page 238
- “DTW_TB_SETN” on page 239
- “DTW_TB_SETV” on page 241
- “DTW_TB_TABLE” on page 243
- “DTW_TB_TEXTAREA” on page 245

DTW_TB_APPENDROW

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X		X	X	X	X	X	X

Purpose

Adds one or more rows to the end of a Net.Data table.

Format

@DTW_TB_APPENDROW(table, rows)

Parameters

Table 123. DTW_TB_APPENDROW Parameters

Data Type	Parameter	Use	Description
table	<i>table</i>	INOUT	The macro table variable for which rows are appended.
integer	<i>rows</i>	IN	The number of rows to append to <i>table</i> .

Return Codes

Table 124. DTW_TB_APPENDROW Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1004	A parameter passed on a function call, required to be a Net.Data macro table variable, was of a different variable type.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1007	A parameter contains a value which is not valid.
1008	A parameter is outside of table bounds.
1010	Data was written to the table until it was full, and the remainder of the data was discarded.

Usage Notes

1. The number of columns in the table must be set before calling DTW_TB_APPENDROW(). You can set the number of columns with the DTW_TB_SETCOLS() or DTW_TB_INSERTCOL() functions, or by passing the table to a language environment to be set.
2. You can assign values to the new rows with the DTW_TB_SETV() function after rows are appended to the table, or pass the table to a language environment for processing.
3. If there is a limit on the total number of rows allowed in the table, and the number of rows to be appended can cause the limit to be exceeded, an error is returned to the caller.

Examples

Example 1: Appends ten rows to the table

```
%DEFINE myTable = %TABLE  
@DTW_TB_APPENDROW(myTable, "10")
```

DTW_TB_COLS

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Returns the number of columns in a Net.Data table.

Format

@DTW_TB_COLS(table, cols)

@DTW_TB_rCOLS(table)

Parameters

Table 125. DTW_TB_COLS Parameters

Data Type	Parameter	Use	Description
table	<i>table</i>	IN	The macro table variable for which the number of columns are returned.
integer	<i>cols</i>	OUT	A variable that contains the number of columns in <i>table</i> .

Return Codes

Table 126. DTW_TB_COLS Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1004	A parameter passed on a function call, required to be a Net.Data macro table variable, was of a different variable type.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.

Examples

Example 1: Retrieves the number of columns and assigns the value to *cols*

```
%DEFINE myTable = %TABLE
%DEFINE cols = ""
...
@FillTable(myTable)
...
@DTW_TB_COLS(myTable, cols)
```

Example 2: Retrieves and displays the value for the current number of columns in the table

```
%DEFINE myTable = %TABLE
...
@FillTable(myTable)
...
<p>My table contains @DTW_TB_rCOLS(myTable) columns.</p>
```

DTW_TB_DELETECOL

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X		X	X	X	X	X	X

Purpose

Deletes one or more columns from a Net.data table.

Format

@DTW_TB_DELETECOL(table, after_col, cols)

Parameters

Table 127. DTW_TB_DELETECOL Parameters

Data Type	Parameter	Use	Description
table	<i>table</i>	INOUT	The macro table variable from which columns are to be deleted.
integer	<i>after_col</i>	IN	The number of the column after which subsequent columns are to be deleted. To delete the first column, specify 0.
integer	<i>cols</i>	IN	The number of columns to delete from <i>table</i> .

Return Codes

Table 128. DTW_TB_DELETECOL Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1004	A parameter passed on a function call, required to be a Net.Data macro table variable, was of a different variable type.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1007	A parameter contains a value which is not valid.
1008	A parameter is outside of table bounds.

Examples

Example 1: Deletes the third and fourth columns from the table

```
%DEFINE myTable = %TABLE  
  
@DTW_TB_DELETECOL(myTable, "3", "2")
```

Example 2: Deletes the first column from the table

```
%DEFINE myTable = %TABLE  
  
@DTW_TB_DELETECOL(myTable, "0", "1")
```

DTW_TB_DELETEROW

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X		X	X	X	X	X	X

Purpose

Deletes one or more rows from a Net.Data table.

Format

@DTW_TB_DELETEROW(table, start_row, rows)

Parameters

Table 129. DTW_TB_DELETEROW Parameters

Data Type	Parameter	Use	Description
table	<i>table</i>	INOUT	The macro table variable from which rows are to be deleted.
integer	<i>start_row</i>	IN	The row number of the first row in <i>table</i> to delete.
integer	<i>rows</i>	IN	The number of rows to delete from <i>table</i> .

Return Codes

Table 130. DTW_TB_DELETEROW Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1004	A parameter passed on a function call, required to be a Net.Data macro table variable, was of a different variable type.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1007	A parameter contains a value which is not valid.
1008	A parameter is outside of table bounds.

Usage Notes

The number of columns in the table must be set before calling DTW_TB_DELETEROW(). You can set the number of columns with the DTW_TB_SETCOLS() or DTW_TB_INSERTCOL() functions, or by passing the table to a language environment to be set.

Examples

Example 1: Deletes five rows starting at row 10 of a table

```
%DEFINE myTable = %TABLE
```

```
@DTW_TB_DELETEROW(myTable, "10", "5")
```

Example 2: Deletes all of the rows of a table

```
%DEFINE myTable = %TABLE  
@DTW_TB_DELETE_ROW(myTable, "1", @DTW_TB_rROWS(myTable))
```

DTW_TB_DLIST

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Generates an HTML definition list from a Net.Data table.

Format

@DTW_TB_DLIST(table, term, def, termstyle, defstyle, link, link_u, image, image_u)

@DTW_TB_DLIST(table, term, def, termstyle, defstyle, link, link_u, image)

@DTW_TB_DLIST(table, term, def, termstyle, defstyle, link, link_u)

@DTW_TB_DLIST(table, term, def, termstyle, defstyle, link)

@DTW_TB_DLIST(table, term, def, termstyle, defstyle)

@DTW_TB_DLIST(table, term, def, termstyle)

@DTW_TB_DLIST(table, term, def)

@DTW_TB_DLIST(table, term)

@DTW_TB_DLIST(table)

Parameters

Table 131. DTW_TB_DLIST Parameters

Data Type	Parameter	Use	Description
table	<i>table</i>	IN	A symbol specifying the macro table variable to display as an HTML definition list.
integer	<i>term</i>	IN	The column number in <i>table</i> that contains <i>term</i> name values (the text to go after the <dt> tag). The default is to use the first column.
integer	<i>def</i>	IN	The column number in <i>table</i> containing term definition values (the text to go after the <dd> tag). The default is to use the second column.
string	<i>termstyle</i>	IN	A variable or literal string that contains a list of HTML elements for the <i>term</i> name values. The default is to use no style tags.
string	<i>defstyle</i>	IN	A variable or literal string containing a list of HTML elements for the <i>term</i> definition values. The default is to use no style tags.
string	<i>link</i>	IN	Specifies for which HTML elements an HTML link is generated. Valid values are DT and DD. The default is not to generate HTML links.
integer	<i>link_u</i>	IN	The column number in <i>table</i> that contains the URLs for the HTML references. The default is not to generate HTML links.
string	<i>image</i>	IN	Specifies for which HTML elements an inline image is generated. Valid values are DT and DD. The default is not to generate inline images (DT).

Table 131. DTW_TB_DLIST Parameters (continued)

Data Type	Parameter	Use	Description
integer	<i>image_u</i>	IN	The column number in <i>table</i> that contains the URLs for the inline images. The default is not to generate inline images.

Return Codes

Table 132. DTW_TB_DLIST Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1004	A parameter passed on a function call, required to be a Net.Data macro table variable, was of a different variable type.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1007	A parameter contains a value which is not valid.
1008	A parameter is outside of table bounds.

Examples

Example 1: Creates a definition list producing the HTML shown below, depending on the table data

```
@DTW_TB_DLIST(Mytable,"3","4","b i","strong","DD","2","DT","1")
```

Results:

```
<dl>
<dt>
<b><i>image1text</i></b></dt>
<dd>
<a href="http://www.mycompany.com/link1.html"><strong>link1text</strong></a></dd>
<dt>
<b><i>image2text</i></b></dt>
<dd>
<a href="http://www.mycompany.com/link2.html"><strong>link2text</strong></a></dd>
<dt>
<b><i>image3text</i></b></dt>
<dd>
<a href="http://www.mycompany.com/link3.html"><strong>link3text</strong></a></dd>
<dt>
<b><i>image4text</i></b></dt>
<dd>
<a href="http://www.mycompany.com/link4.html"><strong>link4text</strong></a></dd>
</dl>
```


DTW_TB_DUMPH

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Prints out the contents of a Net.Data table using the HTML <pre> tag, where each row of the table is displayed on one line.

Format

@DTW_TB_DUMPH(table)

Parameters

Table 133. DTW_TB_DUMPH Parameters

Data Type	Parameter	Use	Description
table	<i>table</i>	IN	A symbol specifying the macro table variable to display.

Return Codes

Table 134. DTW_DB_DUMPH Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1004	A parameter passed on a function call, required to be a Net.Data macro table variable, was of a different variable type.
1007	A parameter contains a value which is not valid.

Usage Notes

If the Net.Data table is empty, an error is returned.

Examples

Example 1:

```
@DTW_TB_DUMPH(Mytable)
```

The HTML generated by this example looks like this:

```
<pre>
Name      Department      Position
Jack Smith Internet Technologies Software Engineer
Helen Williams Database      Development Manager
Alex Jones Manufacturing  Industrial Engineer
Tom Baker  Procurement    Sales Rep
</pre>
```

DTW_TB_DUMPV

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Prints out the contents of the Net.Data table using the HTML <pre> tag, where each field of the table is on one line.

Format

@DTW_TB_DUMPV(table)

Parameters

Table 135. DTW_TB_DUMPV Parameters

Data Type	Parameter	Use	Description
table	<i>table</i>	IN	A symbol specifying the macro table variable to display.

Return Codes

Table 136. DTW_TB_DUMPV Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1004	A parameter passed on a function call, required to be a Net.Data macro table variable, was of a different variable type.
1007	A parameter contains a value which is not valid.

Usage Notes

If the Net.Data table is empty, an error is returned

Examples

Example 1:

```
@DTW_TB_DUMPV(Mytable)
```

The HTML generated for this example looks like this:

```
<pre>
http://www.mycompany.com/images/image1.gif
http://www.mycompany.com/link1.html
image1text
link1text
http://www.mycompany.com/images/image2.gif
http://www.mycompany.com/link2.html
image2text
link2text
http://www.mycompany.com/images/image3.gif
http://www.mycompany.com/link3.html
image3text
link3text
http://www.mycompany.com/images/image4.gif
```

```
http://www.mycompany.com/link4.html  
image4text  
link4text  
</pre>
```

DTW_TB_GETN

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Returns a column heading from a Net.Data table.

Format

@DTW_TB_GETN(table, col, name)

@DTW_TB_rGETN(table, col)

Parameters

Table 137. DTW_TB_GETN Parameters

Data Type	Parameter	Use	Description
table	<i>table</i>	IN	The macro table variable from which a column name is returned.
integer	<i>col</i>	IN	The column number of the column whose name is to be returned.
string	<i>name</i>	OUT	A variable that contains the name of the column specified in <i>col</i> .

Return Codes

Table 138. DTW_TB_GETN Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1004	A parameter passed on a function call, required to be a Net.Data macro table variable, was of a different variable type.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
1007	A parameter contains a value which is not valid.
1008	A parameter is outside of table bounds.

Usage Notes

Before calling DTW_TB_GETN(), set the number of columns in the table. You can set the number of columns with the DTW_TB_SETCOLS() or DTW_TB_INSERTCOL() functions, or by passing the table to a language environment to be set.

Examples

Example 1: Retrieves the column name of column 4

```

%DEFINE myTable = %TABLE
%DEFINE name = ""
...
@FillTable(myTable)
...
@DTW_TB_GETN(myTable, "4", name)

```

Example 2: Retrieves the column name of the last column in the table

```

%DEFINE myTable = %TABLE
...
@FillTable(myTable)
...
<p>The column name of the last column is @DTW_TB_rGETN(myTable,
@DTW_TB_rCOLS(myTable))</p>

```

DTW_TB_GETV

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Returns the value at a given row and column in a Net.Data table.

Format

@DTW_TB_GETV(table, row, col, value)

@DTW_TB_rGETV(table, row, col)

Parameters

Table 139. DTW_TB_GETV Parameters

Data Type	Parameter	Use	Description
table	<i>table</i>	IN	The macro table variable for which a table value is returned.
integer	<i>row</i>	IN	The row number of the value to be returned.
integer	<i>col</i>	IN	The column number of the value to be returned.
string	<i>value</i>	OUT	A variable that contains the value at the row and column specified in <i>row</i> and <i>col</i> .

Return Codes

Table 140. DTW_TB_GETV Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1004	A parameter passed on a function call, required to be a Net.Data macro table variable, was of a different variable type.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
1007	A parameter contains a value which is not valid.
1008	A parameter is outside of table bounds.

Usage Notes

Before calling DTW_TB_GETV(), set the number of columns in the table. You can set the number of columns with the DTW_TB_SETCOLS() or DTW_TB_INSERTCOL() functions, or by passing the table to a language environment to be set.

Examples

Example 1: Retrieves the table value at row 6, column 3

```

%DEFINE myTable = %TABLE
%DEFINE value = ""
...
@FillTable(myTable)
...
@DTW_TB_GETV(myTable, "6", "3", value)

```

Example 2: Retrieves the table value at row 1, column 1

```

%DEFINE myTable = %TABLE
...
@FillTable(myTable)
...
<p>The table value of row 1, column 1 is @DTW_TB_rGETV(myTable, "1", "1").</p>

```

DTW_TB_HTMLENCODE

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Replaces certain characters in the data located in a Net.Data table with their corresponding HTML character escape codes.

Format

@DTW_TB_HTMLENCODE(table, collist)

@DTW_TB_HTMLENCODE(table)

Parameters

Table 141. DTW_TB_HTMLENCODE Parameters

Data Type	Parameter	Use	Description
table	<i>table</i>	INOUT	The macro table variable to modify.
string	<i>collist</i>	IN	The column numbers in <i>table</i> to encode. The default is to encode all columns.

Return Codes

Table 142. DTW_TB_HTMLENCODE Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1004	A parameter passed on a function call, required to be a Net.Data macro table variable, was of a different variable type.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1007	A parameter contains a value which is not valid.
1008	A parameter is outside of table bounds.

Usage Notes

The characters that are replaced are indicated in the table below.

Name	Character	Code
Ampersand	&	&
Double quote	"	"
Greater than	>	>
Less than	<	<

Examples

Example 1:

```
@DTW_TB_HTMLENCODE(Mytable, "3 4")
```


The special characters in columns 3 and 4 of the specified table are replaced with their encoded forms.

DTW_TB_INPUT_CHECKBOX

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Generates one or more HTML check box input tags from a Net.Data table.

Format

@DTW_TB_INPUT_CHECKBOX(table, prompt, namecol, valuecol, rows, checkedrows)

@DTW_TB_INPUT_CHECKBOX(table, prompt, namecol, valuecol, rows)

@DTW_TB_INPUT_CHECKBOX(table, prompt, namecol, valuecol)

@DTW_TB_INPUT_CHECKBOX(table, prompt, namecol)

Parameters

Table 143. DTW_TB_INPUT_CHECKBOX Parameters

Data Type	Parameter	Use	Description
table	<i>table</i>	IN	The macro table variable to display as check box input tags.
string	<i>prompt</i>	IN	The column number in <i>table</i> or a string containing the text to display next to the check box. This parameter is required but can have a null ("") value. When <i>prompt</i> is null, the value used is the value defined for <i>namecol</i> .
string	<i>namecol</i>	IN	The column number in <i>table</i> or a string containing the input field names.
integer	<i>valuecol</i>	IN	The column number in <i>table</i> that contains the input field values. The default is 1.
integer	<i>rows</i>	IN	The list of rows in <i>table</i> from which to generate the input fields. The default is to use all rows.
integer	<i>checkedrows</i>	IN	The list of rows specifying which <i>rows</i> of <i>table</i> to check. The default is not to check fields.

Return Codes

Table 144. DTW_TB_INPUT_CHECKBOX Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1004	A parameter passed on a function call, required to be a Net.Data macro table variable, was of a different variable type.

Table 144. DTW_TB_INPUT_CHECKBOX Return Codes (continued)

Return Code	Explanation
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1007	A parameter contains a value which is not valid.
1008	A parameter is outside of table bounds.

Examples

Example 1: Generates HTML for three check box input tags

```
@DTW_TB_INPUT_CHECKBOX(Mytable,"3","4","", "2 3 4", "1 3 4")
```

Results:

```
<input type="checkbox" name="link2text" value="1" />image2text<br />
<input type="checkbox" name="link3text" value="1" checked />image3text<br />
<input type="checkbox" name="link4text" value="1" checked />image4text<br />
```

DTW_TB_INPUT_RADIO

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Generates HTML radio button input tags from a Net.Data table.

Format

@DTW_TB_INPUT_RADIO(table, prompt, namecol, valuecol, rows, checkedrows)

@DTW_TB_INPUT_RADIO(table, prompt, namecol, valuecol, rows)

@DTW_TB_INPUT_RADIO(table, prompt, namecol, valuecol)

Parameters

Table 145. DTW_TB_INPUT_RADIO Parameters

Data Type	Parameter	Use	Description
table	<i>table</i>	IN	The macro table variable to display as radio button input tags.
string	<i>prompt</i>	IN	The column number in <i>table</i> or a string containing the text to display next to the radio button. Required parameter, but can contain a null ("") value. When <i>prompt</i> is null, uses the value of <i>valuecol</i> .
string	<i>namecol</i>	IN	The column number in <i>table</i> or a string containing the input field names.
integer	<i>valuecol</i>	IN	The column number in <i>table</i> that contains the input field values.
string	<i>rows</i>	IN	The list of rows in <i>table</i> from which to generate the input fields. The default is to use all rows.
integer	<i>checkedrows</i>	IN	A row number in <i>table</i> to display the corresponding radio button as checked. Only one value is allowed.

Return Codes

Table 146. DTW_TB_INPUT_RADIO Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1004	A parameter passed on a function call, required to be a Net.Data macro table variable, was of a different variable type.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.

Table 146. DTW_TB_INPUT_RADIO Return Codes (continued)

Return Code	Explanation
1007	A parameter contains a value which is not valid.
1008	A parameter is outside of table bounds.

Examples

Example 1: Generates HTML for three radio button input tags

```
@DTW_TB_INPUT_RADIO(Mytable,"3","Radio4","4","2 3 4","4")
```

Results:

```
<input type="radio" name="radio4" value="link2text" />image2text<br />
<input type="radio" name="radio4" value="link3text" />image3text<br />
<input type="radio" name="radio4" value="link4text" checked />image4text<br />
```

DTW_TB_INPUT_TEXT

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Generates HTML <input /> tags for specified rows in a Net.Data table.

Format

@DTW_TB_INPUT_TEXT(table, prompt, namecol, valuecol, size, maxlen, rows)

@DTW_TB_INPUT_TEXT(table, prompt, namecol, valuecol, size, maxlen)

@DTW_TB_INPUT_TEXT(table, prompt, namecol, valuecol, size)

@DTW_TB_INPUT_TEXT(table, prompt, namecol, valuecol)

@DTW_TB_INPUT_TEXT(table, prompt, namecol)

Parameters

Table 147. DTW_TB_INPUT_TEXT Parameters

Data Type	Parameter	Use	Description
table	<i>table</i>	IN	The macro table variable to display as text input tags.
string	<i>prompt</i>	IN	The column number in <i>table</i> or a string containing the text to display next to the input field. If <i>prompt</i> is null, no text is displayed.
string	<i>namecol</i>	IN	The column number in <i>table</i> that contains the input field names.
integer	<i>valuecol</i>	IN	The column number in <i>table</i> that contains the default input field values, which is specified for the VALUE attribute on the INPUT tag. The default is to not generate the VALUE attribute value.
integer	<i>size</i>	IN	The number of characters of the input field, which is specified for the SIZE attribute on the INPUT tag. The default is the length of the longest default input value, or 10 if no default input exists.
integer	<i>maxlen</i>	IN	The maximum length of an input string, which is specified for the MAXLENGTH attribute of the INPUT tag. The default is not to generate the MAXLENGTH attribute value.
integer	<i>rows</i>	IN	The list of rows in <i>table</i> from which to generate the input fields. The default is to use all rows.

Return Codes

Table 148. DTW_TB_INPUT_TEXT Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.

Table 148. DTW_TB_INPUT_TEXT Return Codes (continued)

Return Code	Explanation
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1004	A parameter passed on a function call, required to be a Net.Data macro table variable, was of a different variable type.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1007	A parameter contains a value which is not valid.
1008	A parameter is outside of table bounds.

Examples

Example 1: Returns three HTML <input /> tags

```
@DTW_TB_INPUT_TEXT(Mytable,"3","3","4","35","40","1 2 3")
```

Results:

```
<p>image1text
<input type="text" name="image1text" value="link1text" size="35" maxlength="40" /></p>
<p>image2text
<input type="text" name="image2text" value="link2text" size="35" maxlength="40" /></p>
<p>image3text
<input type="text" name="image3text" value="link3text" size="35" maxlength="40" /></p>
```

DTW_TB_INSERTCOL

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X		X	X	X		X	X

Purpose

Inserts one or more columns into a Net.Data table.

Format

@DTW_TB_INSERTCOL(table, after_col, cols)

Parameters

Table 149. DTW_TB_INSERTCOL Parameters

Data Type	Parameter	Use	Description
table	<i>table</i>	INOUT	The macro table variable into which columns are to be inserted.
integer	<i>after_col</i>	IN	The column number of the column after which the new columns are to be inserted. To insert columns at the beginning of the table, specify 0.
integer	<i>cols</i>	IN	The number of columns to insert into <i>table</i> .

Return Codes

Table 150. DTW_TB_INSERTCOL Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1004	A parameter passed on a function call, required to be a Net.Data macro table variable, was of a different variable type.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1007	A parameter contains a value which is not valid.
1008	A parameter is outside of table bounds.

Examples

Example 1: Inserts five columns at the end of a table

```
%DEFINE myTable = %TABLE  
  
@DTW_TB_INSERTCOL(myTable, @DTW_TB_rCOLS(myTable), "5")
```

Example 2: Inserts a column at the beginning of a table

```
%DEFINE myTable = %TABLE  
  
@DTW_TB_INSERTCOL(myTable, "0", "1")
```


DTW_TB_INSERTROW

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X		X	X	X		X	X

Purpose

Inserts one or more rows into a Net.Data table.

Format

@DTW_TB_INSERTROW(table, after_row, rows)

Parameters

Table 151. DTW_TB_INSERTROW Parameters

Data Type	Parameter	Use	Description
table	<i>table</i>	INOUT	The macro table variable into which rows are to be inserted.
integer	<i>after_row</i>	IN	The number of the row after which new rows are inserted. To insert rows at the beginning of the table, specify 0.
integer	<i>rows</i>	IN	The number of rows to insert into <i>table</i> .

Return Codes

Table 152. DTW_TB_INSERTROW Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1004	A parameter passed on a function call, required to be a Net.Data macro table variable, was of a different variable type.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1007	A parameter contains a value which is not valid.
1008	A parameter is outside of table bounds.

Usage Notes

Before calling DTW_TB_INSERTROW(), set the number of columns in the table. You can set the number of columns with the DTW_TB_SETCOLS() or DTW_TB_INSERTCOL() functions, or by passing the table to a language environment to be set.

Examples

Example 1: Inserts a row after row five of a table

```
%DEFINE myTable = %TABLE
```

```
@DTW_TB_INSERTROW(myTable, "5", "1")
```

Example 2: Inserts three rows at the start of a table

```
%DEFINE myTable = %TABLE  
@DTW_TB_INSERTROW(myTable, "0", "3")
```

DTW_TB_LIST

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Generates an HTML list from a Net.Data table.

Format

@DTW_TB_LIST(table, listtype, listitem, itemstyle, link_u, image_u)

@DTW_TB_LIST(table, listtype, listitem, itemstyle, link_u)

@DTW_TB_LIST(table, listtype, listitem, itemstyle)

@DTW_TB_LIST(table, listtype, listitem)

@DTW_TB_LIST(table, listtype)

Parameters

Table 153. DTW_TB_LIST Parameters

Data Type	Parameter	Use	Description
table	<i>table</i>	IN	A symbol specifying the macro table variable to display as an HTML list.
string	<i>listtype</i>	IN	The type of list to generate. Acceptable values include: DIR MENU OL UL
integer	<i>listitem</i>	IN	The column number in <i>table</i> containing the list values (the text to go after the tag). The default is to use the first column.
string	<i>itemstyle</i>	IN	A variable or literal string containing a list of HTML elements for the term name values. The default is to use no style tags.
integer	<i>link_u</i>	IN	The column number in <i>table</i> that contains the URLs for the HTML links. If this value is not specified, no HTML links are generated.
integer	<i>image_u</i>	IN	The column number in <i>table</i> that contains the URLs for the inline images. If this value is not specified, no inline images are generated.

Return Codes

Table 154. DTW_TB_LIST Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.

Table 154. DTW_TB_LIST Return Codes (continued)

Return Code	Explanation
1003	An incorrect number of parameters were passed on a function call.
1004	A parameter passed on a function call, required to be a Net.Data macro table variable, was of a different variable type.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1007	A parameter contains a value which is not valid.
1008	A parameter is outside of table bounds.

Examples

Example 1: Generates HTML tags for an ordered list

```
@DTW_TB_LIST(Mytable,"OL","4","TT U","2","1")
```

Results:

```
<tt><u>
<ol>
<li><a href="http://www.mycompany.com/link1.html">
link1text</a></li>
<li><a href="http://www.mycompany.com/link2.html">
link2text</a></li>
<li><a href="http://www.mycompany.com/link3.html">
<
IMG SRC="http://www.mycompany.com/images/image3.gif"
ALT="">link3text</a></li>
<li><a href="http://www.mycompany.com/link4.html">
link4txt</a></li>
</ol>
</u></tt>
```

DTW_TB_QUERYCOLNONJ

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X		X	X	X		X	X

Purpose

Returns the column number associated with a column heading of a Net.Data table.

Format

@DTW_TB_QUERYCOLNONJ(table, name, col)

@DTW_TB_rQUERYCOLNONJ(table, name)

Parameters

Table 155. DTW_TB_QUERYCOLNONJ Parameters

Data Type	Parameter	Use	Description
table	<i>table</i>	IN	The macro table variable from which a column number is to be returned.
string	<i>name</i>	IN	The name of the column heading for which the column number is returned. If the column heading does not exist in the table, 0 is returned.
integer	<i>col</i>	OUT	A variable that contains the column number of the column whose name is specified in <i>name</i> .

Return Codes

Table 156. DTW_TB_QUERYCOLNONJ Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1004	A parameter passed on a function call, required to be a Net.Data macro table variable, was of a different variable type.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.

Usage Notes

1. Before calling DTW_TB_QUERYCOLNONJ(), set the number of columns in the table. You can set the number of columns with the DTW_TB_SETCOLS() or DTW_TB_INSERTCOL() functions, or by passing the table to a language environment to be set.
2. If the column heading does not exist in the table, 0 is returned.

Examples

Example 1: Retrieves the column number for the column whose name is SERIAL_NUMBER

```
%DEFINE myTable = %TABLE  
%DEFINE col = ""
```

```
@DTW_TB_QUERYCOLNONJ(myTable, "SERIAL_NUMBER", col)
```

Example 2: Retrves the column number for the column whose name is SERIAL_NUMBER

```
%DEFINE myTable = %TABLE
```

```
<p>The "SERIAL_NUMBER" column is column number @DTW_TB_rQUERYCOLNONJ(myTable, "SERIAL_NUMBER")</p>
```

DTW_TB_ROWS

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Returns the number of rows in a Net.Data table.

Format

@DTW_TB_ROWS(table, rows)

@DTW_TB_rROWS(table)

Parameters

Table 157. DTW_TB_ROWS Parameters

Data Type	Parameter	Use	Description
table	<i>table</i>	IN	The macro table variable for which the current number of rows is returned.
integer	<i>rows</i>	OUT	A variable that contains the current number of rows in <i>table</i> .

Return Codes

Table 158. DTW_TB_ROWS Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1004	A parameter passed on a function call, required to be a Net.Data macro table variable, was of a different variable type.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.

Examples

Example 1: Retrieves the current number of rows in the table and assigns the value to *rows*

```
%DEFINE myTable = %TABLE
%DEFINE rows = ""
...
@FillTable(myTable)
...
@DTW_TB_ROWS(myTable, rows)
```

DTW_TB_SELECT

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Generates an HTML selection list from a Net.Data table.

Format

@DTW_TB_SELECT(table, name, optioncol, size, multiple, rows, selectedrows, valuecol)

@DTW_TB_SELECT(table, name, optioncol, size, multiple, rows, selectedrows)

@DTW_TB_SELECT(table, name, optioncol, size, multiple, rows)

@DTW_TB_SELECT(table, name, optioncol, size, multiple)

@DTW_TB_SELECT(table, name, optioncol, size)

@DTW_TB_SELECT(table, name, optioncol)

@DTW_TB_SELECT(table, name)

Parameters

Table 159. DTW_TB_SELECT Parameters

Data Type	Parameter	Use	Description
table	<i>table</i>	IN	The macro table variable to display as a SELECT field.
string	<i>name</i>	IN	The value of the NAME attribute of the SELECT field.
integer	<i>optioncol</i>	IN	The column number in <i>table</i> with values to use in the OPTION tags of the SELECT field. The default is to use the first column.
integer	<i>size</i>	IN	The number of rows in <i>table</i> to use for OPTION tags in the SELECT field. The default is to use all the rows.
string	<i>multiple</i>	IN	Specifies whether multiple selections are allowed. The default is N, which does not allow multiple selections.
string	<i>rows</i>	IN	The row numbers from <i>table</i> to use in the SELECT field. The default is to use all the rows.
string	<i>selectedrows</i>	IN	The list of rows from <i>table</i> whose OPTION tags are checked. To specify more than one row, you must have the <i>multiple</i> parameter set to Y. The default is to select the first item.
string	<i>valuecol</i>	IN	The column number in <i>table</i> to use for the VALUE attribute of the OPTION tags. The default value is 1. This parameter is optional.

Return Codes

Table 160. DTW_TB_SELECT Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1004	A parameter passed on a function call, required to be a Net.Data macro table variable, was of a different variable type.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1007	A parameter contains a value which is not valid.
1008	A parameter is outside of table bounds.

Examples

Example 1: Generates an HTML SELECT menu with multiple selections

```
@DTW_TB_SELECT(Mytable,"URL6","4","","y","1 2 4","1 4")
```

Results:

```
<select name="url6" size="3" multiple>
<option selected>image1text
<option>image2text
<option selected>image4text
</select>
```

Example 2: Uses the *valuecol* parameter to generate an HTML SELECT menu that uses a column number from which to obtain the values.

```
@DTW_TB_SELECT(Mytable,"URL6","4","","y","1 2 4","1 4", "2")
```

Results:

```
<select name="url6" size="3" multiple>
<option value="text_string1" selected>image1text</option>
<option value="text_string2">image2text</option>
<option value="text_string4" selected>image4text</option>
</select>
```

DTW_TB_SETCOLS

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X		X	X	X		X	X

Purpose

Sets the number of columns in a Net.Data table.

Format

@DTW_TB_SETCOLS(table, cols)

Parameters

Table 161. DTW_TB_SETCOLS Parameters

Data Type	Parameter	Use	Description
table	<i>table</i>	INOUT	The macro table variable for which the number of columns is set.
integer	<i>cols</i>	IN	The initial number of columns to allocate in <i>table</i> .

Return Codes

Table 162. DTW_TB_SETCOLS Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1004	A parameter passed on a function call, required to be a Net.Data macro table variable, was of a different variable type.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1007	A parameter contains a value which is not valid.

Usage Notes

1. The DTW_TB_SETCOLS() function can only be used once for a table. Afterwards, use the DTW_TB_DELETECOL() or DTW_TB_INSERTCOL() functions to change the number of columns in the table.
2. Specify the column headings by using the DTW_TB_SETN() function.

Examples

Example 1: Allocates three columns for the table and assigns the names to the columns

```
%DEFINE myTable = %TABLE
```

```
@DTW_TB_SETCOLS(myTable, "3")  
@DTW_TB_SETN(myTable, "Name", "1")  
@DTW_TB_SETN(myTable, "Address", "2")  
@DTW_TB_SETN(myTable, "Phone", "3")
```

DTW_TB_SETN

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X		X	X	X		X	X

Purpose

Assigns a name to a column heading in a Net.Data.

Format

@DTW_TB_SETN(table, name, col)

Parameters

Table 163. DTW_TB_SETN Parameters

Data Type	Parameter	Use	Description
table	<i>table</i>	INOUT	The macro table variable in which a column name will be set.
string	<i>name</i>	IN	A character string that is assigned to the column heading of the column specified in <i>col</i> .
integer	<i>col</i>	IN	The column number of the column whose heading is being set.

Return Codes

Table 164. DTW_TB_SETN Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1004	A parameter passed on a function call, required to be a Net.Data macro table variable, was of a different variable type.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1007	A parameter contains a value which is not valid.
1008	A parameter is outside of table bounds.

Usage Notes

1. Before calling DTW_TB_SETN(), set the number of columns in the table. You can set the number of columns with the DTW_TB_SETCOLS() or DTW_TB_INSERTCOL() functions, or by passing the table to a language environment to be set.
2. To delete a column heading, assign the column heading value to NULL.

Examples

Example 1: Assigns a name to column headings 1 through 3

```
%DEFINE myTable = %TABLE

@DTW_TB_SETCOLS(myTable, "3")
@DTW_TB_SETN(myTable, "Name", "1")
@DTW_TB_SETN(myTable, "Address", "2")
@DTW_TB_SETN(myTable, "Phone", "3")
```

Example 2: Delete the column heading for column 2. This is done by passing a variable on the function call which has not been defined. By default, this variable will have a value of NULL

```
%DEFINE myTable = %TABLE

@DTW_TB_SETN(myTable, nullVar, "2")
```

DTW_TB_SETV

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X		X	X	X		X	X

Purpose

Assigns a value to a particular row and column in a Net.Data table.

Format

@DTW_TB_SETV(table, value, row, col)

Parameters

Table 165. DTW_TB_SETV Parameters

Data Type	Parameter	Use	Description
table	<i>table</i>	INOUT	The macro table variable in which a table value will be set.
string	<i>value</i>	IN	A character string that is assigned to the table value of the row and column specified in <i>row</i> and <i>col</i> .
integer	<i>row</i>	IN	The row number of the value to be set.
integer	<i>col</i>	IN	The column number of the value to be set.

Return Codes

Table 166. DTW_TB_SETV Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1004	A parameter passed on a function call, required to be a Net.Data macro table variable, was of a different variable type.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1007	A parameter contains a value which is not valid.
1008	A parameter is outside of table bounds.

Usage Notes

1. Before calling DTW_TB_SETV(), set the number of columns in the table. You can set the number of columns with the DTW_TB_SETCOLS() or DTW_TB_INSERTCOL() functions, or by passing the table to a language environment to be set.
2. To delete a table value, assign the value to NULL.

Examples

Example 1: Assigns a value to row 3 column 3

```
%DEFINE myTable = %TABLE
```

```
@DTW_TB_SETV(myTable, "value3.3", "3", "3")
```

Example 2: Delete the table value at row 4, column 2. This is done by passing a variable on the function call which has not been defined. By default, this variable will have a value of NULL.

```
%DEFINE myTable = %TABLE
```

```
@DTW_TB_SETV(myTable, nullVar, "4", "2")
```

DTW_TB_TABLE

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Generates an HTML table from a Net.Data table.

Format

@DTW_TB_TABLE(table, options, collist, cellstyle, link_u, image_u, url_text, url_style)

@DTW_TB_TABLE(table, options, collist, cellstyle, link_u, image_u, url_text)

@DTW_TB_TABLE(table, options, collist, cellstyle, link_u, image_u)

@DTW_TB_TABLE(table, options, collist, cellstyle, link_u)

@DTW_TB_TABLE(table, options, collist, cellstyle)

@DTW_TB_TABLE(table, options, collist)

@DTW_TB_TABLE(table, options)

@DTW_TB_TABLE(table)

Parameters

Table 167. DTW_TB_TABLE Parameters

Data Type	Parameter	Use	Description
table	<i>table</i>	IN	A macro table variable to display as an HTML table.
string	<i>options</i>	IN	The table attributes inside the TABLE tag. The default is to use no attributes. Valid values include: <ul style="list-style-type: none">• BORDER• CELLSPACING• WIDTH
string	<i>collist</i>	IN	The column numbers in <i>table</i> to use in the HTML table. The default is to use all the columns.
string	<i>cellstyle</i>	IN	A list of HTML style elements, such as B and I, to go around text in each TD tag. The default is not to use style tags.
integer	<i>link_u</i>	IN	The column number in <i>table</i> containing URLs used to create HTML links. You must specify the column in <i>collist</i> also. The default is not to generate HTML links.
integer	<i>image_u</i>	IN	The column number in <i>table</i> containing URLs used to create inline images. You must specify the column in <i>collist</i> also. The default is not to generate image tags.
integer	<i>url_text</i>	IN	The column number in <i>table</i> containing text to display for HTML links or inline images. The default is to use the URL itself.
string	<i>url_style</i>	IN	A list of HTML style elements for the text specified in <i>url_text</i> . The default is not to generate style tags.

Return Codes

Table 168. DTW_TB_TABLE Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1004	A parameter passed on a function call, required to be a Net.Data macro table variable, was of a different variable type.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1007	A parameter contains a value which is not valid.
1008	A parameter is outside of table bounds.

Examples

Example 1: Generates HTML tags for a table with a border and using B (bold) and I (italics) tags

```
@DTW_TB_TABLE(Mytable,"BORDER","4 2 1","i","2","1","4","b")
```

Results:

```
<table border>
<tr>
<th>TITLE</th>
<th>LINKURL</th>
<th>IMAGEURL</th>
<tr>
<td><i>link1text</i></td>
<td><a href="http://www.mycompany.com/link1.html"><b>link1text</b></a></td>
<td><b>link1text</b></td>
</tr><tr>
<td><i>link2text</i></td>
<td><a href="http://www.mycompany.com/link2.html"><b>link2text</b></a></td>
<td><b>link2text</b></td>
</tr><tr>
<td><i>link3text</i></td>
<td><a href="http://www.mycompany.com/link3.html"><b>link3text</b></a></td>
<td><b>link3text</b></td>
</tr></table>
```


DTW_TB_TEXTAREA

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Generates an HTML text area from a Net.Data table.

Format

@DTW_TB_TEXTAREA(table, name, numrows, numcols, valuecol, rows)

@DTW_TB_TEXTAREA(table, name, numrows, numcols, valuecol)

@DTW_TB_TEXTAREA(table, name, numrows, numcols)

@DTW_TB_TEXTAREA(table, name, numrows)

@DTW_TB_TEXTAREA(table, name)

Parameters

Table 169. DTW_TB_TEXTAREA Parameters

Data Type	Parameter	Use	Description
table	<i>table</i>	IN	A macro table variable to show as a TEXTAREA tag.
string	<i>name</i>	IN	The name of the text area.
integer	<i>numrows</i>	IN	The height of the text area, specified in rows. The default is the number of rows in <i>table</i> .
integer	<i>numcols</i>	IN	The width of the text area, specified in columns. The default is the length of the longest row in <i>table</i> .
integer	<i>valuecol</i>	IN	The column number in <i>table</i> whose values are shown in the text area. The default is the first column.
string	<i>rows</i>	IN	A list of rows in <i>table</i> used to generate the TEXTAREA tag. The default is to use all rows.

Return Codes

Table 170. DTW_TB_TEXTAREA Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1004	A parameter passed on a function call, required to be a Net.Data macro table variable, was of a different variable type.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1007	A parameter contains a value which is not valid.
1008	A parameter is outside of table bounds.

Examples

Example 1: Generates HTML TEXTAREA tags and specifies which rows to include
`@DTW_TB_TEXTAREA(Mytable,"textarea5","3","70","4","1 3 4")`

Results:

```
<textarea name="textarea5" rows="3" cols="70">
link1text
link3text
link4text
</textarea>
```

Flat File Interface Functions

The flat file interface (FFI) enables you to open, read, and manipulate data from flat file sources (text files), as well as store data in flat files. The following flat file interface built-in functions are available:

- “DTWF_APPEND” on page 250
- “DTWF_CLOSE” on page 253
- “DTWF_COPY” on page 254
- “DTWF_DELETE” on page 255
- “DTWF_EXISTS” on page 257
- “DTWF_OPEN” on page 261
- “DTWF_READ” on page 263
- “DTWF_READFILE” on page 266
- “DTWF_REMOVE” on page 268
- “DTWF_SEARCH” on page 270
- “DTWF_UPDATE” on page 273
- “DTWF_WRITE” on page 276
- “DTWF_WRITEFILE” on page 279

The following sections discuss how to use the FFI built-in functions and access flat file sources:

- “Access to Flat File Data Sources”
- “Flat File Interface Delimiters” on page 248
- “Locking Files” on page 249

Access to Flat File Data Sources

You use the FFI_PATH path configuration statement in the Net.Data initialization file to list the directories and sub-directories that are allowed to be specified when using the FFI functions and to provide security for those files not in directories included in the path statement. The Net.Data initialization file is shipped without FFI_PATH. See *Net.Data Administration and Programming Guide* to learn how to configure the path.

The FFI_PATH uses the following syntax:

```
FFI_PATH /path1;/path2;/path3...
```

When you call the FFI language environment in a macro function, you specify the path to the flat file that the FFI function is working with, using the *filename* parameter of the FFI function. For example:

```
%DEFINE myfile = "/macros/myfile.txt" @DTWF_READ(myfile, ...)
```

The following sections discuss:

- “How Net.Data Determines the Flat File Location”
- “Flat File Configuration Rules” on page 248
- “Security Recommendations” on page 248
- “Authorization Requirement” on page 248

How Net.Data Determines the Flat File Location

Net.Data uses the information in the *filename* parameter for FFI functions to search the FFI_PATH statement in the Net.Data initialization file and determine whether to use a specified directory or the current directory.

When a file name is specified on an FFI function, Net.Data attempts to locate the file by searching each of the paths listed in FFI_PATH, starting from the first path that is specified. Net.Data uses the first copy that it finds. If the file is not found, then Net.Data attempts to find the file in the current working directory of the process or thread in which Net.Data is running.

Example: Net.Data uses the FFI_PATH configuration statement to locate a file

The FFI_PATH contains the following directories:

```
FFI_PATH /macros;/macros/org1;/macros/org2
```

And, the file is located in both the current directory and /macros/org1. If the function call is:

```
DTWF_READ("myfile.txt")
```

Net.Data will use /macros/org1/myfile.txt.

If the DTWF_READ function is being used to read an existing file, and a file name of myfile.txt is specified, then Net.Data searches the directories /macros, /macros/org1 and /macros/org2 for the file, assuming that the FFI_PATH contains the list of paths specified above.

Determining the Current Directory:

The current directory for Net.Data depends on the configuration of your Web server:

- If you are using CGI, the current directory is the directory that Net.Data is running from.
- If you are using a Web server API, the current directory can vary. If the server's default request routing or resource mapping is changed, the current directory might be changed, also.

Recommendations for specifying flat file access:

Use the following recommendations to ensure that Net.Data can access flat file data sources.

- When using the DTWF_OPEN function to create flat files, ensure that you specify a directory path that is in FFI_PATH or that you know what the current directory is. If you do not specify a directory, Net.Data attempts to create the file in the current working directory.
- If you include directories in the *filename* parameter, specify the full path that matches one of the paths in FFI_PATH because Net.Data does not search sub-directories within directories specified in FFI_PATH.

- Use absolute paths for the *filename* parameter, especially if you are using a Web server API.

Flat File Configuration Rules

Use the following rules when adding or updating the FFI_PATH in the Net.Data initialization file:

- Path statements in FFI_PATH must contain valid printable characters. FFI does not allow paths that include a question mark (?) or double quotes ("").
- All directories and sub-directories that are used with the *filename* parameter in the macro must be specified in the FFI_PATH. Sub-directories of the paths listed in *filename* are not searched unless explicitly specified in FFI_PATH.
- Use absolute paths for the FFI_PATH statement.

Security Recommendations

You can specify which files FFI functions can access with the FFI_PATH statement in the Net.Data initialization file. FFI only searches the paths listed in the statement, so files in other directories are protected from unauthorized access.

For example, you can specify an FFI_PATH similar to the one below, designating directories for public or guest user IDs.

```
FFI_PATH      C:\public;E:\WWW;E:\guest;A:
```

The following list provides recommendations for making your flat files secure:

- Choose which directories are appropriate to use for flat file operations. These directories need to be added to the FFI_PATH to limit searching to those directories.
- Use care letting people perform DTWF_REMOVE or other export operations in the macro to prevent people from removing or altering files with extensions .dll and .cmd that you might have in the current directory.
- Take appropriate steps to safeguard the files on the system by using reasonable control over what macros are added to the system.
- Do not specify a path in FFI_PATH that lets anonymous FTP users write to the path. If you do, somebody can put a Net.Data macro on the system that allows actions that were not previously allowed.
- Do not add the path of the Net.Data initialization file to the FFI_PATH.

Authorization Requirement

Ensure that the user ID under which Net.Data executes has access rights to files used by the FFI built-in functions. See the section on specifying Web server access rights to Net.Data files in the configuration chapter of *Net.Data Administration and Programming Guide* for more information.

Flat File Interface Delimiters

In order to improve performance, you can keep the Net.Data tabular output from a series of SQL requests in a flat file. You can retrieve the flat file in subsequent requests, instead of re-issuing the SQL requests.

Net.Data flat files can be created from Net.Data tables and Net.Data tables can be built from flat files. In order to make the transformations between the tables and flat files, you must define the mapping between columns in a table and records in a flat file. A *delimiter* is a flag or separator that FFI uses when dividing the file into parts (such as columns of a row) according to the requested transform. Delimiters

provide a method for defining how portions of records in a flat file can be separated and mapped to columns in a table, and how columns in a table can be mapped to records in a flat file.

There are two types of delimiters:

New-line character (ASCIITEXT)

Use this transformation when your table is made up of one column. Net.Data maps each line in the corresponding flat file onto a single row in the table. In this case, the new-line character in the flat file is the only delimiter used.

New-line character and delimiter string (DELIMITED)

Use this transformation when your table is made up of multiple columns. When Net.Data writes row data to a line in a flat file, it places the delimiter string as a separator between the column entries. When Net.Data rebuilds a table from a flat file, it uses the delimiter string to determine how much of each line to place in a column of the table. In this case, the regular new-line character separates the lines in the flat file that correspond to rows in the table, and the delimiter string separates the items within a single line.

For read operations, the delimiter separates the contents of the file into rows and columns of a table. For write operations, the delimiter indicates the end of a value in a table row and column. Net.Data passes the delimiter to the FFI as a Net.Data macro string and does not include a null character at the end of the characters unless explicitly listed in the DELIMITER parameter.

To use the null character in the delimiter, specify the DELIMITER parameter as a slash and a zero in double quotes, “\0”, instead of an empty string by using two double quotes, “””. If you specify the ASCIITEXT transform, Net.Data uses the new-line character as the delimiter and ignores any requested delimiter.

Undesirable changes to a file can occur if you use a different delimiter for write operations than for read operations. Net.Data writes the file with the new delimiter.

The maximum length of a delimiter is 256 characters.

Locking Files

You can lock flat files using the DTWF_OPEN and DTWF_CLOSE functions. With these functions, Net.Data reserves a flat file so that no other applications can read or update the file.

To lock a file, use the DTWF_OPEN function. This function ensures the file is unavailable to other applications and prevents the file from changing between the time it is read and updated.

To free the file, use the DTWF_CLOSE function. This function releases the file so that other applications can read or update the file.

DTWF_APPEND

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Writes the contents of a Net.Data table to the end of a text file.

Format

@DTWF_APPEND(filename, transform, delimiter, table, retry, rows)

@DTWF_APPEND(filename, transform, delimiter, table, retry)

@DTWF_APPEND(filename, transform, delimiter, table)

Parameters

Table 171. DTWF_APPEND Parameters

Data Type	Parameter	Use	Description
string	<i>filename</i>	INOUT	The name of the file to which the variable's contents are being added. On successful completion of the call, this parameter returns the fully qualified file name.
string	<i>transform</i>	IN	The format of the file: <ul style="list-style-type: none">• ASCIITEXT - writes the table to the file with a new-line character between column values and ignores the <i>delimiter</i> parameter.• DELIMITED - writes the table to the file with the delimiter specified in the <i>delimiter</i> parameter. A new-line character in a file indicates the end of a row of a Net.Data macro table for ASCIITEXT and DELIMITED transforms.
string	<i>delimiter</i>	IN	A character string to indicate the ends of values. This parameter is case sensitive. Ignored if <i>transform</i> is ASCIITEXT.
table	<i>table</i>	IN	The table variable from which the records are read. For non-OS/400 users: The maximum length of a row in an FFI table is 16383 characters. This limit includes a null character for each column in the Net.Data macro table.
integer	<i>retry</i>	IN	The number of times to retry if the file cannot be appended to immediately. The default is not to retry.
integer	<i>rows</i>	IN	The maximum number of rows from <i>table</i> to append. The default is to append all the rows. Specifying 0 appends all rows.

Return Codes

Table 172. DTWF_APPEND Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1004	A parameter passed on a function call, required to be a Net.Data macro table variable, was of a different variable type.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
1007	A parameter contains a value which is not valid.
2000	A flat file interface built-in function could not find the specified file.
2003	A flat file interface built-in function could not read a row of data into a table variable because the number of bytes in the row exceeded the maximum supported number of bytes.
2004	A flat file interface built-in function was attempting to find a file, but encountered a path in the FFI_PATH configuration file variable that was longer than the maximum supported number of bytes, which is 4095.
2005	A call to a system function failed.
2006	A flat file interface built-in function could not access the specified file because it was in use by this or another process and could not be shared in the specified mode.

Usage Notes

The current contents of a file affect the results of using DTWF_APPEND, especially the contents of the last column of the last row. If a new-line character follows the last column value of the last row of the file, appended data is placed in a new row. Otherwise, appended data becomes part of the last row of the file. If the file to be appended does not exist, a file is created.

Examples

Example 1:

```
%DEFINE {  
    myFile = "c:/private/myfile"  
    myTable = %TABLE  
}%  
@DTWF_APPEND(myFile, "DELIMITED", " ;", myTable)
```

Example 2:

```
%DEFINE {  
    myFile = "c:/private/myfile"  
    myTable = %TABLE  
}%  
@DTWF_APPEND(myFile, "ASCITEXT", " ;", myTable)
```

Example 3:

```
%DEFINE {  
    myFile = "c:/private/myfile"  
    myTable = %TABLE  
}%  
@DTWF_APPEND(myFile, "ASCII TEXT", " ;", myTable, "0", "10")
```


DTWF_CLOSE

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Closes a file opened by DTWF_OPEN.

Format

@DTWF_CLOSE(filename, retry)

@DTWF_CLOSE(filename)

Parameters

Table 173. DTWF_CLOSE Parameters

Data Type	Parameter	Use	Description
string	<i>filename</i>	INOUT	The name of the file to close. On successful completion of the call, this parameter returns the fully qualified file name.
integer	<i>retry</i>	IN	The number of times to retry if the file cannot be closed immediately. The default is not to retry.

Return Codes

Table 174. DTWF_CLOSE Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1007	A parameter contains a value which is not valid.
2002	A flat file interface built-in function could not close the specified file because it was not opened by this macro invocation.
2004	A flat file interface built-in function was attempting to find a file, but encountered a path in the FFI_PATH configuration file variable that was longer than the maximum supported number of bytes, which is 4095.

Examples

Example 1:

```
@DTWF_CLOSE(myFile, "5")
```

DTWF_COPY

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
				X	X			

Purpose

Copies a file.

Format

@DTWF_COPY(fromFilename, toFilename)

Parameters

Table 175. DTWF_COPY Parameters

Data Type	Parameter	Use	Description
string	<i>fromFilename</i>	INOUT	The name of the file to copy.
string	<i>toFilename</i>	INOUT	The name of the file that will contain the data in the file specified by fromFilename. If the file exists, all data in the file will be removed prior to the copy operation.

Return Codes

Table 176. DTWF_COPY Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
1007	A parameter contains a value which is not valid.
2000	A flat file interface built-in function could not find the specified file.
2001	A flat file interface built-in function could not open the specified file because it was in use by this or another process, and could not be shared in the specified mode.
2004	A flat file interface built-in function was attempting to find a file, but encountered a path in the FFI_PATH configuration file variable that was longer than the maximum supported number of bytes, which is 4095.
2005	A call to a system function failed.
2006	A flat file interface built-in function could not access the specified file because it was in use by this or another process and could not be shared in the specified mode.

DTWF_DELETE

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Deletes lines from a text file.

Format

@DTWF_DELETE(filename, transform, delimiter, retry, rows, startline)

@DTWF_DELETE(filename, transform, delimiter, retry, rows)

@DTWF_DELETE(filename, transform, delimiter, retry)

@DTWF_DELETE(filename, transform, delimiter)

Parameters

Table 177. DTW_DELETE Parameters

Data Type	Parameter	Use	Description
string	<i>filename</i>	INOUT	The name of the file whose records are to be deleted. On successful completion of the call, this parameter returns the fully qualified file name.
string	<i>transform</i>	IN	The format of the file: <ul style="list-style-type: none">• ASCIITEXT - writes the table to the file with a new-line character between column values and ignores the <i>delimiter</i> parameter.• DELIMITED - writes the table to the file with the delimiter specified in the <i>delimiter</i> parameter. A new-line character in a file indicates the end of a row of a Net.Data macro table for ASCIITEXT and DELIMITED transforms.
string	<i>delimiter</i>	IN	A character string to indicate the ends of values. This parameter is case sensitive. Ignored if <i>transform</i> is ASCIITEXT.
integer	<i>retry</i>	IN	The number of times to retry if the records cannot be deleted immediately. The default is not to retry.
integer	<i>rows</i>	IN	The maximum number of rows to delete. The default is to delete all the rows. Specifying 0 deletes all rows.
integer	<i>startline</i>	INOUT	The line number from which to begin deleting. A value of 1 means to begin deleting at the first line. If this value is greater than the number of lines in the file, an error is returned and the value of this parameter is changed to the number of lines in the file. The default is 1.

Return Codes

Table 178. DTWF_DELETE Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
1007	A parameter contains a value which is not valid.
2000	A flat file interface built-in function could not find the specified file.
2003	A flat file interface built-in function could not read a row of data into a table variable because the number of bytes in the row exceeded the maximum supported number of bytes.
2004	A flat file interface built-in function was attempting to find a file, but encountered a path in the FFI_PATH configuration file variable that was longer than the maximum supported number of bytes, which is 4095.
2005	A call to a system function failed.
2006	A flat file interface built-in function could not access the specified file because it was in use by this or another process and could not be shared in the specified mode.

Examples

Example 1:

```
%DEFINE {  
  myFile = "c:/private/myfile"  
  myTable = %TABLE  
  myWait = "5000"  
  myRows = "2"  
%}  
@DTWF_DELETE(myFile, "Delimited", "|", myWait, myRows)
```

Example 2:

```
%DEFINE {  
  myFile = "c:/private/myfile"  
  myTable = %TABLE  
  myStart = "1"  
  myRows = "2"  
%}  
@DTWF_DELETE(myFile, "Asciitext", "|", "0", myRows, myStart)
```

DTWF_EXISTS

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
				X	X			

Purpose

Determines the existence of a file.

Format

@DTWF_EXISTS(filename, existenceFlag)

@DTWF_rEXISTS(filename)

Parameters

Table 179. DTWF_EXISTS Parameters

Data Type	Parameter	Use	Description
string	<i>filename</i>	INOUT	The name of the file searched for.
string	<i>existenceFlag</i>	OUT	A variable set to show one of the following: <ul style="list-style-type: none">• 1 - the file exists• 0 - the file does not exist

Return Codes

Table 180. DTWF_EXISTS Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
1007	A parameter contains a value which is not valid.
2000	A flat file interface built-in function could not find the specified file.
2004	A flat file interface built-in function was attempting to find a file, but encountered a path in the FFI_PATH configuration file variable that was longer than the maximum supported number of bytes, which is 4095.
2005	A call to a system function failed.

DTWF_INSERT

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Inserts lines into an existing text file.

Format

@DTWF_INSERT(filename, transform, delimiter, table, retry, rows, startline)

@DTWF_INSERT(filename, transform, delimiter, table, retry, rows)

@DTWF_INSERT(filename, transform, delimiter, table, retry)

@DTWF_INSERT(filename, transform, delimiter, table)

Parameters

Table 181. DTWF_INSERT Parameters

Data Type	Parameter	Use	Description
string	<i>filename</i>	INOUT	The name of the file to which records are inserted. On successful completion of the call, this parameter returns the fully qualified file name.
string	<i>transform</i>	IN	The format of the file: <ul style="list-style-type: none">• ASCIITEXT - writes the table to the file with a new-line character between column values and ignores the <i>delimiter</i> parameter.• DELIMITED - writes the table to the file with the delimiter specified in the <i>delimiter</i> parameter. A new-line character in a file indicates the end of a row of a Net.Data macro table for ASCIITEXT and DELIMITED transforms.
string	<i>delimiter</i>	IN	A character string to indicate the ends of values. This parameter is case sensitive. Ignored if <i>transform</i> is ASCIITEXT.
table	<i>table</i>	IN	The table variable from which lines are inserted into the file. For non-OS/400 users: The maximum length of a row in an FFI table is 16383 characters. This limit includes a null character for each column in the Net.Data macro table.
integer	<i>retry</i>	IN	The number of times to retry if the file cannot be written to immediately. The default is not to retry.
integer	<i>rows</i>	IN	The maximum number of rows to insert from <i>table</i> . The default is to insert all the rows. A value of 0 inserts all the rows.

Table 181. DTWF_INSERT Parameters (continued)

Data Type	Parameter	Use	Description
integer	<i>startline</i>	INOUT	The line number from which to begin inserting. If this value is greater than the number of lines in the file, an error is returned and the value of this parameter is changed to the number of lines in the file. Specifying 0 means to insert starting at the beginning of the file. The default is 0.

Return Codes

Table 182. DTWF_INSERT Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1004	A parameter passed on a function call, required to be a Net.Data macro table variable, was of a different variable type.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
1007	A parameter contains a value which is not valid.
2000	A flat file interface built-in function could not find the specified file.
2003	A flat file interface built-in function could not read a row of data into a table variable because the number of bytes in the row exceeded the maximum supported number of bytes.
2004	A flat file interface built-in function was attempting to find a file, but encountered a path in the FFI_PATH configuration file variable that was longer than the maximum supported number of bytes, which is 4095.
2005	A call to a system function failed.
2006	A flat file interface built-in function could not access the specified file because it was in use by this or another process and could not be shared in the specified mode.

Examples

Example 1:

```
%DEFINE {
  myFile = "c:/private/myfile"
  myTable = %TABLE
  myWait = "3000"
}%
@DTWF_INSERT(myFile, "Delimited", "|", myTable, myWait)
```

Example 2:

```
%DEFINE {  
    myFile = "c:/private/myfile"  
    myTable = %TABLE  
    myStart = "1"  
    myRows = "2"  
%}  
@DTWF_INSERT(myFile, "AsciiText", "|", myTable, "0", myRows, myStart)
```


DTWF_OPEN

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Opens a text file.

Format

@DTWF_OPEN(filename, mode, retry, createOptions)

@DTWF_OPEN(filename, mode, retry)

@DTWF_OPEN(filename, mode)

Parameters

Table 183. DTWF_OPEN Parameters

Data Type	Parameter	Use	Description
string	<i>filename</i>	INOUT	The name of the file to open. On successful completion of the call, this parameter returns the fully qualified file name.
string	<i>mode</i>	IN	The type of access requested: <ul style="list-style-type: none">• r - opens an existing file for reading.• w - creates a file for writing. (Destroys existing file of same name, if it exists.)• a - opens a file for appending. Net.Data creates the file if it is not found.• r+ - opens an existing file for reading and writing.• w+ - creates a file for reading and writing. (Destroys existing file of same name, if it exists.)• a+ - opens a file in append mode for reading or appending. Net.Data creates the file if it is not found.
integer	<i>retry</i>	IN	The number of times to retry if the file cannot be opened immediately. The default is not to retry.
string	<i>createOptions</i>	IN	Options to use when creating a file. If a file exists, the options specified are not used. Options are ignored by all platforms except the OS/400 platform. Currently, the following option is supported: CCSID=nnn, which specifies the coded character set ID (CCSID) to use when creating a new file. Nnn must be a valid CCSID from 1 to 65534.

Return Codes

Table 184. DTWF_OPEN Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.

Table 184. DTWF_OPEN Return Codes (continued)

Return Code	Explanation
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
1007	A parameter contains a value which is not valid.
2000	A flat file interface built-in function could not find the specified file.
2001	A flat file interface built-in function could not open the specified file because it was in use by this or another process, and could not be shared in the specified mode.
2006	A flat file interface built-in function could not access the specified file because it was in use by this or another process and could not be shared in the specified mode.

Usage Notes

1. When the file does not exist, an absolute path for the filename should be specified, and the directory where the file is to be created must match a directory specified in FFI_PATH. If an absolute path is not used, the file will be opened in the current working directory.
2. DTWF_OPEN keeps the file open, otherwise, the file is closed after each flat file operation.
3. Use DTWF_OPEN to reduce the number of times a file is open. If DTWF_OPEN is not used, the file is closed after each flat file operation. The file is left open until it is closed using DTWF_CLOSE or macro processing ends.

Examples

Example:

```
%DEFINE {
  myFile = "c:/private/myfile"
  myMode = "r+"
}%
@DTWF_OPEN(myFile, myMode, "1000")
```

DTWF_READ

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Reads lines from a text file into a Net.Data table.

Format

@DTWF_READ(filename, transform, delimiter, table, retry, lines, startline, columns)

@DTWF_READ(filename, transform, delimiter, table, retry, lines, startline)

@DTWF_READ(filename, transform, delimiter, table, retry, lines)

@DTWF_READ(filename, transform, delimiter, table, retry)

@DTWF_READ(filename, transform, delimiter, table)

Parameters

Table 185. DTWF_READ Parameters

Data Type	Parameter	Use	Description
string	<i>filename</i>	INOUT	The name of the file whose records are read into a table variable. On successful completion of the call, this parameter returns the fully qualified file name.
string	<i>transform</i>	IN	The format of the file: <ul style="list-style-type: none">• ASCIITEXT - writes the table to the file with a new-line character between column values and ignores the <i>delimiter</i> parameter.• DELIMITED - writes the table to the file with the delimiter specified in the <i>delimiter</i> parameter. A new-line character in a file indicates the end of a row of a Net.Data macro table for ASCIITEXT and DELIMITED transforms.
string	<i>delimiter</i>	IN	A character string to indicate the ends of values. This parameter is case sensitive. Ignored if <i>transform</i> is ASCIITEXT.
table	<i>table</i>	OUT	The table variable into which the file records are read. For non-OS/400 users: The maximum length of a row in an FFI table is 16383 characters. This limit includes a null character for each column in the Net.Data macro table.
integer	<i>retry</i>	IN	The number of times to retry if the file cannot be read immediately. The default is not to retry.

Table 185. DTWF_READ Parameters (continued)

Data Type	Parameter	Use	Description
integer	<i>lines</i>	INOUT	The number of lines in the file to read into the table. A value of 0 means to read to the end of the file or until the table is full; this is the default. Upon successful completion of this function call, the number of rows in the resulting table is returned.
integer	<i>startline</i>	IN	The line in the file from which to start reading. The default is to start reading at the first line.
integer	<i>columns</i>	OUT	Returns the number of columns in the table.

Return Codes

Table 186. DTWF_READ Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1004	A parameter passed on a function call, required to be a Net.Data macro table variable, was of a different variable type.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
1007	A parameter contains a value which is not valid.
1010	Data was written to the table until it was full, and the remainder of the data was discarded.
2000	A flat file interface built-in function could not find the specified file.
2003	A flat file interface built-in function could not read a row of data into a table variable because the number of bytes in the row exceeded the maximum supported number of bytes.
2004	A flat file interface built-in function was attempting to find a file, but encountered a path in the FFI_PATH configuration file variable that was longer than the maximum supported number of bytes, which is 4095.
2005	A call to a system function failed.
2006	A flat file interface built-in function could not access the specified file because it was in use by this or another process and could not be shared in the specified mode.

Examples

Example 1:

```
%DEFINE {
    myFile = "c:/private/myfile"
    myTable = %TABLE
    myWait = "1000"
}%
@DTWF_READ(myFile, "DELIMITED", ";", myTable, myWait)
```

Example 2:

```
%DEFINE {
    myFile = "c:/private/myfile"
    myTable = %TABLE
    myWait = "0"
    myRows = "0"
    myStartrow = "1"
    myColumns = ""
}%
@DTWF_READ(myFile, "DELIMITED", ";", myTable, myWait, myRows,
            myStartrow, myColumns)
```

Example 3:

```
%DEFINE {
    myFile = "c:/private/myfile"
    myTable = %TABLE
}%
@DTWF_READ(myFile, "ASCII TEXT", ";", myTable)
@DTW_TB_TABLE(myTable, "BORDER", "")
```

DTWF_READFILE

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Reads a file into a Net.Data variable.

Format

@DTWF_READFILE(filename,fileData)

Parameters

Table 187. DTWF_READFILE Parameters

Data Type	Parameter	Use	Description
string	<i>filename</i>	IN	The name of the file to read into the variable. On successful completion of the function call, the fully qualified file name is returned in this variable.
string	<i>fileData</i>	OUT	The variable that is assigned the contents of the file.

Return Codes

Table 188. DTWF_READFILE Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1004	A parameter passed on a function call, required to be a Net.Data macro table variable, was of a different variable type.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
1007	A parameter contains a value which is not valid.
2000	A flat file interface built-in function could not find the specified file.
2001	A flat file interface built-in function could not open the specified file because it was in use by this or another process, and could not be shared in the specified mode.
2004	A flat file interface built-in function was attempting to find a file, but encountered a path in the FFI_PATH configuration file variable that was longer than the maximum supported number of bytes, which is 4095.
2005	A call to a system function failed.

Table 188. DTWF_READFILE Return Codes (continued)

Return Code	Explanation
2006	A flat file interface built-in function could not access the specified file because it was in use by this or another process and could not be shared in the specified mode.

Examples

```
%define filename="/bios/${name}.txt"
%html(input) {
  <form method="get" action="report">
    <p>Name: <input name="name" /><br />
      <input type="submit" /></p>
  </form>
%}

%html(report) {
@DTWF_READFILE(filename, contents)
p><b>Bio:</b><br />
$(contents)</p>
%}
```

DTWF_REMOVE

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Deletes an entire file.

Format

@DTWF_REMOVE(filename, retry)

@DTWF_REMOVE(filename)

Parameters

Table 189. DTWF_REMOVE Parameters

Data Type	Parameter	Use	Description
string	<i>filename</i>	INOUT	The name of the file to delete. On successful completion of the call, this parameter returns the fully qualified file name.
integer	<i>retry</i>	IN	The number of times to retry if the file cannot be deleted immediately. The default is not to retry.

Return Codes

Table 190. DTWF_REMOVE Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
1007	A parameter contains a value which is not valid.
2000	A flat file interface built-in function could not find the specified file.
2006	A flat file interface built-in function could not access the specified file because it was in use by this or another process and could not be shared in the specified mode.

Examples

Example 1:

```
%DEFINE myFile = "c:/private/myfile"  
@DTWF_REMOVE(myFile)
```


Example 2:

```
%DEFINE {  
    myFile = "c:/private/myfile"  
    myWait = "2000"  
}%  
@DTWF_REMOVE(myFile, myWait)
```

DTWF_SEARCH

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Searches a text file for a string, returning the results into a Net.Data table.

Format

@DTWF_SEARCH(filename, transform, delimiter, table, searchFor, retry, linesToSearch, startline)

@DTWF_SEARCH(filename, transform, delimiter, table, searchFor, retry, linesToSearch)

@DTWF_SEARCH(filename, transform, delimiter, table, searchFor, retry)

@DTWF_SEARCH(filename, transform, delimiter, table, searchFor)

Parameters

Table 191. DTWF_SEARCH Parameters

Data Type	Parameter	Use	Description
string	<i>filename</i>	INOUT	The name of the file to search. On successful completion of the call, this parameter returns the fully qualified file name.
string	<i>transform</i>	IN	The format of the file: <ul style="list-style-type: none">• ASCIITEXT - writes the table to the file with a new-line character between column values and ignores the <i>delimiter</i> parameter.• DELIMITED - writes the table to the file with the delimiter specified in the <i>delimiter</i> parameter. A new-line character in a file indicates the end of a row of a Net.Data macro table for ASCIITEXT and DELIMITED transforms.
string	<i>delimiter</i>	IN	A character string to indicate the ends of values. This parameter is case sensitive. Ignored if <i>transform</i> is ASCIITEXT.
table	<i>table</i>	OUT	The table variable into which the search results are placed. Three columns are returned: <ul style="list-style-type: none">• The line in which the match was found• The field in which the match was found (for ASCIITEXT transform, this is always 1)• The value of the field that contained the search string For non-OS/400 users: The maximum length of a row in an FFI table is 16383 characters. This limit includes a null character for each column in the Net.Data macro table.

Table 191. DTWF_SEARCH Parameters (continued)

Data Type	Parameter	Use	Description
string	<i>searchFor</i>	IN	The string of characters to search for.
integer	<i>retry</i>	IN	The number of times to retry if the file cannot be searched immediately. The default is not to retry.
integer	<i>linesToSearch</i>	INOUT	The number of lines in the file to search. A value of 0 means all the lines in the file are searched or until the table is full; this is the default. Upon successful completion, the number of rows in the resulting table is returned by this parameter.
integer	<i>startline</i>	IN	The line in the file to start searching from. The default is 1, which begins the search at the first record.

Return Codes

Table 192. DTWF_SEARCH Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1004	A parameter passed on a function call, required to be a Net.Data macro table variable, was of a different variable type.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
1007	A parameter contains a value which is not valid.
1010	Data was written to the table until it was full, and the remainder of the data was discarded.
2000	A flat file interface built-in function could not find the specified file.
2003	A flat file interface built-in function could not read a row of data into a table variable because the number of bytes in the row exceeded the maximum supported number of bytes.
2004	A flat file interface built-in function was attempting to find a file, but encountered a path in the FFI_PATH configuration file variable that was longer than the maximum supported number of bytes, which is 4095.
2005	A call to a system function failed.
2006	A flat file interface built-in function could not access the specified file because it was in use by this or another process and could not be shared in the specified mode.

Usage Notes

1. The table that is returned for DTWF_SEARCH has three columns. The first two columns contain the row and the column number where the match is found; the last column contains the column value that contains the characters that are specified in the *SearchFor* parameter. For example, if the fourth row of the file contains matching characters in column three, the returned table has a row with the number 4 in the first column to indicate the row of the file that it came from; it has a number 3 in the second column to indicate which column of the file contains a match; and it has the complete column value in the third column.
2. The SearchFor parameter cannot include the contents of the *delimiter* parameter.

Examples

Example 1:

```
%DEFINE {  
  myFile = "c:/private/myfile"  
  myTable = %TABLE  
  myWait = "1000"  
  mySearch = "0123456789abcdef"  
@DTWF_SEARCH(myFile, "DELIMITED", ";",  
  myTable, mySearch, myWait)
```

Example 2:

```
%DEFINE {  
  myFile = "c:/private/myfile"  
  myTable = %TABLE  
  mySearch = "answer:"  
  myWait = "0"  
  myRows = "0"  
  myStartrow = "1"  
%}  
@DTWF_SEARCH(myFile, "DELIMITED", ";", myTable,  
  mySearch, myWait, myRows, myStartrow)
```

DTWF_UPDATE

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Update lines in a text file with data from a Net.Data table.

Format

@DTWF_UPDATE(filename, transform, delimiter, table, retry, rows, startline)

@DTWF_UPDATE(filename, transform, delimiter, table, retry, rows)

@DTWF_UPDATE(filename, transform, delimiter, table, retry)

@DTWF_UPDATE(filename, transform, delimiter, table)

Parameters

Table 193. DTWF_UPDATE Parameters

Data Type	Parameter	Use	Description
string	<i>filename</i>	INOUT	The name of the file whose records are updated from a table variable. On successful completion of the call, this parameter returns the fully qualified file name.
string	<i>transform</i>	IN	The format of the file: <ul style="list-style-type: none">• ASCIITEXT - writes the table to the file with a new-line character between column values and ignores the <i>delimiter</i> parameter.• DELIMITED - writes the table to the file with the delimiter specified in the <i>delimiter</i> parameter. A new-line character in a file indicates the end of a row of a Net.Data macro table for ASCIITEXT and DELIMITED transforms.
string	<i>delimiter</i>	IN	A character string to indicate the ends of values. This parameter is case sensitive. Ignored if <i>transform</i> is ASCIITEXT.
table	<i>table</i>	IN	The table variable from which the file records are updated. For non-OS/400 users: The maximum length of a row in an FFI table is 16383 characters. This limit includes a null character for each column in the Net.Data macro table.
integer	<i>retry</i>	IN	The number of times to retry if the file cannot be written to immediately. The default is not to retry.
integer	<i>rows</i>	IN	The number of rows in the table to use when updating the file. A value of 0 means to use all the rows when updating the file; this is the default. Note that only existing lines in the file are updated, no lines are added.

Table 193. DTWF_UPDATE Parameters (continued)

Data Type	Parameter	Use	Description
integer	<i>startline</i>	INOUT	The first file record to update. The default is 1, which means to start updating at the beginning of the file. If the value is greater than the number of lines in a file, the value is changed to indicate the number of the last line in the file and an error is returned.

Return Codes

Table 194. DTWF_UPDATE Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1004	A parameter passed on a function call, required to be a Net.Data macro table variable, was of a different variable type.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
1007	A parameter contains a value which is not valid.
2000	A flat file interface built-in function could not find the specified file.
2001	A flat file interface built-in function could not open the specified file because it was in use by this or another process, and could not be shared in the specified mode.
2003	A flat file interface built-in function could not read a row of data into a table variable because the number of bytes in the row exceeded the maximum supported number of bytes.
2004	A flat file interface built-in function was attempting to find a file, but encountered a path in the FFI_PATH configuration file variable that was longer than the maximum supported number of bytes, which is 4095.
2005	A call to a system function failed.
2006	A flat file interface built-in function could not access the specified file because it was in use by this or another process and could not be shared in the specified mode.

Usage Notes

If the file does not exist, an absolute path for the filename should be specified, and the directory where the file is to be created must match a directory specified in FFI_PATH. If an absolute path is not used, the file will be opened in the current working directory.

Examples

Example 1:

```
%DEFINE {  
    myFile = "c:/private/myfile"  
    myTable = %TABLE  
    myWait = "1500"  
    myRows = "2"  
%}  
@DTWF_UPDATE(myFile, "Delimited", "|", myTable, myWait, myRows)
```

Example 2:

```
%DEFINE {  
    myFile = "c:/private/myfile"  
    myTable = %TABLE  
    myStart = "1"  
    myRows = "2"  
%}  
@DTWF_UPDATE(myFile, "Asciitext", "|", myTable, "0", myRows, myStart)
```

DTWF_WRITE

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X	X	X	X	X	X	X	X	X

Purpose

Writes the contents of a Net.Data table to a text file.

Format

@DTWF_WRITE(filename, transform, delimiter, table, retry, rows, startline)

@DTWF_WRITE(filename, transform, delimiter, table, retry, rows)

@DTWF_WRITE(filename, transform, delimiter, table, retry)

@DTWF_WRITE(filename, transform, delimiter, table)

Parameters

Table 195. DTWF_WRITE Parameters

Data Type	Parameter	Use	Description
string	<i>filename</i>	INOUT	The name of the file the records of the table variable are written to. On successful completion of the call, this parameter returns the fully qualified file name.
string	<i>transform</i>	IN	The format of the file: <ul style="list-style-type: none">• ASCIITEXT - writes the table to the file with a new-line character between column values and ignores the <i>delimiter</i> parameter.• DELIMITED - writes the table to the file with the delimiter specified in the <i>delimiter</i> parameter. A new-line character in a file indicates the end of a row of a Net.Data macro table for ASCIITEXT and DELIMITED transforms.
string	<i>delimiter</i>	IN	A character string to indicate the ends of values. This parameter is case sensitive. Ignored if <i>transform</i> is ASCIITEXT.
table	<i>table</i>	IN	The table variable used to export rows to the file. For non-OS/400 users: The maximum length of a row in an FFI table is 16383 characters. This limit includes a null character for each column in the Net.Data macro table.
integer	<i>retry</i>	IN	The number of times to retry if the file cannot be written to immediately. The default is to not retry.
integer	<i>rows</i>	IN	The number of rows in table to write into the file. A value of 0 means that all rows in table are written into the file; this is the default.

Table 195. DTWF_WRITE Parameters (continued)

Data Type	Parameter	Use	Description
integer	<i>startline</i>	INOUT	The line number in the file from which to begin writing. A value of 1 means to start at the first line in the file; this is the default. If a value beyond the end of the file is specified, an error is returned and this parameter is set to the number of lines in the file.

Return Codes

Table 196. DTWF_WRITE Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1004	A parameter passed on a function call, required to be a Net.Data macro table variable, was of a different variable type.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
1007	A parameter contains a value which is not valid.
2000	A flat file interface built-in function could not find the specified file.
2003	A flat file interface built-in function could not read a row of data into a table variable because the number of bytes in the row exceeded the maximum supported number of bytes.
2004	A flat file interface built-in function was attempting to find a file, but encountered a path in the FFI_PATH configuration file variable that was longer than the maximum supported number of bytes, which is 4095.
2005	A call to a system function failed.
2006	A flat file interface built-in function could not access the specified file because it was in use by this or another process and could not be shared in the specified mode.

Usage Notes

- If the file does not exist, an absolute path for the filename should be specified, and the directory where the file is to be created must match a directory specified in FFI_PATH.
- If an absolute path is not used, the file will be opened in the current working directory.
- If a file has not been previously opened, DTWF_WRITE() will clear the file of all of its contents before writing the data from the passed-in table to the file.

Examples

Example 1:

```
%DEFINE {  
    myFile = "c:/private/myfile"  
    myTable = %TABLE  
}%  
@DTWF_WRITE(myFile, "DELIMITED", ";", myTable)
```

Example 2:

```
%DEFINE {  
    myFile = "c:/private/myfile"  
    myTable = %TABLE  
}%  
@DTWF_WRITE(myFile, "ASCIIITEXT", ";", myTable, "5000")
```

Example 3:

```
%DEFINE {  
    myFile = "c:/private/myfile"  
    myTable = %TABLE  
}%  
@DTWF_WRITE(myFile, "ASCIIITEXT", ";", myTable, "5000", "10", "50")
```

DTWF_WRITEFILE

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
				X	X			

Purpose

Writes a string to a file.

Format

@DTWF_WRITEFILE(filename, dataString, appendOptions)

@DTWF_WRITEFILE(filename, dataString)

Parameters

Table 197. DTWF_WRITEFILE Parameters

Data Type	Parameter	Use	Description
string	<i>filename</i>	INOUT	The name of the file that the data specified by <i>dataString</i> is written to. On successful completion of the call
string	<i>dataString</i>	IN	The variable that is assigned the contents of the file.
string	<i>appendOptions</i>	IN	The variable that is assigned the contents of the file.

Return Codes

Table 198. DTWF_WRITEFILE Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
1007	A parameter contains a value which is not valid.
2000	A flat file interface built-in function could not find the specified file.
2001	A flat file interface built-in function could not open the specified file because it was in use by this or another process, and could not be shared in the specified mode.
2004	A flat file interface built-in function was attempting to find a file, but encountered a path in the FFI_PATH configuration file variable that was longer than the maximum supported number of bytes, which is 4095.
2005	A call to a system function failed.

Table 198. DTWF_WRITEFILE Return Codes (continued)

Return Code	Explanation
2006	A flat file interface built-in function could not access the specified file because it was in use by this or another process and could not be shared in the specified mode.

Usage Notes

- If the file does not exist, specify an absolute path for the filename. The directory where the file is to be created must match a directory specified in the FFI_PATH. If an absolute path is not used, the file will be opened in the current working directory.
- If the specified file has been opened using DTWF_OPEN with an open mode of "w" and if the append option is set to "N," then DTWF_WRITEFILE will clear any data in the file.

Web Registry Functions

A Web registry is a file with a key maintained by Net.Data to allow you to add, retrieve, and delete entries easily. You can create multiple Net.Data Web registries on a single system. Each registry has a name and can contain multiple entries. Net.Data provides functions to maintain registries and the entries they contain.

- "DTWR_ADDENTRY" on page 281
- "DTWR_CLEARREG" on page 283
- "DTWR_CLOSEREG" on page 284
- "DTWR_CREATEREG" on page 285
- "DTWR_DELENTY" on page 287
- "DTWR_DELREG" on page 289
- "DTWR_LISTREG" on page 290
- "DTWR_LISTSUB" on page 292
- "DTWR_OPENREG" on page 294
- "DTWR_RTVENTRY" on page 295
- "DTWR_UPDATEENTRY" on page 297

Restrictions:

- Do not use asterisks (*) for the *registry*, *registryVariable*, and *registryData* parameters when using OS/2.
- Each parameter passed to a Web Registry function is limited to a maximum of 2048 characters.

DTWR_ADDENTRY

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X			X		X			X

Purpose

Adds an entry to a Web registry.

Format

@DTWR_ADDENTRY(registry, registryVariable, registryData, index)

@DTWR_ADDENTRY(registry, registryVariable, registryData)

Parameters

Table 199. DTWR_ADDENTRY Parameters

Data Type	Parameter	Use	Description
string	<i>registry</i>	IN	The name of the registry to which the entry is added.
string	<i>registryVariable</i>	IN	The value of the <i>registryVariable</i> string portion of the registry entry to add.
string	<i>registryData</i>	IN	The value of the <i>registryData</i> string portion of the registry entry to add.
string	<i>index</i>	IN	The value of the index portion of the <i>registryVariable</i> string in an indexed entry to add. This parameter is optional. If specified, an indexed entry is added to the specified registry.

Return Codes

Table 200. DTWR_ADDENTRY Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1007	A parameter contains a value which is not valid.
3003	A Web registry built-in function could not add an entry to the specified registry because the specified entry already exists.
3005	A Web registry built-in function could not use the specified registry because it cannot be found.
3006	A Web registry built-in function could not create the specified registry because a path in the registry name does not exist.
3007	A Web registry built-in function could not complete the specified operation because the requestor does not have the proper authority to the specified registry.

Examples

Example 1:

```
@DTWR_ADDENTRY("Myregistry", "Jones", "http://Advantis.com/~Jones/webproj")
```

Example 2:

```
@DTWR_ADDENTRY("URLLIST", "SMITH", "http://www.ibm.com/software/",  
"WORK_URL,")
```

DTWR_CLEARREG

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X			X		X			X

Purpose

Clears entries from a Web registry.

Format

@DTWR_CLEARREG(registry)

Parameters

Table 201. DTWR_CLEARREG Parameters

Data Type	Parameter	Use	Description
string	registry	IN	The name of the registry to clear.

Return Codes

Table 202. DTWR_CLEARREG Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1007	A parameter contains a value which is not valid.
3005	A Web registry built-in function could not use the specified registry because it cannot be found.
3006	A Web registry built-in function could not create the specified registry because a path in the registry name does not exist.
3007	A Web registry built-in function could not complete the specified operation because the requestor does not have the proper authority to the specified registry.

Examples

Example 1:

```
@DTWR_CLEARREG("Myregistry")
```

DTWR_CLOSEREG

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
					X			

Purpose

Closes a Web registry

Format

@DTWR_CLOSEREG(registry)

Parameters

Table 203. DTWR_CLOSEREG Parameters

Data Type	Parameter	Use	Description
string	registry	IN	The name of the registry to close. Restriction: Do not use special characters such as the asterisk (*) and the backslash (\) in Web registry names.

Return Codes

Table 204. DTWR_CLOSEREG Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1007	A parameter contains a value which is not valid.
3005	A Web registry built-in function could not use the specified registry because it cannot be found.

Examples

Example 1: Close a registry

```
@DTWR_CLOSEREG("/qsys.lib/mylib.lib/myreg.file")
```


DTWR_CREATEREG

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X			X		X			X

Purpose

Creates a new Web registry.

Format

@DTWR_CREATEREG(registry, security)

@DTWR_CREATEREG(registry)

Parameters

Table 205. DTWR_CREATEREG Parameters

Data Type	Parameter	Use	Description
string	<i>registry</i>	IN	The name of the registry to create. Restriction: Do not use special characters such as the asterisk (*) and the backslash (\) in Web registry names.
string	<i>security</i>	IN	The type of security with which to create <i>registry</i> . On UNIX operating systems, the default security is the same as the directory where the registry is created. Specify security for the three security groups: user, group, and public. R gives read permission, W gives write permission, and X give execute permission. For example, to give all three groups full authority, specify *RWX, *RWX, *RWX for this parameter. This parameter is optional.

Return Codes

Table 206. DTWR_CREATEREG Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1007	A parameter contains a value which is not valid.
3002	A Web registry built-in function could not delete the specified registry.
3006	A Web registry built-in function could not create the specified registry because a path in the registry name does not exist.

Table 206. DTWR_CREATEREG Return Codes (continued)

Return Code	Explanation
3007	A Web registry built-in function could not complete the specified operation because the requestor does not have the proper authority to the specified registry.
3008	A Web registry built-in function could not create the specified registry for unknown reasons.

Examples

Example 1:

```
@DTWR_CREATEREG("myRegistry")
```

Example 2:

```
@DTWR_CREATEREG("URLLIST", "*RWX, *RWX, *R")
```

DTWR_DELENTY

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X			X		X			X

Purpose

Deletes an entry from a Web registry.

Format

@DTWR_DELENTY(registry, registryVariable, index)

@DTWR_DELENTY(registry, registryVariable)

Parameters

Table 207. DTWR_DELENTY Parameters

Data Type	Parameter	Use	Description
string	<i>registry</i>	IN	The name of the registry from which the entry is removed.
string	<i>registryVariable</i>	IN	The value of the <i>registryVariable</i> string portion of the entry to remove.
string	<i>index</i>	IN	The value of the index portion of the <i>registryVariable</i> string in an indexed entry. This is an optional parameter. If specified, the indexed entry is removed from the registry.

Return Codes

Table 208. DTWF_DELENTY Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1007	A parameter contains a value which is not valid.
3004	A Web registry built-in function could not remove or retrieve an entry from the specified registry because the specified entry does not exist.
3005	A Web registry built-in function could not use the specified registry because it cannot be found.
3007	A Web registry built-in function could not complete the specified operation because the requestor does not have the proper authority to the specified registry.

Examples

Example 1:

```
@DTWR_DELENTY("Myregistry", "Jones")
```

Example 2:

```
@DTWR_DELENTY("URLLIST", "SMITH", "WORK_URL")
```

DTWR_DELREG

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X			X		X			X

Purpose

Deletes a Web registry

Format

@DTWR_DELREG(registry)

Parameters

Table 209. DTWR_DELREG Parameters

Data Type	Parameter	Use	Description
string	registry	IN	The name of the registry to delete.

Return Codes

Table 210. DTWR_DELREG Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1007	A parameter contains a value which is not valid.
3005	A Web registry built-in function could not use the specified registry because it cannot be found.
3007	A Web registry built-in function could not complete the specified operation because the requestor does not have the proper authority to the specified registry.

Examples

Example 1:

```
@DTWR_DELREG("Myregistry")
```

DTWR_LISTREG

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X			X		X			X

Purpose

Lists the contents of a Web registry.

Format

@DTWR_LISTREG(registry, registryTable)

Parameters

Table 211. DTWR_LISTREG Parameters

Data Type	Parameter	Use	Description
string	<i>registry</i>	IN	The name of the registry to list.
table	<i>registryTable</i>	OUT	The name of the table variable in which the registry entries are placed.

Return Codes

Table 212. DTWR_LISTREG Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1004	A parameter passed on a function call, required to be a Net.Data macro table variable, was of a different variable type.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
1007	A parameter contains a value which is not valid.
3005	A Web registry built-in function could not use the specified registry because it cannot be found.
3007	A Web registry built-in function could not complete the specified operation because the requestor does not have the proper authority to the specified registry.

Usage Notes

DTWR_LISTREG returns information about the registry entries in an OUT table variable passed by the user. The table variable is defined in the user macro before being passed as a parameter to the FUNCTION block for the LISTREG registry operation.

If the user defined the table variable using the ALL option for the maximum number of rows for the table, this operation lists all available registry entries in the

table, one for each table row. On the other hand if the user specified a value X for the maximum number of table rows, then if there are more than X entries in the specified registry only the first X entries are listed and an error code is sent back to indicate that only a partial listing could be done because not enough table rows were available to list additional entries. All registry entries are listed if the value X exceeds the number of available entries in the specified registry.

There are always 2 columns in the table. The Column headers for the table are set to REGISTRY_VARIABLE and REGISTRY_DATA.

Examples

Example 1:

```
%DEFINE RegistryTable = %TABLE(ALL)

@DTWR_LISTREG("URLLIST", RegistryTable)
```

DTWR_LISTSUB

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X			X					X

Purpose

Lists immediate subkey entries in a Web registry.

Format

@DTWR_LISTSUB(registry, registryTable)

Parameters

Table 213. DTWR_LISTSUB Parameters

Data Type	Parameter	Use	Description
string	<i>registry</i>	IN	The name of the registry to list.
table	<i>registryTable</i>	OUT	The name of the table variable in which the registry entries are placed.

Return Codes

Table 214. DTWR_LISTSUB Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
1007	A parameter contains a value which is not valid.
3005	A Web registry built-in function could not use the specified registry because it cannot be found.
3007	A Web registry built-in function could not complete the specified operation because the requestor does not have the proper authority to the specified registry.

Usage Notes

1. DTWR_LISTSUB returns information about the registry entries in an OUT table parameter passed by the user. The table variable is defined in the macro before being passed as a parameter to the LISTSUB registry operation.

If the user has defined the table variable using the ALL option for the maximum number of rows for the table, this operation lists all available registry entries in the table, one for each table row. On the other hand, if the user specified a value X for the maximum number of table rows then if there are more than X entries in the specified registry only the first X entries are listed and an error code is sent back to indicate that only a partial listing could

be done because not enough table rows are available to list additional entries. All registry entries are listed if the value X exceeds the number of available entries in the specified registry. The number of columns in the table is always one.

The column header for the table is set to "REGISTRY_SUBKEY".

2. This function is only valid on operating system that are compatible Windows 95 System Registries.

Examples

Example 1:

```
%DEFINE RegistryTable = %TABLE(ALL)

@DTWR_LISTSUB("URLLIST", RegistryTable)
```

DTWR_OPENREG

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
					X			

Purpose

Opens a Web registry.

Format

@DTWR_OPENREG(registry, commit)

@DTWR_OPENREG(registry)

Parameters

Table 215. DTWR_OPENREG Parameters

Data Type	Parameter	Use	Description
string	<i>registry</i>	IN	The name of the registry to open.
string	<i>commit</i>	IN	A single symbol or literal string specifying whether the registry is opened under commitment control or not. The possible values are: Y Open the registry under commitment control. N Do not open the registry under commitment control. The default is N

Return Codes

Table 216. DTWR_OPENREG Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1007	A parameter contains a value which is not valid.
3005	A Web registry built-in function could not use the specified registry because it cannot be found.
3007	A Web registry built-in function could not complete the specified operation because the requestor does not have the proper authority to the specified registry.

Examples

Example 1: Open the registry under commitment control

```
@DTWR_OPENREG("/qsys.lib/mylib.lib/myreg.file", "Y")
```

DTWR_RTENTRY

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X			X		X			X

Purpose

Retrieves a registry string value from a Web registry.

Format

@DTWR_RTENTRY(registry, registryVariable, registryData, index)

@DTWR_RTENTRY(registry, registryVariable, registryData)

@DTWR_rRTENTRY(registry, registryVariable, index)

@DTWR_rRTENTRY(registry, registryVariable)

Parameters

Table 217. DTWR_RTENTRY Parameters

Data Type	Parameter	Use	Description
string	<i>registry</i>	IN	The name of the registry with entries to retrieve.
string	<i>registryVariable</i>	IN	The value of the <i>registryVariable</i> string portion of the registry entry whose <i>registryData</i> string is retrieved.
string	<i>registryData</i>	OUT	Returns the value of the <i>registryData</i> string portion of the registry entry that matches the <i>registryVariable</i> .
string	<i>index</i>	IN	The value of the index portion of the <i>registryVariable</i> string in an indexed entry whose <i>registryData</i> string is returned. This is an optional parameter. If specified, the <i>registryData</i> string of the indexed entry is returned.

Return Codes

Table 218. DTWR_RTENTRY Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.
1007	A parameter contains a value which is not valid.

Table 218. DTWR_RTVENTRY Return Codes (continued)

Return Code	Explanation
3004	A Web registry built-in function could not remove or retrieve an entry from the specified registry because the specified entry does not exist.
3005	A Web registry built-in function could not use the specified registry because it cannot be found.
3007	A Web registry built-in function could not complete the specified operation because the requestor does not have the proper authority to the specified registry.

Examples

Example 1:

```
%DEFINE RegistryData = ""
@DTWR_RTVENTRY("Myregistry", "Jones", RegistryData)
```

Example 2:

```
@DTWR_RTVENTRY("URLLIST", "SMITH", RegistryData, "WORK_URL")
```

Example 3:

```
@DTWR_rRTVENTRY("Myregistry", "Jones")
```

Example 4:

```
@DTWR_rRTVENTRY("URLLIST", "SMITH", "WORK_URL")
```

DTWR_UPDATEENTRY

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
X			X		X			X

Purpose

Updates a registry string value in the Web registry.

Format

@DTWR_UPDATEENTRY(registry, registryVariable, newData, index)

@DTWR_UPDATEENTRY(registry, registryVariable, newData)

Parameters

Table 219. DTWR_UPDATEENTRY Parameters

Data Type	Parameter	Use	Description
string	<i>registry</i>	IN	The name of the registry with the entry to update.
string	<i>registryVariable</i>	IN	The value of the <i>registryVariable</i> string portion of the registry entry to update.
string	<i>newData</i>	IN	The new value for the <i>registryData</i> string portion of the registry entry to update.
string	<i>index</i>	IN	The value of the index portion of the <i>registryVariable</i> string in an indexed entry to update. This is an optional parameter. If specified, the indexed entry is updated.

Return Codes

Table 220. DTWR_UPDATEENTRY Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1002	An input parameter contained a string value which consisted of the null-terminating character.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1007	A parameter contains a value which is not valid.
3003	A Web registry built-in function could not add an entry to the specified registry because the specified entry already exists.
3004	A Web registry built-in function could not remove or retrieve an entry from the specified registry because the specified entry does not exist.
3005	A Web registry built-in function could not use the specified registry because it cannot be found.
3007	A Web registry built-in function could not complete the specified operation because the requestor does not have the proper authority to the specified registry.

Usage Notes

The registry entry name corresponding to the value cannot be changed.

Examples

Example 1:

```
@DTWR_UPDATEENTRY("Myregistry", "Jones", "http://advantis.com/~Jones/personal")
```

Example 2:

```
@DTWR_UPDATEENTRY("URLLIST", "SMITH", "http://www.ibm.com/software/personal",  
"WORK_URL")
```

Persistent Macro Functions

The persistent macro functions support transaction processing in Net.Data by helping you define which macro blocks are persistent within a single transaction. Use these functions to define the start and end of a transaction, which HTML blocks are persistent throughout the transaction, the scope of the variables within the transaction, and whether to commit or rollback changes within the transaction.

- “DTW_ACCEPT” on page 299
- “DTW_COMMIT” on page 301
- “DTW_ROLLBACK” on page 302
- “DTW_RTVHANDLE” on page 303
- “DTW_STATIC” on page 304
- “DTW_TERMINATE” on page 306

DTW_ACCEPT

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
					X			

Purpose

Defines the transaction handle used to invoke a persistent macro.

Format

@DTW_ACCEPT(handle, timeout)

@DTW_ACCEPT(handle)

Parameters

Table 221. DTW_ACCEPT Parameters

Data Type	Parameter	Use	Description
string	<i>handle</i>	IN	A variable or literal string specifying a transaction handle to be used in URLs for subsequent macro invocations in this persistent transaction.
integer	<i>timeout</i>	IN	A variable or literal string specifying an amount of time in seconds for the job servicing this port to wait for a response. This value overrides any timeout value specified on the DTW_STATIC() function.

Return Codes

Table 222. DTW_ACCEPT Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1007	A parameter contains a value which is not valid.
8200	Macro persistence is not enabled.
8201	A persistent built-in function was called out of sequence.

Usage Notes

1. Net.Data requires that the transaction handle be included in the URL that invokes the macro as a response from the Web browser. When a request comes in to the Web server, the server uses the transaction handle to route the request to the CGI process that is processing the transaction.

The transaction handle must be called at the start of each HTML block in the macro until the last logical block, which contains a call to DTW_TERMINATE(). If either a call to DTW_ACCEPT() or DTW_TERMINATE() is not found before any text is output to the browser, a Net.Data error occurs.

2. You can specify a timeout value for this page that overrides the timeout value specified on the @DTW_STATIC() function. The Web server waits for specified amount of time (in seconds) for the user to respond to this request.
3. If this function is called when the macro is not in a persistent state, a Net.Data error occurs.
4. The URLs containing the transaction handle can be coded as actions on form push buttons or as hypertext links on the page presented to the browser.

Examples

Example 1:

```
%DEFINE handle = ""
@DTW_RTVHANLDE(handle)

%HTML (Report){
@DTW_ACCEPT(handle)
...
%}
```


DTW_COMMIT

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
					X			

Purpose

Makes permanent any pending changes made to resources under commitment control since the last commitment boundary and establishes a new commitment boundary.

Format

@DTW_COMMIT()

Parameters

None.

Return Codes

Table 223. DTW_COMMIT Return Codes

Return Code	Explanation
1003	An incorrect number of parameters were passed on a function call.

Examples

Example 1: Specifies a commit

```
@DTW_COMMIT()  
%HTML (Report){  
%}
```

DTW_ROLLBACK

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
					X			

Purpose

Reestablishes the last commitment boundary as the current commitment boundary. All changes to resources under commitment control for the process that Net.Data is running under made since the last commitment boundary are backed out.

Format

@DTW_ROLLBACK()

Parameters

None.

Return Codes

Table 224. DTW_ROLLBACK Return Codes

Return Code	Explanation
1003	An incorrect number of parameters were passed on a function call.

Examples

Example 1: Specifies a rollback

```
@DTW_ROLLBACK()  
%HTML (Report){  
%}
```

DTW_RTVHANDLE

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
					X			

Purpose

Generates and returns a transaction handle that is unique to this macro across separate invocations and is calculated based on a combination of thread information, timestamp, and current user.

Format

@DTW_RTVHANDLE(handle)

Parameters

Table 225. DTW_RTVHANDLE Parameters

Data Type	Parameter	Use	Description
string	<i>handle</i>	OUT	A variable that contains a unique transaction handle for the current persistent macro.

Return Codes

Table 226. DTW_RTVHANDLE Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1006	A literal string was passed on a function call for a parameter which was required to be an output parameter.

Usage Notes

The transaction handle can be used to ensure that URLs specified as part of a persistent transaction are unique to the HTTP server and can be securely identified as valid requests.

Examples

Example 1: Defines the `handle` variable used to retrieve the transaction handle

```
%DEFINE handle = ""  
@DTW_RTVHANDLE(handle)
```

DTW_STATIC

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
					X			

Purpose

Indicates that the entire macro is persistent.

Format

@DTW_STATIC(timeout)

@DTW_STATIC()

Parameters

Table 227. DTW_STATIC Parameters

Data Type	Parameter	Use	Description
integer	<i>timeout</i>	IN	A variable or literal string that specifies an amount of time, in seconds, that the process handling this transaction should wait for a response.

Return Codes

Table 228. DTW_STATIC Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1001	An input parameter contained a NULL value.
1003	An incorrect number of parameters were passed on a function call.
1005	A parameter passed on a function call, required to be a string variable, was of a different variable type.
1007	A parameter contains a value which is not valid.
8202	Persistence could not be enabled.

Usage Notes

1. DTW_STATIC should be the first statement in the macro. All variables defined in the macro after this function call will be persistent across multiple macro invocations unless specified otherwise and until DTW_TERMINATE() is called or the process is ended.
2. A timeout value, in seconds, can be specified on the function call to indicate the amount of time the process Net.Data is running under waits for a response from the browser. If the timeout value expires, the process ends, and all changes to resources under commitment control since the last commitment boundary are rolled back.
3. If a timeout value is specified on a subsequent @DTW_ACCEPT() call, Net.Data overrides this value with the value in the subsequent call. If a timeout value is not specified on this call or a subsequent @DTW_ACCEPT() call, the Web server default timeout value is used.

Examples

Example 1: A call to `DTW_STATIC()` specifying a timeout value of 60 seconds.

```
@DTW_STATIC("60")
```

DTW_TERMINATE

AIX	HP-UX	Linux	OS/2	OS/390	OS/400	PTX	SUN	Win NT
					X			

Purpose

Ends a persistent transaction. All changes to resources under commitment control since the last commitment boundary are made permanent.

Format

@DTW_TERMINATE()

Parameters

None

Return Codes

Table 229. DTW_TERMINATE Return Codes

Return Code	Explanation
-1001	The server could not process a Net.Data request to allocate memory.
1003	An incorrect number of parameters were passed on a function call.
8200	Macro persistence is not enabled.
8201	A persistent built-in function was called out of sequence.

Usage Notes

1. The DTW_TERMINATE function is called at the start of the logical last HTML block of the persistent transaction before any text is output to the browser. If any text output appears before the function, within the block, a Net.Data error will occur. Note that there could be more than one logical last HTML block depending on how the application is written.
2. If this function is called when the macro is not in a persistent state, a Net.Data error will occur.

Examples

Example 1: Terminates the persistent transaction

```
%HTML(QUIT){
@DTW_TERMINATE()
...
%}
```

Java Applet Functions

The Java applet language environment lets you easily generate HTML tags for Java applets in your Net.Data applications. When you call the Java applet functions, you specify the name of your applet and pass any parameters that the applet needs. The language environment processes the macro and generates the HTML applet tags, which the Web browser uses to run the applet.

Additionally, Net.Data provides a set of interfaces your applet can use to access table parameters. These interfaces are contained in the class, DTW_Applet.class.

The following sections describe how to use the Java applet language environment to run your Java applets.

Configuring the Java Applet Language Environment

Verify that the following configuration statement is in the initialization file, on one line:

```
ENVIRONMENT (DTW_APPLET)    app1d11    ()
```

See the *Net.Data Administration and Programming Guide* to learn more about the Net.Data initialization file and language environment ENVIRONMENT statements.

Creating Java Applets

Before using the Net.Data Java applet language environment, you need to determine which applets you plan to use or which applets you need to write. See your Java documentation for more information on creating applets.

Generating the Applet Tags

You specify a call to the applet language environment with a Net.Data function call. No declaration is needed for the function call. The syntax for the function call is shown here:

```
@DTWA_AppletName(param1, param2, ..., paramN)
```

- DTWA_ identifies the function call to the applet language environment.
- AppletName is the name of the applet for which tags are generated.
- param1 through paramN are parameters used to generate PARAM tags.

To write a macro that generates applet tags:

1. Define any parameters required by the applet in the DEFINE section of the macro. These parameters include any applet tag attributes, Net.Data variables, and Net.Data table parameters that you need as input for the applet. For example:

```
%define{
  DATABASE = "celdial"           <=Name of the database
  MyGraph.codebase = "/netdata-java/" <=Required applet attribute
  MyGraph.height = "200"         <=Required applet attribute
  MyGraph.width = "400"          <=Required applet attribute
  MyTitle = "Celdial results"    <=Name of the Web page
  MyTable = %TABLE(all)          <=Table to store query results
%}
```

2. Optional: Specify a query to the database to generate a result set as input for the applet. This is useful when you are using an applet that generates a chart or table. For example:

```
%FUNCTION(DTW_SQL) mySQL(OUT table){
  select name, ages from ibmuser.guests
%}
```

3. Specify the function call in the Net.Data macro to call the Java applet language environment and invoke the applet. The function call specifies the name of the applet and the parameters you want to pass to the language environment. These parameters include any Net.Data variables, and Net.Data table or column parameters that you need as input for the applet.

For example:

```
%HTML (Report){
  @mySQL(MyTable)                                <=A call to mySQL
  @DTWA_MyGraph(MyTitle, DTW_COLUMN(ages) MyTable) <=Applet function call
%}
```

Applet Tag Attributes

You can specify attributes for applet tags anywhere in your Net.Data macro. Net.Data substitutes all variables that have the form *AppletName.attribute* into the applet tag as attributes. The syntax for defining an attribute on an applet tag is shown here:

```
%define AppletName.attribute = "value"
```

The following attributes are required for all applets:

- *codebase*: The location of the applet, which is identified by a URL.
- *height*: The height of the applet in pixels.
- *width*: The width of the applet in pixels.

The following attributes are optional:

- *align*: the alignment of the applet
- *alt*: any text that should be displayed if the browser understands the APPLET tag but can't run Java applets
- *archive*: an archive containing classes and other resources
- *hspace*: the number of pixels on each side of the applet
- *name*: a name for the applet instance
- *object*: the name of the file that contains a serialized representation of an applet
- *vspace*: the number of pixels above and below the applet

For example, if your applet is called MyGraph, you can define these required attributes as shown here:

```
%DEFINE{
MyGraph.codebase = "/netdata-java/"
MyGraph.height   = "200"
MyGraph.width    = "400"
%}
```

The actual assignment need not be in a DEFINE section. You can set the value with the DTW_ASSIGN function. If you do not define a variable for *AppletName.code* variable, Net.Data adds a default *code* parameter to the applet tag. The value of the *code* parameter is *AppletName.class*, where *AppletName* is the name of your applet.

Applet Tag Parameters

You define a list of parameters to pass to the Java applet language environment in the function call. You can pass parameters that include:

- Net.Data variables (including LIST variables)
- Net.Data tables
- Columns of Net.Data tables

When you pass a parameter, Net.Data creates a Java applet PARAM tag in the HTML output with the name and value that you assign to the parameter. You cannot pass string literals or results of function calls.

Net.Data Variable Parameters:

You can use Net.Data variables as parameters. If you define a variable in the DEFINE block of the macro and pass the variable value in the DTWA_AppletName function call, Net.Data generates a PARAM tag that has the same name and value as the variable. For example, given the following macro statement:

```
%define{
...

MyTitle = "This is my Title"
%}

%HTML (Report){
@DTWA_MyGraph( MyTitle, ...)
%}
```

Net.Data produces the following applet PARAM tag:

```
<param name = 'MyTitle' value = "This is my Title" />
```

Net.Data Table Parameters:

Net.Data automatically generates a PARAM tag with the name DTW_NUMBER_OF_TABLES every time the Java applet language environment is called, specifying whether the function call has passed any table variables. The value is the number of table variables that Net.Data uses in the function. If no table variables are specified in the function call, the following tag is generated:

```
<param name = "DTW_NUMBER_OF_TABLES" value = "0" />
```

You can pass one or more Net.Data table variables as parameters on the function call. If you specify a Net.Data table variable on a DTWA_AppletName function call, Net.Data generates the following PARAM tags:

Table name parameter tag:

This tag specifies the names of the tables to pass. The tag has the following syntax:

```
<param name = 'DTW_TABLE_i_NAME' value = "tname" />
```

Where *i* is the number of the table based on the ordering of the function call, and *tname* is the name of the table.

Row and column specification parameter tags:

PARAM tags are generated to specify the number of rows and columns a particular table. This tag has the following syntax:

```
<param name = 'DTW_tname_NUMBER_OF_ROWS' value = "rows" />
<param name = 'DTW_tname_NUMBER_OF_COLUMNS' value = "cols" />
```

Where the name of the table is *tname*, *rows* is the number of rows in the table, and *cols* is the number of columns in the table. This pair of tags is generated for each unique table specified in the function call.

Column value parameter tags:

This PARAM tag specifies the column name of a particular column. This tag has the following syntax:

```
<param name = 'DTW_tname_COLUMN_NAME_j' value = "cname" />
```

Where the table name is *tname*, *j* is the column number, and *cname* is the name of the column in the table.

Row value parameter tags:

This PARAM tag specifies the values at a particular row and column. This tag has the following syntax:

```
<param name = 'DTW_tname_cname_VALUE_k' value = "val" />
```

Where the table name is *tname*, *cname* is the column name, *k* is the row number, and *val* is the value that matches the value in the corresponding row and column.

Table Column Parameters: You can pass a table column as a parameter on a function call to generate tags for a specific column. Net.Data generates the corresponding applet tags only for the specified column. A table column parameter uses the following syntax:

```
@DTWA_AppletName(DTW_COLUMN( x )Table)
```

Where *x* is the name or number of the column in the table.

Table column parameters use the same applet tags defined for the table parameters.

Alternate Text for the Applet Tag on Browsers that are not Java-Enabled

The variable DTW_APPLET_ALTTEXT specifies the text to display on browsers that do not support Java or have turned Java support off. For example, the following variable definition:

```
%define DTW_APPLET_ALTTEXT = "<p>Sorry, your browser is not Java-enabled.</p>"
```

produces the following HTML tag and text:

```
<p>Sorry, your browser is not Java-enabled.</p><
```

If this variable is not defined, no alternate text is displayed.

Java Applet Example

The following example demonstrates a Net.Data macro that calls the Java applet language environment and the resulting applet tag that the language environment generates.

The Net.Data macro contains the following function calls to the Java applet language environment:

```
%define{
  DATABASE = "celdial"
  DTW_APPLET_ALTTEXT = "<p>Sorry, your browser is not Java-enabled.</p>"
  DTW_DEFAULT_REPORT = "no"
  MyGraph.codebase = "/netdata-java/"
  MyGraph.height = "200"
  MyGraph.width = "400"
  MyTitle = "This is my Title"
}%
%FUNCTION(DTW_SQL) mySQL(OUT table){
  select name, ages from ibmuser.guests
}%
%HTML (Report){
  @mySQL(MyTable)
  @DTWA_MyGraph(MyTitle, DTW_COLUMN(ages) MyTable)
}%
```

The Net.Data macro lines in the DEFINE section specify the attributes of the applet tag:

```
MyGraph.codebase = "/netdata-java/"
MyGraph.height = "200"
MyGraph.width = "400"
```

The language environment generates an applet tag with the following qualifiers:

```
<applet code='MyGraph.class'
        codebase='/netdata-java/'
width='400'
height='200'
>
```

Net.Data returns the SQL query results from the SQL section of the Net.Data macro in the output table, MyTable. This table is specified in the DEFINE section:

```
MyTable = %TABLE(all)
```

The call to the applet in the macro is specified in the HTML section:

```
@DTWA_MyGraph(MyTitle, DTW_COLUMN(ages) MyTable)
```

Based on the parameters in the function call, Net.Data generates the complete applet tag containing the information about the result table, such as the number of columns, the number of rows returned, and the result rows. Net.Data generates one parameter tag for each cell in the result table, as shown in the following example:

```
<param name = 'DTW_MyTable_ages_VALUE_1' value = "35" />
```

The parameter name, *DTW_MyTable_ages_VALUE_1*, specifies the table cell (row 1, column ages) in the table, MyTable, which has a value of 4. The keyword, DTW_COLUMN, in the function call to the applet, specifies that you are interested only in the column ages of the resulting table, MyTable, shown here:

```
@DTWA_MyGraph( MyTitle, DTW_COLUMN(ages) MyTable )
```

The following output shows the complete applet tag that Net.Data generates for the example:

```
<applet code='MyGraph.class' codebase='/netdata-java/'
        width='400'          height='200'
>
<param name = 'MyTitle' value = "This is my Title" />
<param name = 'DTW_NUMBER_OF_TABLES' value = "1" />
<param name = 'DTW_TABLE_1_NAME' value = "MyTable" />
<param name = 'DTW_MyTable_NUMBER_OF_ROWS' value = "5" />
<param name = 'DTW_MyTable_NUMBER_OF_COLUMNS' value = "1" />
<param name = 'DTW_MyTable_COLUMN_NAME_1' value = "ages" />
<param name = 'DTW_MyTable_ages_VALUE_1' value = "35" />
<param name = 'DTW_MyTable_ages_VALUE_2' value = "32" />
<param name = 'DTW_MyTable_ages_VALUE_3' value = "31" />
<param name = 'DTW_MyTable_ages_VALUE_4' value = "28" />
<param name = 'DTW_MyTable_ages_VALUE_5' value = "40" />
<p>Sorry, your browser is not Java-enabled.</p>
</applet>
```

Using the Net.Data Java Applet Interface

Net.Data provides a set of interfaces in a class called DTW_Applet.class, which you can use with your Java applets to help process the PARAM tags that are generated for table variables. You can create an applet that extends this interface to call the routines from your applet.

Net.Data provides these interfaces:

- **int GetNumberOfTables()** returns the number of tables found in the applet tag.
- **String [] GetTableNames()** returns a list of the table names found in the applet tag.
- **int GetNumberOfColumns(String table_name)** returns the number of columns in the table table_name.
- **int GetNumberOfRows(String table_name)** returns the number of rows in the table table_name.
- **String[] GetColumnNames(String table_name)** returns the names of the columns in the table table_name.
- **String[][] GetTable(String table_name)** returns a two-dimensional array of strings containing the values of the table's rows and columns.

To access the interfaces, use the EXTENDS keyword in your applet code to subclass your applet from the DTW_APPLET class, as shown in the following example:

```
import java.io.*;
import java.applet.Applet;

public class myDriver extends DTW_Applet
{
    public void init()
    {
        super.init();

        if (GetNumberOfTables() > 0)
        {
            String [] tables = GetTableNames();
            printTables(tables);
        }
    }

    private void printTables(String[] tables)
    {
        String table_name;

        for (int i = 0; i < tables.length; i++)
        {
            table_name = tables[i];
            printTable(table_name);
        }
    }

    private void printTable(String table_name)
    {
        int nrows = GetNumberOfRows(table_name);
        int ncols = GetNumberOfColumns(table_name);

        System.out.println("Table: " + table_name + " has " + ncols +
            " columns and " + nrows + " rows.");

        String [] col_names = GetColumnNames(table_name);

        System.out.println("-----");

        for (int i = 0; i < ncols; i++)
            System.out.print("    " + col_names[i] + "    ");
        System.out.println("\n-----");

        String [][] mytable = GetTable(table_name);

        for (int j = 0; j < nrows; j++)
```

```
        {  
        for (int i = 0; i < ncols; i++)  
            System.out.print(" " + mytable[i][j] + " ");  
  
        System.out.println("\n");  
        }  
    }  
}
```

Appendix A. Net.Data Technical Library

The Net.Data Technical Library is available from the Net.Data Web site at
<http://www.ibm.com/software/data/net.data/library.html>

Document	Description
<ul style="list-style-type: none">• <i>Net.Data Administration and Programming Guide for OS/390</i>• <i>Net.Data Administration and Programming Guide for OS/2, Windows NT, and UNIX</i>• <i>Net.Data Administration and Programming Guide for OS/400</i>	Contains conceptual and task information about installing, configuring, and invoking Net.Data. Also describes how to write Net.Data macros, use Net.Data performance techniques, use Net.Data language environments, manage connections, and use Net.Data logging and traces for trouble shooting and performance tuning.
<i>Net.Data Reference</i>	Describes the Net.Data macro language, variables, and built-in functions.
<i>Net.Data Language Environment Interface Reference</i>	Describes the Net.Data language environment interface.
<i>Net.Data Messages and Codes Reference</i>	Lists Net.Data error messages and return codes.

Appendix B. Deprecated Features

The following features are still supported, but not recommended. If you have macros that contain these language constructs, it is recommended that you use the suggested alternatives.

EXEC_SQL

A DB2 WWW Connection language construct that calls an SQL block. We recommend calling SQL statements as functions instead. See “FUNCTION Block” on page 17 for more information.

HTML_INPUT

A DB2 WWW Connection language construct that is the same as an HTML block named INPUT. See “HTML Block” on page 27 for more information.

HTML_REPORT

A DB2 WWW Connection language construct that is the same as an HTML block named REPORT. See “HTML Block” on page 27 for more information.

INCLUDE_URL

A statement used to read and incorporate another file into the Net.Data generated output. Upon execution, the entire contents of the included file will replace the INCLUDE_URL statement. The specified file can exist on a local or remote server.

Though there is no recommended alternative to including the contents of a remote URL, you can use the INCLUDE statement to include local files, including macros. Including remote URLs is not recommended because there is no way to trap any of the unexpected situations that might occur when accessing a remote site.

SQL

A DB2 WWW Connection language construct that is equivalent to a function called with FUNCTION(DTW_SQL) in Net.Data.

It can contain SQL_REPORT and SQL_MESSAGE statements, which are also from DB2 WWW Connection. DB2 WWW Connection does not support named %SQL blocks.

Examples:

Example 1: A DB2 WWW Connection macro

```
%SQL{  
UPDATE $(dbtb1) SET URL='${URL}' WHERE ID=$(ID)  
%SQL_MESSAGE{  
100: "<b>The selected URL no longer exists in the table</b>." : continue  
%}  
%}  
  
%HTML_INPUT{  
<html>
```

```

...
%EXEC_SQL
</html>
%}

%HTML_REPORT{
<html>
...
</html>
%}

```

Example 1: An equivalent Net.Data macro

```

%FUNCTION(DTW_SQL) URLquery(){
UPDATE $(dbtb1) SET URL='$(URL)' WHERE ID=$(ID)
%MESSAGE{
100: "<b>The selected URL no longer exists in the table</b>." : continue
%}
%}

%HTML(INPUT){
<html>
...
@URLquery
</html>
%}

%HTML (Report){
<html>
...
</html>
%}

```

SQL_MESSAGE

A DB2 WWW Connection language construct that is equivalent to the Net.Data MESSAGE statement. See “MESSAGE Block” on page 43 for an example.

SQL_REPORT

A DB2 WWW Connection language construct that is equivalent to the Net.Data REPORT statement. See “REPORT Block” on page 47 for an example.

SQL_CODE

A DB2 WWW Connection language construct that is equivalent to “RETURN_CODE” on page 112.

Appendix C. Net.Data Operating System Reference

Not all Net.Data features are supported on each operating system. This section shows which features are supported for your operating system. An **X** indicates the feature is supported.

Table 230. Net.Data Language Environments

Language Environment	AIX	HP	LINUX	OS/2	OS/390	OS/400	PTX	SUN	Win NT
Direct Call						X			
COBOL					X				
IMS Web	X			X				X	X
Java Applications	X			X		X		X	X
ODBC	X	X		X	X			X	X
Oracle	X								X
Perl	X	X	X	X	X		X	X	X
REXX	X		X	X	X	X		X	X
SQL	X	X	X	X	X	X	X	X	X
System	X	X	X	X	X	X	X	X	X
Web Registry	X			X		X			X

Table 231. Net.Data Configuration Variables

Configuration Variable	AIX	HP	LINUX	OS/2	OS/390	OS/400	PTX	SUN	Win NT
DB2INSTANCE	X	X	X	X			X	X	X
DB2MSG					X				
DB2PLAN					X				
DB2SSID					X				
DefaultDBCp					X				
DSNAOINI					X				
DTW_CACHE_HOST	X								X
DTW_CACHE_MACRO					X				
DTW_CACHE_MANAGEMENT_INTERVAL					X				
DTW_CACHE_PAGE					X				
DTW_CACHE_PORT	X								X
DTW_CM_PORT	X	X		X					X
DTW_DEFAULT_ERROR_MESSAGE	X	X	X	X	X	X	X	X	X
DTW_DEFAULT_MACRO					X	X			
DTW_DIRECT_REQUEST	X	X		X	X			X	X
DTW_DO_NOT_CACHE_MACRO					X				
DTW_ERROR_LOG_DIR					X				
DTW_ERROR_LOG_LEVEL					X				
DTW_INST_DIR	X		X	X			X	X	X
DTW_LOB_DIR	X		X	X	X		X	X	X
DTW_LOB_LIFETIME					X				
DTW_LOG_DIR	X	X	X	X			X	X	X
DTW_LOG_LEVEL	X	X	X	X			X	X	X
DTW_MBMODE	X	X	X	X	X		X	X	X
DTW_OUTPUT_DIR					X				
DTW_REMOVE_WS	X	X	X	X	X	X	X	X	X
DTW_SHOWSQL	X	X	X	X	X	X	X	X	X
DTW_SMTP_CHARSET						X			

Table 231. Net.Data Configuration Variables (continued)

Configuration Variable	AIX	HP	LINUX	OS/2	OS/390	OS/400	PTX	SUN	Win NT
DTW_SMTP_SERVER	X	X	X	X		X	X	X	X
DTW_SQL_ISOLATION						X			
DTW_SQL_NAMING_MODE						X			
DTW_STORE_PAGE					X				
DTW_TRACE_LOG_DIR					X				
DTW_TRACE_LOG_LEVEL					X				
DTW_UNICODE	X	X	X	X			X	X	X
DTW_USE_DB2_PREPARE_CACHE	X	X	X	X	X	X	X	X	X
DTW_UPLOAD_DIR	X	X	X	X	X	X	X	X	X
DTW_VARIABLE_SCOPE	X	X	X	X			X	X	X

Table 233. Net.Data Functions (continued)

[illegible]

Table 233. Net.Data Functions (continued)

Function	AIX	HP	LINUX	OS/2	OS/390	OS/400	PTX	SUN	Win NT
DTWF_OPEN	X	X	X	X	X	X	X	X	X
DTWF_READ	X	X	X	X	X	X	X	X	X
DTWF_READFILE	X	X	X	X	X	X	X	X	X
DTWF_REMOVE	X	X	X	X	X	X	X	X	X
DTWF_SEARCH	X	X	X	X	X	X	X	X	X
DTWF_UPDATE	X	X	X	X	X	X	X	X	X
DTWF_WRITE	X	X	X	X	X	X	X	X	X
DTWF_WRITEFILE					X	X			
DTWR_ADDENTRY	X			X		X			X
DTWR_CLEARREG	X			X		X			X
DTWR_CLOSEREG						X			
DTWR_CREATEREG	X			X		X			X
DTWR_DELENTY	X			X		X			X
DTWR_DELREG	X			X		X			X
DTWR_LISTREG	X			X		X			X
DTWR_LISTSUB	X			X					X
DTWR_OPENREG						X			
DTWR_RTVENTRY	X			X		X			X
DTWR_UPDATEENTRY	X			X		X			X

Table 234. Net.Data Interfaces

Interface Type	AIX	HP	LINUX	OS/2	OS/390	OS/400	PTX	SUN	Win NT
FastCGI	X				X			X	
CGI	X	X	X	X	X	X	X	X	X
Java Beans									X
Live Connection	X			X				X	X
Lotus Domino Go Web Server (GWAPI)	X			X	X				X
Netscape API (NSAPI)								X	X
Servlets	X				X			X	X

Table 235. Net.Data Tools

Tool	AIX	HP	LINUX	OS/2	OS/390	OS/400	PTX	SUN	Win NT
Administration Tool	X			X					X
NetObjects Fusion Plug-ins									X
Wizards	X			X				X	X

Notices

This information was developed for products and services offered in the U.S.A. IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing
IBM Corporation
500 Columbus Avenue
Thornwood, NY 10594
U.S.A.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

IBM World Trade Asia Corporation
Licensing
2-31 Roppongi 3-chome, Minato-ku
Tokyo 106, Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law:

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information that has been exchanged, should contact:

IBM Corporation
555 Bailey Avenue, W92/H3
P.O. Box 49023
San Jose, CA 95161-9023

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this information and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement or any equivalent agreement between us.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrates programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. You may copy, modify, and distribute these sample programs in any form without payment to IBM for the purposes of developing, using, marketing, or distributing application programs conforming to IBM's application programming interfaces.

Trademarks

The following terms are trademarks of the IBM Corporation in the United States or other countries or both:

AIX	Language Environment
AS/400	MVS/ESA
DB2	Net.Data
DB2 Universal Database	OS/2
DRDA	OS/390
DataJoiner	OS/400
IBM	OpenEdition
IMS	

The following terms are trademarks of other companies as follows:

Java and all Java-based trademarks and logos are trademarks of Sun Microsystems, Inc. in the United States and/or other countries.

UNIX is a registered trademark in the United States and/or other countries licensed exclusively through X/Open Company Limited.

Lotus and Domino Go Webserver are trademarks of Lotus Development Corporation in the United States and/or other countries.

Microsoft, Windows, Windows NT, and the Windows logo are trademarks or registered trademarks of Microsoft Corporation in the United States and/or other countries.

Other company, product, and service names, which may be denoted by a double asterisk (**), may be trademarks or service marks of others.

Index

A

- absolute paths, for flat files 247
- accessing flat files 246
- ALIGN 75
- alternate text, Web browsers 86
- APPLET tag, alternate text 86
- authorization requirement,
 - FFI_PATH 248

B

- built-in functions 113

C

- calling
 - external programs 14
 - functions 23
- calling FFI language environment 246
- case, specifying for SQL commands 83
- COMMENT block
 - description 8
 - syntax 8
- conditional string processing 29, 53
- conditional variables
 - description 60
 - example 63
 - with LIST statements 60
 - with variable references 60
- configuring the FFI language environment 248
- connecting to a database, DATABASE variable 81
- connecting to DB2 subsystem
 - DB2 plan 84
 - location 91
 - subsystem ID 85
- cookies
 - DTW_GETCOOKIE 125
 - DTW_PRINT_HEADER 108
 - DTW_SETCOOKIE 139
 - sending 108
- current directory, determining for flat files 247

D

- DATABASE 81
- database consistency, transaction scope 97
- date formats, UTF-8 122
- date variables 98
- DB_CASE 83
- DB2PLAN 84
- DB2SSID 85
- declaration part, macro 1
- DEFINE block
 - description 10
 - syntax 10
- DEFINE statement
 - description 10

- DEFINE statement (*continued*)
 - syntax 10
- delimited string of values 63
- delimiters, FFI language environment
 - ASCIITEXT 249
 - DELIMITED 249
- DTW_ACCEPT 299
- DTW_ADD 149
- DTW_ADDQUOTE 116
- DTW_APPLET 306
- DTW_APPLET_ALTTEXT 86
- DTW_ASSIGN 66, 167, 168
- DTW_CACHE_PAGE 118
- DTW_CHARTOHEX 169
- DTW_COMMIT 301
- DTW_CONCAT 170
- DTW_CURRENT_FILENAME 99
- DTW_CURRENT_LAST_MODIFIED 100
- DTW_DATE 121
- DTW_DEFAULT_MESSAGE 101
- DTW_DEFAULT_REPORT 76
- DTW_DELSTR 170
- DTW_DELOWORD 193
- DTW_DIVIDE 151
- DTW_DIVREM 153
- DTW_EDIT_CODES 87
- DTW_FORMAT 155
- DTW_GETCOOKIE 125
- DTW_GETENV 126
- DTW_GETINIDATA 127
- DTW_HEXTOCHAR 173
- DTW_HTML_TABLE 77
- DTW_HTMLENCODER 128
- DTW_INSERT 174
- DTW_INTDIV 158
- DTW_LASTPOS 175
- DTW_LENGTH 177
- DTW_LOG_ERRORMSG 130
- DTW_LOG_LEVEL 102
- DTW_LOG_TRACEMSG 131
- DTW_LOWERCASE 178
- DTW_MACRO_FILENAME 103
- DTW_MACRO_LAST_MODIFIED 104
- DTW_MBMODE 105
- DTW_MP_PATH 106
- DTW_MP_VERSION 107
- DTW_MULTIPLY 160, 161
- DTW_PAD_PGM_PARMS 88
- DTW_POS 180
- DTW_POWER 162
- DTW_PRINT_HEADER 108
- DTW_QHTMLENCODER 132
- DTW_REMOVE_WS 109
- DTW_REPLACE 183
- DTW_REVERSE 185
- DTW_ROLLBACK 302
- DTW_RTVHANDLE 303
- DTW_SAVE_TABLE_IN 89
- DTW_SENDEMIL 134
- DTW_SET_TOTAL_ROWS 90
- DTW_SETCOOKIE 139

- DTW_SETENV 142
- DTW_STATIC 304
- DTW_STRIP 186
- DTW_SUBSTR 187
- DTW_SUBTRACT 164
- DTW_SUBWORD 195
- DTW_TB_APPENDROW 205
- DTW_TB_COLS 207
- DTW_TB_deleteCOL 208
- DTW_TB_DELETEROW 209
- DTW_TB_DLIST 211
- DTW_TB_DUMP 212
- DTW_TB_DUMPV 213
- DTW_TB_GETN 216
- DTW_TB_GETV 218
- DTW_TB_HTMLENCODER 220
- DTW_TB_INPUT_CHECKBOX 221
- DTW_TB_INPUT_RADIO 223
- DTW_TB_INPUT_TEXT 225
- DTW_TB_INSERTCOL 228
- DTW_TB_INSERTROW 229
- DTW_TB_LIST 227
- DTW_TB_QUERYCOLNONJ 233
- DTW_TB_ROWS 235
- DTW_TB_SELECT 236
- DTW_TB_SETCOLS 238
- DTW_TB_SETN 239
- DTW_TB_SETV 241
- DTW_TB_TABLE 243
- DTW_TB_TEXTAREA 245
- DTW_TERMINATE 306
- DTW_TIME 144
- DTW_TRANSLATE 189
- DTW_UPPERCASE 191
- DTW_URLESCSEQ 146
- DTW_USE_DB2_PREPARE_CACHE 110
- DTW_WORD 197
- DTW_WORDINDEX 199
- DTW_WORDLENGTH 200
- DTW_WORDPOS 200
- DTW_WORDS 202
- DTWF_APPEND 249
- DTWF_CLOSE 249, 252
- DTWF_COPY 253
- DTWF_DELETE 254
- DTWF_EXISTS 256
- DTWF_INSERT 257
- DTWF_OPEN 249, 260
- DTWF_READ 262
- DTWF_READFILE 265
- DTWF_REMOVE 267
- DTWF_SEARCH 269
- DTWF_UPDATE 272
- DTWF_WRITE 275
- DTWF_WRITEFILE 278
- DTWR_ADDENTRY 280
- DTWR_CLEARREG 282
- DTWR_CLOSEREG 284
- DTWR_CREATEREG 284
- DTWR_DELENTY 286
- DTWR_DELREG 288

DTWR_LISTREG 289
DTWR_LISTSUB 291
DTWR_OPENREG 294
DTWR_RTVENTRY 295
DTWR_UPDATEENTRY 296

E

environment variables
 description 61
 ENVVAR statement 14
 example 61
ENVVAR statement 61
 description 14
 syntax 14
error handling 43
EXEC block
 description 15
 syntax 15
EXEC_PATH 15
EXEC_SQL 317
EXEC statement 61
 description 15
 syntax 15
executable variables
 as a variable reference 62
 description 61
 example 62
 with parameters 62

F

FFI functions
 DTWF_APPEND 250
 DTWF_CLOSE 253
 DTWF_COPY 254
 DTWF_DELETE 255
 DTWF_EXISTS 257
 DTWF_INSERT 258
 DTWF_OPEN 261
 DTWF_READ 263
 DTWF_READFILE 266
 DTWF_REMOVE 268
 DTWF_SEARCH 270
 DTWF_UPDATE 273
 DTWF_WRITE 276
 DTWF_WRITEFILE 279
 freeing files 249
 locking files 249
FFI language environment
 accessing files 246
 authorization requirement 248
 configuration rules 248
 current directory 247
 delimiters 248
 file location 247
 security recommendations 248
FFI_PATH
 accessing flat files 246
 configuration rules 248
 flat file location 247
 matching paths with *filename*
 parameter 247
 security recommendations 248
 syntax 246
file location variables 98
flat files
 absolute paths 247

flat files (*continued*)
 accessing 246
 authorization requirement 248
 configuration rules 248
 creating in current directory 247
 data sources 246
 definition 246
 delimiters 248
 location
 current directory 247
 FFI_PATH 247
 locking files 249
 matching the FFI_PATH 247
 recommendations for access 247
 security recommendations 248
footers 35
freeing files, FFI functions 249
FUNCTION block
 description 17
 syntax 18
function calls
 description 24
 formatting output 47
 processing table rows 49
 syntax 24
 use of INOUT variables 25
functions
 description 113
 flat file interface (FFI) 246
 general 114
 Java applet 306
 math 148
 naming conventions 113
 passing groups of values 64
 persistent 298
 string 166
 table 203
 Web registry 280
 word 193

G

general functions 114
 DTW_ADDQUOTE 116
 DTW_CACHE_PAGE 118
 DTW_DATE 122
 DTW_EXIT 124
 DTW_GETCOOKIE 125
 DTW_GETENV 127
 DTW_GETINIDATA 128
 DTW_HTMLENCODE 129
 DTW_LOG_ERRORMSG 131
 DTW_LOG_TRACEMSG 132
 DTW_QHTMLENCODE 133
 DTW_SENDEMAIL 134
 DTW_SETCOOKIE 139
 DTW_SETENV 143
 DTW_TIME 145
 DTW_URLESCSEQ 147
generating Java applets 306

H

headers 35
hidden variables
 description 62
 example, in an HTML form 63

hidden variables (*continued*)
 steps 62
hiding variable names 62
HTML
 displaying table results in 77
 form, entering passwords 94
 form, entering user IDs 92
 hiding variable names 62
HTML block
 description 27
 syntax 27
HTML_INPUT block 317
HTML_REPORT block 317

I

IF block
 description 29
 syntax 29
IN keyword 19, 40, 113
include files 35
INCLUDE_PATH 35
INCLUDE statement
 description 35
 syntax 35
INCLUDE_URL 317
INOUT keyword 19, 40, 113
INOUT variable
 example 25
invoking applets 307

J

Java applets
 classes 311
 creating 307
 generating tags 307
 invoking 307

L

language constructs
 COMMENT block 8
 common syntax elements 4
 DEFINE block or statement 10
 ENVVAR statement 14
 EXEC block or statement 15
 FUNCTION block 17
 function calls 24
 HTML block 27
 IF block 29
 INCLUDE statement 35
 LIST statement 37
 macro
 description 6
 syntax 1
 MACRO_FUNCTION block 39
 MESSAGE block 43
 REPORT block 47
 ROW block 49
 strings 5
 TABLE statement 51
 variable name 4
 variable reference 4
 WHILE block 53
 XML block 56
language environment variables
 DATABASE 81

language environment variables
(continued)

DB_CASE 83
DB2PLAN 84
DB2SSID 85
description 80
DTW_APPLET_ALTTEXT 86
DTW_EDIT_CODES 87
DTW_MBMODE 105
DTW_PAD_PGM_PARMS 88
DTW_SAVE_TABLE_IN 89
DTW_SET_TOTAL_ROWS 90
LOCATION 91
LOGIN 92
NULL_RPT_FIELD 93
PASSWORD 94
SHOWSQL 95
SQL_STATE 96
TRANSACTION_SCOPE 97

language environments

Java applet 306

line length limits, macros 3

LIST statement

description 37
syntax 37

list variables

description 63
example 63
value separators 64

listing delimited strings 63

local DB2 subsystem, ID 85

LOCATION 91

location, connecting to DB2

subsystem 91

location, flat files 247

locking files, FFI functions 249

LOGIN 92

looping 53

lower case, specifying 83

M

MACRO_FUNCTION block

description 39
syntax 39

macros

common syntax elements 4
declaration part 1
format 2
global syntax 1
language constructs 1
line length limits 3
presentation part 1
sample 2
stop processing 124

math functions

DTW_ADD 150
DTW_DIVIDE 152
DTW_DIVREM 154
DTW_FORMAT 156
DTW_INTDIV 159
DTW_MULTIPLY 161
DTW_POWER 163
DTW_SUBTRACT 165

MBCS support for functions

string functions 166
word functions 193

MESSAGE block

description 43

MESSAGE block (continued)

syntax 43
messages, default text 101
miscellaneous variables
description 98
DTW_CURRENT_FILENAME 99
DTW_CURRENT_LAST_MODIFIED 100
DTW_DEFAULT_MESSAGE 101
DTW_MACRO_LAST_MODIFIED 104
DTW_MP_PATH 106
DTW_MP_VERSION 107
DTW_PRINT_HEADER 108
DTW_REMOVE_WS 109
DTW_USE_DB2_PREPARE_CACHE 110
RETURN_CODE 112

N

Nn 66

Net.Data tables

defining 51
upper limit 51

Next button, RPT_MAX_ROWS 79

NLIST 67

Notices 331

NULL_RPT_FIELD 93

NUM_COLUMNS 68

NUM_ROWS 69

numeric comparison of strings 29, 53

O

operating system reference 318

OUT keyword 19, 40, 113

P

parameters, passing 23

passing groups of values 64

passing parameters, System language
environment 23

PASSWORD 94

performance, DTW_EXIT 124

Persistent macro functions

DTW_ACCEPT 299
DTW_COMMIT 301
DTW_ROLLBACK 302
DTW_RTVHANDLE 303
DTW_STATIC 304
DTW_TERMINATE 306

plan, connecting to DB2 subsystem 84

platform support reference 318

presentation part, macro 1

Previous button, RPT_MAX_ROWS 79

R

remote DB2 subsystem, location 91

REPORT block

ALIGN 75
description 47
DTW_DEFAULT_REPORT 76
DTW_HTML_TABLE 77
Nn 66
NLIST 67
NUM_COLUMNS 68

REPORT block (continued)

NUM_ROWS 69
RPT_MAX_ROWS 78
START_ROW_NUM 79
syntax 47
table variables 64
TOTAL_ROWS 71
report variables
ALIGN 75
description 74
DTW_DEFAULT_REPORT 76
DTW_HTML_TABLE 77
RPT_MAX_ROWS 78
START_ROW_NUM 79
reports
formatting 47
overriding Net.Data default 76
restricting database access 92, 94
RETURN_CODE 112
RETURNS keyword 20, 40
ROW block
description 49
Nn 66
NLIST 67
NUM_COLUMNS 68
NUM_ROWS 69
ROW_NUM 70
syntax 49
TOTAL_ROWS 71
V_columnName 72
Vn 73, 74
ROW_NUM 70
RPT_MAX_ROWS 78

S

scrolling, with Next and Previous
buttons 79

security

login ID 92
passwords 94

security recommendations,
FFI_PATH 248

sending e-mail from the macro 134

SHOWSQL 95

SQL

commands, specifying case 83
hiding or displaying 95

SQL block 317

SQL_CODE 318

SQL_MESSAGE block 318

SQL_REPORT block 318

SQL_STATE 96

SQL state, displaying 96

START_ROW_NUM 79

string functions

DTW_ASSIGN 168
DTW_CHARTOHEX 169
DTW_CONCAT 170
DTW_DELSTR 171
DTW_HEXTOCHAR
DTW_HEXTOCHAR 173
DTW_INSERT
DTW_INSERT 174
DTW_LASTPOS 176
DTW_LENGTH 178
DTW_LOWERCASE 179
DTW_POS 181

- string functions (*continued*)
 - DTW_REPLACE 183
 - DTW_REVERSE 185
 - DTW_STRIP 186
 - DTW_SUBSTR 188
 - DTW_TRANSLATE 190
 - DTW_UPPERCASE 192
 - MBCS support 166
- strings
 - conditional processing 29, 53
 - description 5
 - numeric comparisons 29, 53
 - of values, delimited 63
- subsystem ID, connecting to DB2
 - subsystem 85
- supported features table 318
- System language environment, passing
 - parameters 23

T

- table functions
 - DTW_TB_APPENDROW 205
 - DTW_TB_COLS 207
 - DTW_TB_DELETECOL 208
 - DTW_TB_DELETEROW 209
 - DTW_TB_DLIST 211
 - DTW_TB_DUMPH 213
 - DTW_TB_DUMPV 214
 - DTW_TB_GETN 216
 - DTW_TB_GETV 218
 - DTW_TB_HTMLENCODE 220
 - DTW_TB_INPUT_CHECKBOX 222
 - DTW_TB_INPUT_RADIO 224
 - DTW_TB_INPUT_TEXT 226
 - DTW_TB_INSERTCOL 228
 - DTW_TB_INSERTROW 229
 - DTW_TB_LIST 231
 - DTW_TB_QUERYCOLNONJ 233
 - DTW_TB_ROWS 235
 - DTW_TB_SELECT 236
 - DTW_TB_SETCOLS 238
 - DTW_TB_SETN 239
 - DTW_TB_SETV 241
 - DTW_TB_TABLE 243
 - DTW_TB_TEXTAREA 245
- table processing variables
 - description 65
 - Nn 66
 - NLIST 67
 - NUM_COLUMNS 68
 - NUM_ROWS 69
 - ROW_NUM 70
 - specifying for SQL language
 - environment 89
 - TOTAL_ROWS 71
 - V_columnName 72
 - Vn 74
 - VLIST 73
- TABLE statement 64
 - description 51
 - syntax 51
- table variables
 - description 64
 - example 65
- tables
 - Net.Data, specifying number of
 - rows 78

- tables (*continued*)
 - results in HTML 77
- TOTAL_ROWS 71
- TRANSACTION_SCOPE 97

U

- upper case, specifying 83
- upper limit 51
- UTF-8 format
 - date 122

V

- V_columnName 72
- variable name 4
- variable reference 4
- variables
 - conditional 60
 - environment 61
 - executable 61
 - hidden 62
 - language environment 80
 - list 63
 - miscellaneous 98
 - Net.Data, overview 59
 - report 74
 - table 64, 65
- VLIST 73
- Vn 74

W

- Web registry functions
 - DTWR_ADDENTRY 281
 - DTWR_CLEARREG 283
 - DTWR_CLOSEREG 284
 - DTWR_CREATEREG 285
 - DTWR_DELENTY 287
 - DTWR_DELREG 289
 - DTWR_LISTREG 290
 - DTWR_LISTSUB 292
 - DTWR_OPENREG 294
 - DTWR_RTVENTRY 295
 - DTWR_UPDATEENTRY 297
- WHILE block
 - description 53
 - syntax 53
- word functions
 - DTW_DELWORD 194
 - DTW_SUBWORD 196
 - DTW_WORD 198
 - DTW_WORDINDEX 199
 - DTW_WORDLENGTH 200
 - DTW_WORDPOS 201
 - DTW_WORDS 203
 - MBCS support 193

X

- XML block
 - description 56
 - syntax 56



Printed in the United States of America
on recycled paper containing 10%
recovered post-consumer fiber.